

**VA FileMan 22.2**  
**Developer's Guide**



**November 2017**

**Department of Veterans Affairs (VA)**  
**Office of Information and Technology (OIT)**  
**Enterprise Program Management Office (EPMO)**

## Revision History

Date	Revision	Description	Author
11/07/2017	1.8	Tech Edits: <ul style="list-style-type: none"> <li>• Updated all references throughout to Kernel manuals to the current, correct title:               <ul style="list-style-type: none"> <li>○ <i>Kernel 8.0 &amp; Kernel Toolkit 7.3 Systems Management Guide</i></li> <li>○ <i>Kernel 8.0 &amp; Kernel Toolkit 7.3 Developer's Guide</i></li> </ul> </li> <li>• Made format and content updates throughout this document related to HTML and Word document synchronization project.</li> </ul>	VA Technical Writer: T. B.
08/08/2017	1.7	Tech Edits: Updated Example 1 and Example 4 in Section <a href="#">3.5.15</a> , " <a href="#">\$\$GET1^DID(): Attribute Retriever</a> ," based on feedback from developer P. R.	Developer P. R. Technical Writer: T. B.
04/19/2017	1.6	Tech Edits: <ul style="list-style-type: none"> <li>• Updated the <a href="#">\$\$GET^DDSVAL()</a> API.</li> <li>• Updated the <a href="#">BUILDNEW^DIBTED(): Sort Template Builder</a> API.</li> </ul>	VA FileMan 23 Development Team
04/14/2017	1.5	Tech edits for patch DI*22.2*8, Data Access Control (DAC): <ul style="list-style-type: none"> <li>• Added the "<a href="#">Data Access Control (DAC) API</a>" section.</li> <li>• Reformatted Section III, "<a href="#">Other APIs</a>."</li> <li>• Added brackets around the optional input parameters in the formatted API as per documentation conventions for the <a href="#">CHANGED^DIAUTL(): Retrieve Audit Histor</a> API.</li> <li>• Reformatted display of file and field names throughout; moved file/field number immediately following the file/field name.</li> </ul>	Developer M. B. Technical Writer: T. B.
03/13/2017	1.4	Changes for patch DI*22.2*5: <ul style="list-style-type: none"> <li>• Removed incorrect 'entry' parameter from the Input Parameter List in Section <a href="#">7.2.3</a> - <a href="#">CHANGED^DIAUTL(): Historical Data Retriever</a>.</li> </ul>	Developer D. B. Technical Writer: T. K.
01/17/2017	1.3	Changes for patch DI*22.2*2: <ul style="list-style-type: none"> <li>• Added Section <a href="#">9</a>, "<a href="#">Coordinated Universal Time (UTC) API</a>."</li> <li>• Added Section <a href="#">14</a>, "<a href="#">Meta Data Dictionary</a>."</li> </ul>	Developer: D. B., A. C. Technical Writer: T. K.

Date	Revision	Description	Author
		<ul style="list-style-type: none"> <li>Added Sections <a href="#">20.8</a> – <a href="#">20.13</a> for new data types.</li> </ul>	
11/29/2016	1.2	Updates for patch DI*22.2*4: <ul style="list-style-type: none"> <li>Added NOTE in Section <a href="#">3.5.8</a> (FIND^DIC(): Finder) for the output of COMPUTED date fields.</li> <li>Added NOTE to Section <a href="#">2.3.46</a> to clarify syntax checking in ^DIR.</li> <li>Added NOTE to Section <a href="#">2.3.47</a> to document new functionality in ^DIR to exit after 50 failed reads.</li> <li>Updated Section <a href="#">2.3.46.1</a> to document the use of DIR("A",#), DIR("L",#) and DIR("?",#) variables.</li> </ul>	VA FileMan 23 Development Team Technical Writer: T. K.
08/05/2016	1.1	Tech Edits: <ul style="list-style-type: none"> <li>Updated the "<a href="#">Assigning a Location for Fields Stored within a Global</a>" section to expand capacity limit of global data storage capacity to 4094 characters.</li> <li>Removed all tables used for formatting (not data tables) for Section 508 conformance.</li> <li>Updated the "<a href="#">LANG^DIALOGZ(): File Modification for Multiple Languages</a>" section and <a href="#">Figure 321</a>, <a href="#">Figure 322</a>, and <a href="#">Figure 323</a>.</li> </ul>	Developer: R. D. Technical Writer: T. B.
08/03/2016	1.0	Initial release of VA FileMan 22.2 Developer's Guide.	VA FileMan 22.2 Development Team



**REF:** For the current patch history related to this software, see the Patch Module (i.e., Patch User Menu [A1AE USER]) on FORUM.

# Table of Contents

Revision History .....	ii
List of Figures .....	xiii
List of Tables .....	xxiii
Orientation .....	27
<b>1 Introduction.....</b>	<b>1</b>
1.1 What is VA FileMan? .....	1
1.2 Functional Description .....	1
1.3 Standalone VA FileMan .....	2
<b>I. Major APIs .....</b>	<b>4</b>
<b>2 Classic VA FileMan API.....</b>	<b>4</b>
2.1 Introduction .....	4
2.2 Classic Calls Cross-Referenced by Category.....	5
2.3 Classic Calls Presented in Alphabetical Order .....	8
2.3.1 Introduction to Date/Time Formats: %DT .....	8
2.3.2 X ^DD("DD"): Converts Internal to External Date Format.....	9
2.3.3 EN^DDIOL(): Message Loader .....	9
2.3.4 ^DIAC: File Access Determination .....	13
2.3.5 EN^DIB: User Controlled Editing .....	14
2.3.6 ^DIC: Lookup/Add with "B" Cross-References .....	14
2.3.7 IX^DIC: Lookup/Add Using User-Specified Cross-Reference .....	29
2.3.8 DO^DIC1: File Information Setup.....	31
2.3.9 MIX^DIC1: Lookup/Add Using User-Specified Set of Cross-References.....	32
2.3.10 WAIT^DICD: Wait Messages.....	35
2.3.11 FILE^DICN: Adds New Entry to File.....	35
2.3.12 YN^DICN: Reader for a Yes/No Response .....	37
2.3.13 DQ^DICQ: Entry Display for Lookups .....	38
2.3.14 DT^DICRW: FM Variable Setup.....	38
2.3.15 EN^DID: Print/Display Data Dictionary Listing .....	39
2.3.16 ^DIE: Data Input Edit of a File.....	39
2.3.17 ^DIEZ: INPUT Template Compile—User Interactive .....	49
2.3.18 EN^DIEZ: INPUT Template Compile—No User Interaction .....	50
2.3.19 ^DIK: Delete Entries .....	50
2.3.20 EN^DIK: Reindex Field Cross-References for One File Entry—KILL and SET Logic.....	52
2.3.21 EN1^DIK: Reindex Field Cross-References for One File Entry—SET Logic .....	54
2.3.22 EN2^DIK: Executes KILL Logic for One or More Field Cross-References for One File Entry .....	55
2.3.23 ENALL^DIK: Reindex All File Entries for Specific Field Cross-References—SET Logic.....	57

2.3.24	ENALL2^DIK: Executes KILL Logic for One or More Field Cross-References for All File Entries .....	58
2.3.25	IX^DIK: Reindex All File Cross-References for One File Entry—KILL and SET Logic.....	60
2.3.26	IX1^DIK: Reindex All File Cross-References for One File Entry—SET Logic .....	61
2.3.27	IX2^DIK: Executes KILL Logic of All Cross-References at File Level Specified .....	63
2.3.28	IXALL^DIK: Reindexes All Cross-References for All File Entries—SET Logic .....	64
2.3.29	IXALL2^DIK: Executes KILL Logic for All File Entries .....	65
2.3.30	^DIKZ: Compiles Cross-References into M Routines .....	67
2.3.31	EN^DIKZ: Recompiles a File's Cross-References—No User Intervention .....	67
2.3.32	\$\$ROUSIZE^DILF: Returns Maximum Routine Size.....	67
2.3.33	^DIM: Validates M Code .....	68
2.3.34	DT^DIO2: Writes External Date from Internal .....	68
2.3.35	^DIOZ: SORT Template Compile.....	68
2.3.36	EN1^DIP: Print Data .....	69
2.3.37	^DIPT: PRINT Template Display.....	84
2.3.38	DIBT^DIPT: SORT Template Display .....	84
2.3.39	^DIPZ: PRINT Template Compile for Code Generation—User Interactive.....	84
2.3.40	EN^DIPZ: PRINT Template Compile—No User Interaction .....	85
2.3.41	D^DIQ: Converts Internal Date to External Form .....	86
2.3.42	DT^DIQ: Converts Internal Date to External Form and Writes Date ..	86
2.3.43	EN^DIQ: Displays Captioned Range of Data .....	87
2.3.44	Y^DIQ: Converts Internal Data to External Form.....	87
2.3.45	EN^DIQ1: Data Retrieval .....	88
2.3.46	^DIR: Response Reader .....	91
2.3.47	EN^DIS: Searches File Entries .....	106
2.3.48	EN^DIU2: Delete Data Dictionary .....	107
2.3.49	EN^DIWE: Text Editing.....	108
2.3.50	^DIWF: Form Document Print.....	111
2.3.51	EN1^DIWF: Form Document Print with Known Document .....	112
2.3.52	EN2^DIWF: Form Document Print with Known Document and Entry.....	113
2.3.53	^DIWP: Formats and Outputs Text Lines.....	113
2.3.54	^DIWW: Output Remaining Text in ^UTILITY(\$J,“W”) by ^DIWP ....	115
2.3.55	^%DT: Validates Date/Time Input and Converts to Internal Format	115
2.3.56	DD^%DT: Converts Internal to External Date Format .....	119
2.3.57	^%DTC: Returns Number of Days between Two Dates .....	120
2.3.58	C^%DTC: Adds/Subtracts Days and Returns VA FileMan Date and \$H Format .....	120
2.3.59	COMMA^%DTC: Formats Number to String with Commas.....	121

2.3.60	DW^%DTC: Converts VA FileMan Date to \$H Format and Outputs Name of the Day .....	122
2.3.61	H^%DTC: Converts VA FileMan Date to \$H Format .....	122
2.3.62	HELP^%DTC: Display Help Prompt Based on Date .....	123
2.3.63	NOW^%DTC: Returns Current Date/Time in VA FileMan and \$H Formats .....	123
2.3.64	S^%DTC: Converts Time into Decimal Part of VA FileMan Internal Date .....	123
2.3.65	YMD^%DTC: Converts \$H to VA FileMan Format .....	124
2.3.66	YX^%DTC: Returns Printable and VA FileMan Internal Formats from \$H .....	124
2.3.67	%XY^%RCR: Moves Arrays between Locations .....	125
<b>3</b>	<b>Database Server (DBS) API .....</b>	<b>126</b>
3.1	Introduction .....	126
3.2	How to Use DBS Calls .....	126
3.2.1	Format and Conventions of the Calls .....	126
3.2.2	IENS: Identify Entries and Subentries .....	127
3.2.3	FDA: Format of Data Passed to and from VA FileMan .....	128
3.2.4	Documentation Conventions .....	129
3.3	How the Database Server (DBS) Communicates .....	129
3.3.1	Overview .....	130
3.3.2	How Information Is Returned .....	130
3.3.3	Contents of Arrays .....	131
3.3.4	Obtaining Formatted Text from the Arrays .....	134
3.3.5	Cleaning Up the Output Arrays .....	135
3.3.6	Example of Call to VA FileMan DBS .....	135
3.4	Database Server Calls Cross-Referenced by Category .....	137
3.5	Database Server (DBS) Calls Presented in Alphabetical Order) .....	139
3.5.1	CREIXN^DDMOD(): New-Style Cross-Reference Creator .....	139
3.5.2	DELIX^DDMOD(): Traditional Cross-reference Delete .....	150
3.5.3	DELIXN^DDMOD(): New-Style Index Delete .....	153
3.5.4	FILESEC^DDMOD(): Set File Protection Security Codes .....	156
3.5.5	BLD^DIALOG(): DIALOG Extractor .....	158
3.5.6	\$\$EZBLD^DIALOG(): DIALOG Extractor (Single Line) .....	164
3.5.7	MSG^DIALOG(): Output Generator .....	165
3.5.8	FIND^DIC(): Finder .....	169
3.5.9	\$\$FIND1^DIC(): Finder (Single Record) .....	191
3.5.10	LIST^DIC(): Lister .....	203
3.5.11	FIELD^DID(): DD Field Retriever .....	222
3.5.12	FIELDLST^DID(): DD Field List Retriever .....	224
3.5.13	FILE^DID(): DD File Retriever .....	225
3.5.14	FILELST^DID(): DD File List Retriever .....	227
3.5.15	\$\$GET1^DID(): Attribute Retriever .....	228
3.5.16	CHK^DIE(): Data Checker .....	230

3.5.17	FILE^DIE(): Filer .....	231
3.5.18	HELP^DIE(): Helper.....	235
3.5.19	\$\$KEYVAL^DIE(): Key Validator.....	237
3.5.20	UPDATE^DIE(): Updater .....	240
3.5.21	VAL^DIE(): Validator.....	248
3.5.22	VALS^DIE(): Fields Validator.....	252
3.5.23	WP^DIE(): Word-processing Filer .....	256
3.5.24	CLEAN^DILF: Array and Variable Clean-up.....	258
3.5.25	\$\$CREF^DILF(): Root Converter (Open to Closed Format) .....	258
3.5.26	DA^DILF(): Convert IENS to DA() Array Structure .....	259
3.5.27	DT^DILF(): Date Converter.....	260
3.5.28	FDA^DILF(): FDA Loader .....	262
3.5.29	\$\$HTML^DILF(): HTML Encoder/Decoder.....	264
3.5.30	\$\$IENS^DILF(): Return IENS from a DA() Array Structure.....	265
3.5.31	LOCK^DILF(): Lock Global Reference .....	265
3.5.32	\$\$OREF^DILF(): Root Converter (Closed to Open Format).....	266
3.5.33	\$\$VALUE1^DILF(): FDA Value Retriever (Single).....	266
3.5.34	VALUES^DILF(): FDA Values Retriever .....	267
3.5.35	\$\$EXTERNAL^DILFD(): Converts Internal Value to External Format.....	268
3.5.36	\$\$FLDNUM^DILFD(): Field Number Retriever .....	273
3.5.37	PRD^DILFD(): Package Revision Data Initializer .....	274
3.5.38	RECALL^DILFD(): Recall Record Number.....	275
3.5.39	\$\$ROOT^DILFD(): File Root Resolver.....	276
3.5.40	\$\$VFIELD^DILFD(): Field Verifier .....	277
3.5.41	\$\$VFILE^DILFD(): File Verifier .....	278
3.5.42	\$\$GET1^DIQ(): Data Retriever (Single Field) .....	279
3.5.43	GETS^DIQ(): Data Retriever (Multiple Fields).....	282

**II. ScreenMan.....287**

<b>4</b>	<b>ScreenMan Forms.....</b>	<b>287</b>
4.1	Introduction .....	287
4.2	Form Layout: Forms and Pages.....	287
4.2.1	Form Structure.....	287
4.2.2	Linking Pages of a Form.....	288
4.3	Features .....	290
4.3.1	Displaying Multiples in Repeating Blocks.....	290
4.3.2	Form-Only Fields .....	291
4.3.3	Relational Navigation: Forward Pointers.....	293
4.3.4	Relational Navigation: Backward Pointers .....	296
4.3.5	Computed Fields .....	296
4.3.6	DDSBK Variable.....	299
4.3.7	DDSSTACK Variable .....	300
4.3.8	Data Filing (When Is It Performed?).....	300
4.3.9	Word Processing Field Data Indication .....	301

4.4	Form Property Reference.....	301
4.4.1	Form Properties.....	301
4.4.2	Page Properties.....	302
4.4.3	Block Properties .....	304
4.4.4	Field Properties .....	306
4.5	ScreenMan Menu Options .....	311
4.5.1	Edit/Create a Form .....	311
4.5.2	Run a Form .....	311
4.5.3	Delete a Form.....	312
4.5.4	Purge Unused Blocks .....	313
4.6	Callable Routines.....	314
4.7	Programmer Mode Utilities.....	314
4.7.1	^DDGF: Invoke the Form Editor from Programmer Mode .....	314
4.7.2	CLONE^DDS: Make a Copy of a Form .....	315
4.7.3	PRINT^DDS: Print a Form .....	317
4.7.4	RESET^DDS: Reset Terminal, Variables, and Remove Temp Data .....	318
<b>5</b>	<b>ScreenMan Form Editor .....</b>	<b>319</b>
5.1	Introduction .....	319
5.2	Invoking the Form Editor.....	319
5.3	Command Summary .....	320
5.3.1	Navigating on the Main Screen and Block Viewer Screen .....	321
5.3.2	Quick Page Navigation .....	321
5.3.3	Moving Screen Elements.....	322
5.3.4	Adding, Selecting, and Editing .....	322
5.4	Form Editor's Main Screen.....	323
5.4.1	Exiting, Quitting, Saving, and Obtaining Help .....	324
5.5	Block Viewer Screen.....	324
5.6	Navigating on the Form Editor Screens.....	325
5.7	Going to Another Page .....	325
5.8	Adding Pages, Blocks, and Fields.....	326
5.8.1	Adding Pages (<PF2>P).....	326
5.8.2	Adding Blocks <PF2>B.....	327
5.8.3	Adding Fields <PF2>F .....	327
5.9	Selecting and Moving Screen Elements.....	328
5.9.1	Selecting Screen Elements.....	328
5.9.2	Moving Screen Elements.....	328
5.10	Editing Properties.....	329
5.10.1	Editing Field Properties.....	329
5.10.2	Editing Block Properties.....	331
5.10.3	Editing Page Properties .....	333
5.10.4	Editing Form Properties .....	335
5.11	Choosing Another Form .....	335
5.12	Deleting Screen Elements (Fields, Blocks, Pages, and Forms).....	336



5.12.1	Deleting Fields.....	336
5.12.2	Deleting Blocks.....	336
5.12.3	Deleting Pages.....	336
5.12.4	Deleting Forms.....	337
<b>6</b>	<b>ScreenMan API .....</b>	<b>338</b>
6.1	Introduction.....	338
6.2	^DDS: Invoke ScreenMan.....	338
6.2.1	DDS Variable.....	339
6.2.2	Examples.....	339
6.2.3	Error Codes Returned.....	340
6.3	\$\$GET^DDSVAl(): Retrieve Data from a Data Dictionary Field.....	341
6.3.1	Examples.....	342
6.4	PUT^DDSVAl(): Stuff Data into a Data Dictionary Field .....	342
6.4.1	Examples.....	344
6.5	\$\$GET^DDSVAlF(): Retrieve Data from a Form-only Field .....	345
6.5.1	Examples.....	345
6.6	PUT^DDSVAlF(): Stuff Data into a Form-only Field .....	346
6.6.1	Example .....	347
6.7	HLP^DDSUTL(): Print Help Messages in the Command Area.....	347
6.8	MSG^DDSUTL(): Print Data Validation Messages on a Separate Screen....	347
6.9	REFRESH^DDSUTL: Refresh Screen .....	348
6.10	REQ^DDSUTL(): Change Required Property of a Field on a Form .....	348
6.11	UNED^DDSUTL(): Change Disable Editing Property of a Field on a Form...	349
<b>III.</b>	<b>Other APIs .....</b>	<b>350</b>
<b>7</b>	<b>Auditing API.....</b>	<b>350</b>
7.1	Introduction.....	350
7.2	Application Programming Interfaces (APIs).....	350
7.2.1	TURNON^DIAUTL(): Enable/Disable Auditing.....	350
7.2.2	LAST^DIAUTL(): Retrieve Last Person Who Changed Data.....	351
7.2.3	CHANGED^DIAUTL(): Retrieve Audit History.....	352
<b>8</b>	<b>Browser API.....</b>	<b>354</b>
8.1	Browser (DDBR) Introduction.....	354
8.2	Application Programming Interfaces (APIs).....	354
8.2.1	EN^DDBR: Display Word-Processing Fields in Browser .....	354
8.2.2	BROWSE^DDBR(): View and Navigate a Document in an Array Using the Browser.....	355
8.2.3	WP^DDBR(): Display Word-Processing Field Using the Browser ...	358
8.2.4	DOCLIST^DDBR(): View and Navigate Multiple Documents in an Array Using the Browser.....	361
8.2.5	\$\$TEST^DDBRT: Verify Monitor Supports Browser.....	363
8.2.6	CLOSE^DDBRZIS: Rewind File and Copy Text to Global.....	364
8.2.7	OPEN^DDBRZIS: Capture Text in Browser Title .....	364
8.2.8	POST^DDBRZIS: Initialize Browser to Display Text .....	365
<b>9</b>	<b>Coordinated Universal Time (UTC) API.....</b>	<b>366</b>

9.1	Introduction .....	366
9.2	Application Programming Interfaces (APIs).....	366
9.2.1	\$\$UTC^DIUTC(): Return GMT in VA FileMan Internal Format with Time Zone Offset.....	366
<b>10</b>	<b>Data Access Control (DAC) API.....</b>	<b>370</b>
10.1	Introduction .....	370
10.2	Application Programming Interface (API) .....	370
10.2.1	\$\$CANDO^DIAC1(): Policy Evaluation .....	370
<b>11</b>	<b>Import and Export Tools .....</b>	<b>373</b>
11.1	Introduction .....	373
11.2	Application Programming Interfaces (APIs).....	373
11.2.1	FILE^DDMP(): Data Import.....	373
11.2.2	EXPORT^DDXP(): Data Export .....	379
<b>12</b>	<b>Extract Tool.....</b>	<b>385</b>
12.1	Introduction .....	385
12.2	Application Programming Interfaces (APIs).....	385
12.2.1	EN^DIAXU: Extract Data (Single Entry) .....	385
12.2.2	EXTRACT^DIAXU(): Extract Data (Multiple Entries) .....	387
<b>13</b>	<b>Filegrams API.....</b>	<b>394</b>
13.1	Introduction .....	394
13.2	Application Programming Interfaces (APIs).....	394
13.2.1	^DIFG: Filegram Installer .....	394
13.2.2	EN^DIFGG: Filegram Generator .....	396
<b>14</b>	<b>Meta Data Dictionary .....</b>	<b>398</b>
14.1	Introduction .....	398
14.2	Application Programming Interfaces (APIs).....	398
14.2.1	^DDD: Initial Creation .....	398
14.2.2	FILELIST^DDD: File List Partial Update .....	399
14.2.3	PARTIAL1^DDD: Partial Update using ^DIC(DDD,“%MSC”) .....	399
14.2.4	PARTIAL2^DDD: Partial Update using ^DD(FILE,FIELD,“DT”) .....	400
<b>15</b>	<b>Create Sort Templates Silently API .....</b>	<b>401</b>
15.1	BUILDNEW^DIBTED(): Sort Template Builder.....	401
<b>IV.</b>	<b>Developer Tools.....</b>	<b>403</b>
<b>16</b>	<b>^DI: Programmer Access .....</b>	<b>403</b>
<b>17</b>	<b>^DIKCBLD: Build an M Routine that Makes a Call to CREIXN^DDMOD.....</b>	<b>404</b>
17.1	Details.....	404
17.2	Example.....	405
<b>18</b>	<b>LANG^DIALOGZ(): File Modification for Multiple Languages .....</b>	<b>406</b>
<b>19</b>	<b>Global File Structure .....</b>	<b>411</b>
19.1	Introduction .....	411
19.2	Data Storage Conventions .....	411
19.3	File’s Entry in the Dictionary of Files .....	412
19.4	File Header .....	412
19.5	File Entries (Data Storage).....	413

19.6	Cross-References .....	415
19.7	INDEX File .....	415
19.8	KEY File.....	416
19.9	Attribute Dictionary: ^DD(Filenumber .....	416
19.9.1	File Characteristics Nodes .....	417
19.9.2	Field Definition 0-Node .....	420
19.9.3	Other Field Definition Nodes.....	423
19.9.4	Reading the Attribute Dictionary—Example .....	426
<b>20</b>	<b>Advanced File Definition .....</b>	<b>428</b>
20.1	Introduction .....	428
20.2	File Global Storage .....	428
20.2.1	Storing Data in a Global other than ^DIZ .....	428
20.3	Field Global Storage .....	429
20.3.1	Assigning a Location for Fields Stored within a Global.....	429
20.3.2	Storing Data by Position within a Node .....	430
20.4	Assigning Sub-Dictionary Numbers.....	430
20.5	Computed Expressions .....	431
20.5.1	Computed Dates.....	431
20.5.2	Computed Pointers.....	431
20.5.3	Computed Multiples .....	432
20.6	MUMPS Data Type .....	433
20.7	Screened Pointers and Set of Codes .....	433
20.8	LABEL REFERENCE Data Type .....	434
20.9	TIME Data Type.....	434
20.10	YEAR Data Type.....	434
20.11	FT POINTER Data Type .....	434
20.12	FT DATE Data Type .....	435
20.13	RATIO Data Type .....	435
20.14	INPUT Transform.....	435
20.14.1	INPUT Transforms and the Verify Fields Option .....	438
20.15	OUTPUT Transform.....	438
20.16	Special Lookup Programs .....	439
20.17	Post-Selection Action.....	439
20.18	Audit Condition .....	440
20.19	Editing a Cross-Reference .....	440
20.20	Executable Help.....	441
<b>21</b>	<b>Trigger Cross-References .....</b>	<b>442</b>
21.1	Introduction .....	442
21.2	Trigger on the Same File.....	443
21.3	Triggers for Different Files.....	445
<b>22</b>	<b>DIALOG File .....</b>	<b>447</b>
22.1	DIALOG File: User Messages .....	447
22.1.1	Introduction.....	447
22.1.2	Use of the DIALOG File .....	447

22.1.3	Creating DIALOG File Entries.....	448
22.2	Internationalization and the DIALOG File .....	449
22.2.1	Role of the VA FileMan DIALOG File in Internationalization.....	449
22.2.2	Use of the DIALOG File in Internationalization.....	449
22.2.3	Creating Non-English Text in the DIALOG File .....	450
22.3	VA FileMan LANGUAGE File .....	451
22.3.1	Introduction.....	451
22.3.2	Use of the LANGUAGE File.....	451
22.3.3	Creating LANGUAGE File Entries.....	452
<b>23</b>	<b>VA FileMan Functions (Creating).....</b>	<b>454</b>
23.1	Introduction .....	454
23.2	Function File Entries .....	454
<b>24</b>	<b>DIFROM .....</b>	<b>456</b>
24.1	Introduction .....	456
24.2	Exporting Data .....	456
24.2.1	Preparing To Run DIFROM .....	456
24.2.2	PACKAGE File and DIFROM.....	457
24.3	Order Entry and DIFROM .....	462
24.4	Running DIFROM (Steps 1-17).....	463
24.4.1	Starting DIFROM.....	463
24.4.2	Preliminary Validations .....	463
24.4.3	Package Identification.....	464
24.4.4	Identifying Init Routines .....	464
24.4.5	Specifications for Exported Files.....	464
24.4.6	Entering Current Version Information.....	465
24.4.7	Including Templates (No Package File Entry) .....	465
24.4.8	Including Other Package Components .....	465
24.4.9	Exporting File Security.....	466
24.4.10	Specifying Routine Size.....	466
24.4.11	DIFROM Gathers Miscellaneous Package Components.....	466
24.4.12	DIFROM Builds Routines Containing Data Dictionaries .....	466
24.4.13	DIFROM Builds Routines Containing Data Values.....	467
24.4.14	DIFROM Builds Routines Containing Security Access Codes.....	467
24.4.15	DIFROM Gathers Templates and Forms .....	468
24.4.16	DIFROM Completes Building Routines of Package Components ...	468
24.4.17	DIFROM Completes the Code that Runs the Init .....	468
24.5	Importing Data .....	469
24.6	DIFROM: Running an INIT (Steps 1-16) .....	469
24.6.1	Preliminary Steps .....	469
24.6.2	Check of Version Number.....	470
24.6.3	Running Environment Check Routine (DIFROM and DIFQ Variables).....	470
24.6.4	Determining Install Status of DDs and Data.....	470
24.6.5	Determining Install Status of Security Codes.....	472

24.6.6	Determining Install Status of other Package Components .....	472
24.6.7	Starting the Update.....	472
24.6.8	Running the Pre-Init after User Commit Routine .....	472
24.6.9	Installing Data Dictionaries .....	473
24.6.10	Installing Data.....	473
24.6.11	Reindexing Files .....	474
24.6.12	Installing Other Package Components.....	474
24.6.13	General Processing .....	475
24.6.14	Special Processing .....	476
24.6.15	Running the Post-Initialization Routine .....	477
24.6.16	Recording the Install on the Target System .....	477
<b>25</b>	<b>Appendix A—VA FileMan Error Codes.....</b>	<b>479</b>
25.1	Introduction .....	479
25.2	Error Codes .....	479
	Glossary .....	506
	Index .....	514

## List of Figures

Figure 1:	Type of M System Prompt.....	xxxii
Figure 2:	X ^DD(“DD”) API—Example.....	9
Figure 3:	EN^DDIOL API—Sample .array Input Parameter Array Name .....	10
Figure 4:	EN^DDIOL API—Sample global_root Input Parameter (1 of 2) .....	10
Figure 5:	EN^DDIOL API—Sample global_root Input Parameter (2 of 2) .....	10
Figure 6:	EN^DDIOL—Example: Write Identifier Node.....	11
Figure 7:	EN^DDIOL—Example: Write Identifier Node Converted.....	11
Figure 8:	EN^DDIOL—Example: Input .....	11
Figure 9:	EN^DDIOL—Example: Output in Scroll Mode .....	11
Figure 10:	EN^DDIOL—Example: Output in DBS Mode.....	12
Figure 11:	EN^DDIOL—Example: Input Passing a Text Array.....	12
Figure 12:	EN^DDIOL—Example: Input Passing a Global Containing Text.....	12
Figure 13:	EN^DDIOL—Sample Formatting for Arrays.....	13
Figure 14:	^DIC—Sample Code to: Use ^DIC to Interactively Select a Top-level Record, Create a Subentry; and Use ^DIE to Edit Fields in the Subentry .....	27
Figure 15:	^DIC—Sample Code to Display a List of Entries from two Different Files Starting with Different Letters (1 of 2) .....	27
Figure 16:	^DIC—Sample Code to Display a List of Entries from two Different Files Starting with Different Letters (2 of 2) .....	28
Figure 17:	^DIC—Example: Input to Display Entries from the Pointing File Using the “AC” Index.....	28
Figure 18:	^DIC—Example: Output Prompts .....	29
Figure 19:	WAIT^DICD API—Sample VA FileMan Informational Messages: “Wait” Type Messages.....	35
Figure 20:	^DIE API—Sample Code Using Incremental Locks.....	44

Figure 21: ^DIE API—Sample Code to Calculate Y Based on X .....	45
Figure 22: ^DIE API—Prompting User for Specific Fields in Multiples .....	46
Figure 23: ^DIE API—Editing a Subfile Directly.....	46
Figure 24: ^DIE API—Sample INPUT Template.....	47
Figure 25: ^DIE API—Sample Array when DIEFIRE Contains an L and a Key is Invalid.....	48
Figure 26: ^DIE API—Sample Code Setting the Variable X to the String “BADKEY”, if Any of the Keys is Invalid .....	49
Figure 27: ^DIK API—Sample Code Looping to Delete Several Entries .....	51
Figure 28: ^DIK API—Sample Code Deleting <i>Single-valued Fields</i> from a File .....	52
Figure 29: ^DIK API—Sample Code Deleting a <i>Multiple Sub-field</i> from a File.....	52
Figure 30: IXALL^DIK API—Example 1: Input.....	65
Figure 31: IXALL^DIK API—Example 2: Input.....	65
Figure 32: \$\$ROUSIZE^DILF API—Example: Input and Output.....	67
Figure 33: DT^DIO2 API—Example: Input and Output.....	68
Figure 34: EN1^DIP API—Example 1: Cross-Reference.....	80
Figure 35: EN1^DIP API—Example 1: Setting Up Variables .....	80
Figure 36: EN1^DIP API—Example 2: Sample Record Numbers.....	80
Figure 37: EN1^DIP API—Example 2: Input to Sort and Print Records .....	80
Figure 38: EN1^DIP API—Example 3: Cross-Reference.....	80
Figure 39: EN1^DIP API—Example 3: Input Setting Variables to Sort and Print .....	81
Figure 40: EN1^DIP API—Sort BY(0) Example .....	82
Figure 41: Example of How to Call EN1^DIP when the BY(0) Information is Contained in a Template .....	83
Figure 42: EN^DIQ1 API—Data Retrieval: DIQ and DIQ(0) Undefined.....	90
Figure 43: EN^DIQ1 API—Data Retrieval: DIQ(0) Defined, DIQ Undefined .....	90
Figure 44: EN^DIQ1 API—Data Retrieval: DIQ Defined.....	90
Figure 45: EN^DIQ1 API—Data Retrieval: DIQ Defined: Output .....	90
Figure 46: EN^DIQ1 API—Data Retrieval: Word-Processing Field.....	91
Figure 47: EN^DIQ1 API—Data Retrieval: Word-Processing Field: DIQ is Defined.....	91
Figure 48: ^DIR API—Date Example.....	101
Figure 49: ^DIR API—End-of-Page Example: Input .....	102
Figure 50: ^DIR API—End-of-Page Example: Prompt Displayed .....	102
Figure 51: ^DIR API—Free-Text Example: Input.....	102
Figure 52: ^DIR API—With DIR(0) Containing U Example: Input .....	102
Figure 53: ^DIR API—With DIR(0) Containing A Example: Input.....	102
Figure 54: ^DIR API—With DIR(0) Containing A Example: Prompt Displayed.....	102
Figure 55: ^DIR API—List or Range Example: Input .....	102
Figure 56: ^DIR API—List or Range Example: Acceptable Responses .....	103
Figure 57: ^DIR API—With DIR(0) Containing C Example: Input and Output.....	103
Figure 58: ^DIR API—Numeric Example: Input .....	103
Figure 59: ^DIR API—With DIR(0) Containing O Example: Input .....	103
Figure 60: ^DIR: Reader—With DIR(0) Containing O Example: Prompt Displayed .....	103
Figure 61: ^DIR API—Pointer Example: Input .....	104
Figure 62: ^DIR API—Pointer Example: Subfile Lookup.....	104

Figure 63: ^DIR API—Set Example: Input.....	104
Figure 64: ^DIR API—Set Example: Input and Prompt Displayed .....	104
Figure 65: ^DIR API—With DIR(0) Containing A Example: Input.....	104
Figure 66: ^DIR API—With DIR(0) Containing A Example: Prompt Displayed.....	104
Figure 67: ^DIR API—With DIR(0) Containing B Example: Input.....	105
Figure 68: ^DIR API—With DIR(0) Containing B Example: Prompt Displayed.....	105
Figure 69: ^DIR API—With DIR(0) Containing X Example: Input.....	105
Figure 70: ^DIR API—With DIR(0) Containing X Example: Prompt Displayed.....	105
Figure 71: ^DIR API—Yes/No Example: Input.....	105
Figure 72: ^DIR API—DD Example: Input Format 1 .....	105
Figure 73: ^DIR API—DD Example: Input Format 2 .....	106
Figure 74: EN^DIS API—Sort Template.....	106
Figure 75: EN^DIU2 API—Example: Input .....	107
Figure 76: EN^DIU2 API—Example: Input for Subfile Deletion.....	108
Figure 77: ^DIWF API—Example: Word-Processing Type Field.....	111
Figure 78: EN1^DIWF API—Example: Input .....	112
Figure 79: DD^%DT API—Example: Input and Output.....	120
Figure 80: COMMA^%DTC API—Example 1: Input .....	121
Figure 81: COMMA^%DTC API—Example 1: Output.....	121
Figure 82: COMMA^%DTC API—Example 2: Input .....	121
Figure 83: COMMA^%DTC API—Example 2: Output.....	121
Figure 84: COMMA^%DTC API—Example 3: Input .....	122
Figure 85: COMMA^%DTC API—Example 3: Output.....	122
Figure 86: COMMA^%DTC API—Example 4: Input .....	122
Figure 87: COMMA^%DTC API—Example 4: Output.....	122
Figure 88: S^%DTC API—Example: Input and Output.....	124
Figure 89: %XY^%RCR API—Example: Input.....	125
Figure 90: Database Server (DBS) API—Format and Conventions of the Calls: Order of the Parameters in the Argument List.....	126
Figure 91: Database Server (DBS) API—Documentation Conventions: Passing by Reference Only .....	129
Figure 92: Database Server (DBS) API—Documentation Conventions: Passing by Reference or by Value.....	129
Figure 93: Database Server (DBS) API—How Information Is Returned: Arrays .....	130
Figure 94: Database Server (DBS) API—How Information Is Returned: Passing Parameters: Input.....	130
Figure 95: Database Server (DBS) API—How Information Is Returned: Passing Parameters: Output .....	131
Figure 96: Database Server (DBS) API—DIHELP Array: Input to Return Help for a Particular Field .....	131
Figure 97: Database Server (DBS) API—DIMSG Array: Sample Input Transform.....	132
Figure 98: Database Server (DBS) API—DIMSG Array: Changing Input Transform: Executed in Scrolling Mode .....	132
Figure 99: Database Server (DBS) API—DIMSG Array: Changing Input Transform: Executed from a Silent Call.....	132

Figure 100: Database Server (DBS) API—DIERR Array: Sample Input and Output.....	133
Figure 101: Database Server (DBS) API—Obtaining Formatted Text from the Arrays: Input...	134
Figure 102: Database Server (DBS) API—Cleaning Up the Output Arrays: Input.....	135
Figure 103: Database Server (DBS) API—Example of Call to VA FileMan DBS: Input.....	135
Figure 104: Database Server (DBS) API—Example of Call to VA FileMan DBS: Sample Array Output .....	136
Figure 105: CREIXN^DDMOD API—Example 1: Test Routine.....	145
Figure 106: CREIXN^DDMOD API—Example 1: Input and Output .....	145
Figure 107: CREIXN^DDMOD API—Example 1: Sample Data Dictionary Listing of the Created Index .....	146
Figure 108: CREIXN^DDMOD API—Example 2: Test Routine.....	147
Figure 109: CREIXN^DDMOD API—Example 2: Input and Output .....	147
Figure 110: CREIXN^DDMOD API—Example 2: Sample Data Dictionary Listing of the Created Index .....	148
Figure 111: CREIXN^DDMOD API—Example 3: Test Routine.....	148
Figure 112: CREIXN^DDMOD API—Example 3: Input and Output .....	149
Figure 113: CREIXN^DDMOD API—Example 3: Sample Data Dictionary Listing of the Created Index .....	149
Figure 114: DELIX^DDMOD API—Example 1: Input and Output .....	151
Figure 115: DELIX^DDMOD API—Example 2: Input and Output .....	152
Figure 116: DELIXN^DDMOD API—Example 1: Input and Output.....	154
Figure 117: DELIXN^DDMOD API—Example 2: Input and Output.....	155
Figure 118: FILESEC^DDMOD API—Example 1: Input and Output.....	157
Figure 119: FILESEC^DDMOD API—Example 2: Input and Output.....	157
Figure 120: BLD^DIALOG API—Example 1: Input .....	160
Figure 121: BLD^DIALOG API—Example 1: Output .....	160
Figure 122: BLD^DIALOG API—Example 2: Input .....	161
Figure 123: BLD^DIALOG API—Example 2: Output .....	161
Figure 124: BLD^DIALOG API—Example 3: Input .....	161
Figure 125: BLD^DIALOG API—Example 3: Output .....	161
Figure 126; BLD^DIALOG API—Example 4: Input .....	162
Figure 127: BLD^DIALOG API—Example 4: Output .....	162
Figure 128: BLD^DIALOG API—Example 5: Input .....	162
Figure 129: BLD^DIALOG API—Example 5: Output .....	162
Figure 130: BLD^DIALOG API—Example 6: Input .....	163
Figure 131: BLD^DIALOG API—Example 6: Output .....	163
Figure 132: BLD^DIALOG API—Example 7: Input .....	163
Figure 133: BLD^DIALOG API—Example 7: Output .....	163
Figure 134: \$\$EZBLD^DIALOG API—Example 1: Input and Output .....	164
Figure 135: \$\$EZBLD^DIALOG API—Example 2: Input and Output .....	164
Figure 136: \$\$EZBLD^DIALOG API—Example 3: Input and Output .....	165
Figure 137: MSG^DIALOG API—Example 1: “DIERR” Portion of the ^TMP Global .....	167
Figure 138: MSG^DIALOG API—Example 1: Input and Output.....	167
Figure 139: MSG^DIALOG API—Example 2: Input.....	167



Figure 140: MSG^DIALOG API—Example 2: Output .....	168
Figure 141: MSG^DIALOG API—Example 3: Sample Local Array with Help Text Returned ...	168
Figure 142: MSG^DIALOG API—Example 3: Input .....	168
Figure 143: FIND^DIC API—Example 1: Input and Output.....	183
Figure 144: FIND^DIC API—Example 2: Input and Output.....	183
Figure 145: FIND^DIC API—Example 3: Input and Output.....	184
Figure 146: FIND^DIC API—Example 4: Input and Output.....	184
Figure 147: FIND^DIC API—Example 5: Input and Output.....	185
Figure 148: FIND^DIC API—Example 5: Input with “B” Flag and Output.....	185
Figure 149: FIND^DIC API—Example 6: Input with “T” Lookup Value and Output .....	186
Figure 150: FIND^DIC API—Example 6: Input with “B” and “BS5” Lookup Values and Output .....	186
Figure 151: \$\$FIND1^DIC API—Example 1: Input and Output.....	198
Figure 152: \$\$FIND1^DIC API—Example 2: Input and Output.....	198
Figure 153: \$\$FIND1^DIC API—Example 3: Input and Output.....	198
Figure 154: \$\$FIND1^DIC API—Example 4: Input and Output: Failure .....	199
Figure 155: \$\$FIND1^DIC API—Example 1: Input and Output: Success .....	199
Figure 156: LIST^DIC API—Example 1: Input and Output .....	217
Figure 157: LIST^DIC API—Example 2: Input and Output .....	217
Figure 158: LIST^DIC API—Example 3: Input and Output .....	218
Figure 159: LIST^DIC API—Example 4: Input and Output .....	219
Figure 160: LIST^DIC API—Example 5: Input and Output .....	220
Figure 161: FIELD^DID API—Example: Input and Output.....	223
Figure 162: FIELDLST^DID API—Example: Input and Output .....	224
Figure 163: FILE^DID API—Example: Input and Output .....	226
Figure 164: FILELST^DID API—Example: Input and Output.....	227
Figure 165: \$\$GET1^DID API—Example 1: Input and Output.....	229
Figure 166: \$\$GET1^DID API—Example 2: Input and Output.....	229
Figure 167: \$\$GET1^DID API—Example 3: Input and Output.....	229
Figure 168: \$\$GET1^DID API—Example 4: Input and Output.....	229
Figure 169: CHK^DIE API—Example: Input and Output.....	231
Figure 170: HELP^DIE API—Example: Input and Output.....	236
Figure 171: \$\$KEYVAL^DIE API—Example: Input and Output .....	238
Figure 172: UPDATE^DIE API—Example 1: Input and Output.....	243
Figure 173: UPDATE^DIE API—Example 2: Input and Output.....	243
Figure 174: UPDATE^DIE API—Example 3: Input and Output.....	244
Figure 175: VAL^DIE API—Example: Input and Output .....	249
Figure 176: VALS^DIE API—Example 1: Input and Output .....	253
Figure 177: VALS^DIE API—Example 2: Input and Output .....	254
Figure 178: VALS^DIE API—Example 3: Input and Output .....	255
Figure 179: WP^DIE API—Example: Input.....	257
Figure 180: WP^DIE API—Example: Word-Processing Text Location 1 .....	257
Figure 181: WP^DIE API—Example: Word-Processing Text Location 2 .....	257
Figure 182: \$\$CREF^DILF API—Example: Input and Output.....	259

Figure 183: DA^DILF API—Example: Input and Output .....	259
Figure 184: DT^DILF API—Example 1: Input and Output.....	261
Figure 185: DT^DILF API—Example 2: Input and Output.....	261
Figure 186: FDA^DILF API—Node Format.....	263
Figure 187: FDA^DILF API—Example: Input and Output .....	263
Figure 188: \$\$IENS^DILF API—Example: Input and Output .....	265
Figure 189: LOCK^DILF API—Example: Input and Output.....	266
Figure 190: \$\$OREF^DILF API—Example: Input and Output .....	266
Figure 191: \$\$VALUE1^DILF API—Example: Input and Output.....	267
Figure 192: VALUES^DILF API—Example: Input and Output .....	268
Figure 193: \$\$EXTERNAL^DILFD API—Example 1: Input and Output .....	270
Figure 194: \$\$EXTERNAL^DILFD API—Example 2: Input and Output .....	270
Figure 195: \$\$EXTERNAL^DILFD API—Example 3: Input and Output .....	270
Figure 196: \$\$EXTERNAL^DILFD API—Example 4: Input and Output .....	270
Figure 197: \$\$EXTERNAL^DILFD API—Example 5: Input and Output .....	270
Figure 198: \$\$EXTERNAL^DILFD API—Example 6: Input and Output .....	270
Figure 199: \$\$EXTERNAL^DILFD API—Example 7: Input and Output .....	271
Figure 200: \$\$EXTERNAL^DILFD API—Example 8: Input and Output .....	271
Figure 201: \$\$FLDNUM^DILFD API—Example: Input and Output .....	273
Figure 202: PRD^DILFD API—Example: Input and Output .....	274
Figure 203: RECALL^DILFD API—Example: Input and Output.....	275
Figure 204: \$\$ROOT^DILFD API—Example 1: Input and Output.....	276
Figure 205: \$\$ROOT^DILFD API—Example 2: Input and Output.....	277
Figure 206: \$\$ROOT^DILFD API—Example 3: Input and Output.....	277
Figure 207: \$\$VFIELD^DILFD API—Example: Input and Output .....	278
Figure 208: \$\$VFILE^DILFD API—Example: Input and Output.....	278
Figure 209: \$\$GET1^DIQ API—Example 1: Input and Output .....	279
Figure 210: \$\$GET1^DIQ API—Example 2: Input and Output .....	280
Figure 211: \$\$GET1^DIQ API—Example 3: Input and Output .....	280
Figure 212: \$\$GET1^DIQ API—Example 4: Input and Output .....	280
Figure 213: \$\$GET1^DIQ API—Example 5: Input and Output .....	280
Figure 214: \$\$GET1^DIQ API—Example 6: Input and Output .....	281
Figure 215: \$\$GET1^DIQ API—Example 7: Input and Output .....	281
Figure 216: GETS^DIQ API—Example 1: Input and Output .....	283
Figure 217: GETS^DIQ API—Example 2: Input and Output .....	284
Figure 218: GETS^DIQ API—Example 3: Input and Output .....	284
Figure 219: GETS^DIQ API—Example 4: Input and Output .....	285
Figure 220: GETS^DIQ API—Example 5: Input and Output .....	285
Figure 221: ScreenMan Forms—DDSSTACK Variable: Sample Page Links.....	289
Figure 222: ScreenMan Forms—Sample of Two Subfields of a Multiple Displayed in a Repeating Block.....	290
Figure 223: ScreenMan Forms—Relational Navigation: Forward Pointers .....	293
Figure 224: ScreenMan Forms—Computed Fields: Example of Format.....	296
Figure 225: ScreenMan Forms—Referencing Form-Only and Computed Fields: Example .....	298

Figure 226: ScreenMan Forms—DDSBR Variable: Example .....	299
Figure 227: ScreenMan Forms—DDSBR Variable: Example of Format to Branch the User to the Command Line.....	300
Figure 228: ScreenMan Forms—DDSSTACK Variable: Example of Setting Variable to a Page Number .....	300
Figure 229: ScreenMan Forms—ScreenMan Menu Options .....	311
Figure 230: ScreenMan Forms—Run a Form Option .....	311
Figure 231: ScreenMan Forms—Delete a Form Option .....	312
Figure 232: ScreenMan Forms—Delete a Form Option: Report of All Blocks Used on the Form .....	312
Figure 233: ScreenMan Forms—Delete a Form Option: Delete Blocks.....	312
Figure 234: ScreenMan Forms—Delete a Form Option: Delete Blocks with or without Confirmation.....	313
Figure 235: ScreenMan Forms—Delete a Form Option: Deleting Blocks without Confirmation.....	313
Figure 236: ScreenMan Forms—Purge Unused Blocks Option.....	313
Figure 237: ScreenMan Forms—Purge Unused Blocks Option: Report of Unused Blocks on any Forms.....	314
Figure 238: ScreenMan Forms—Purge Unused Blocks Option: Delete Blocks with or without Confirmation.....	314
Figure 239: ScreenMan Forms—Purge Unused Blocks Option: Delete Blocks without Confirmation.....	314
Figure 240: ScreenMan Forms—CLONE^DDS: Sample Dialogue to Copy a Form.....	315
Figure 241: ScreenMan Forms—CLONE^DDS: Report Showing Blocks Used on a Form .....	315
Figure 242: ScreenMan Forms—CLONE^DD: Assigning New Form and Block Names .....	316
Figure 243: ScreenMan Forms—CLONE^DDS: Cloning a Form.....	316
Figure 244: ScreenMan Forms—PRINT^DDS: Printing a Form .....	317
Figure 245: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Invoking the Form Editor .....	319
Figure 246: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Selecting a File .....	320
Figure 247: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Selecting a Form.....	320
Figure 248: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Creating a New Form .....	320
Figure 249: ScreenMan Form Editor—Main Screen .....	323
Figure 250: ScreenMan Form Editor—Block Viewer Screen .....	324
Figure 251: ScreenMan Form Editor—Going to Another Page.....	325
Figure 252: ScreenMan Form Editor—Adding a Page.....	326
Figure 253: ScreenMan Form Editor—Adding a Page Confirmation.....	326
Figure 254: ScreenMan Form Editor—Adding a Block .....	327
Figure 255: ScreenMan Form Editor—Adding a Block Confirmation .....	327
Figure 256: ScreenMan Form Editor—Adding a Block to a Page .....	327
Figure 257: ScreenMan Form Editor—Adding Fields .....	327
Figure 258: ScreenMan Form Editor—Editing Field Properties .....	329
Figure 259: ScreenMan Form Editor—Other Parameters.....	330
Figure 260: ScreenMan Form Editor—Editing Block Properties .....	332

Figure 261: ScreenMan Form Editor—Editing Page Properties.....	333
Figure 262: ScreenMan Form Editor—Editing “Popup” Page Coordinates .....	334
Figure 263: ScreenMan Form Editor—Editing Form Properties.....	335
Figure 264: ScreenMan Form Editor—Choosing Another Form .....	335
Figure 265: ScreenMan Form Editor—Select Form.....	335
Figure 266: ScreenMan Form Editor—Save Changes.....	335
Figure 267: ScreenMan Form Editor—Choosing Another Form .....	337
Figure 268: ^DDS API—Example 1: Input.....	339
Figure 269: ^DDS API—Example 2: Input.....	340
Figure 270: \$\$GET^DDSVAL API—Example 1: Input.....	342
Figure 271: \$\$GET^DDSVAL API—Example 2: Input.....	342
Figure 272: \$\$GET^DDSVAL API—Example 3: Input.....	342
Figure 273: \$\$GET^DDSVAL API—Example 3: Output Array.....	342
Figure 274: PUT^DDSVAL API—Example 1: Input .....	344
Figure 275: PUT^DDSVAL API—Example 2: Input .....	344
Figure 276: PUT^DDSVAL API—Example 2: Output Array (1 of 2).....	344
Figure 277: PUT^DDSVAL API—Example 2: Output Array (2 of 2).....	344
Figure 278: \$\$GET^DDSVLAF API—Example 1: Input.....	345
Figure 279: \$\$GET^DDSVLAF API—Example 2: Input.....	346
Figure 280: PUT^DDSVLAF API—Example: Input.....	347
Figure 281: TURNON^DIAUTL API—Example: Input to Turn On Auditing for a Field in a File (1 of 2).....	351
Figure 282: TURNON^DIAUTL API—Example: Input to Turn On Auditing for a Field in a File (2 of 2).....	351
Figure 283: TURNON^DIAUTL API—Example: Input to Turn Off Auditing for a Field in a File	351
Figure 284: LAST^DIAUTL API—Example: Input and Output .....	352
Figure 285: CHANGED^DIAUTL API—Example 1: Input and Output.....	353
Figure 286: CHANGED^DIAUTL API—Example 2: Input and Output.....	353
Figure 287: BROWSE^DDBR API—Example: Input.....	356
Figure 288: BROWSE^DDBR API—Example: Output.....	357
Figure 289: Setting up Tab Stops.....	358
Figure 290: WP^DDBR API—Example: Input.....	359
Figure 291: DOCLIST^DDBR API—Example: Sample Document in ^TMP .....	362
Figure 292: DOCLIST^DDBR API—Example: Input to Build the Document List Array .....	362
Figure 293: DOCLIST^DDBR API—Example: Input Making a Procedure Call with Switching Restricted to Only this List.....	362
Figure 294: \$\$TEST^DDBRT API—Example: Input and Output.....	363
Figure 295: \$\$UTC^DIUTC API—Example 1: Input and Output.....	368
Figure 296: \$\$UTC^DIUTC API—Example 2: Input and Output.....	368
Figure 297: \$\$UTC^DIUTC API—Example 3: Input and Output.....	368
Figure 298: \$\$UTC^DIUTC API—Example 4: Input and Output.....	368
Figure 299: \$\$UTC^DIUTC API—Example 5: Input and Output.....	368
Figure 300: \$\$CANDO^DIAC1—Example 1: Input and Output.....	371
Figure 301: \$\$CANDO^DIAC1—Example 2: Input and Output.....	372

Figure 302: \$\$CANDO^DIAC1—Example 3: Input and Output.....	372
Figure 303: FILE^DDMP API—Example: Input Code to Import Data.....	376
Figure 304: FILE^DDMP API—Example: Input Code to Set the Array.....	376
Figure 305: Sample Listing of an Import File .....	378
Figure 306: EXPORT^DDXP API—Example 1: Input and Output.....	381
Figure 307: EXPORT^DDXP API—Example 2: Input and Output.....	381
Figure 308: EXPORT^DDXP API—Example 3: Input and Output.....	381
Figure 309: EXPORT^DDXP API—Example 4: Input for Special Case with the AUDIT (#1.1) File .....	381
Figure 310: EXPORT^DDXP API—Example 1: Input and Output.....	382
Figure 311: EXPORT^DDXP API—Example 5: Sample Sort Template Used.....	382
Figure 312: EXPORT^DDXP API—Example 5: Export Template Used.....	383
Figure 313: EXPORT^DDXP API—Example 5: Routine and Output .....	384
Figure 314: EXTRACT^DIAXU API—Example 1: Input .....	391
Figure 315: EXTRACT^DIAXU API—Example 1: Output Results Messages.....	391
Figure 316: EXTRACT^DIAXU API—Example 1: Output Error Messages .....	391
Figure 317: EXTRACT^DIAXU API—Example 2: Output Results and Error Messages.....	392
Figure 318: META DATA DICTIONARY (#.9) File Sample Entry.....	398
Figure 319: BUILDNEW^DIBTED—Example .....	402
Figure 320: ^DIKCBLD API—Sample User Dialogue .....	405
Figure 321: LANG^DIALOGZ API—Sample User Dialogue .....	407
Figure 322: LANG^DIALOGZ API—Sample Translated Editing Dialogue .....	408
Figure 323: LANG^DIALOGZ API—Sample Translated Print File Entries Dialogue .....	409
Figure 324: LANG^DIALOGZ API—Translations .....	410
Figure 325: ^DIC Global—Sample File Entry in the Dictionary of Files.....	412
Figure 326: ^DIC Global—Sample File Security Protection Codes.....	412
Figure 327: ^DIC Global—Sample File Descriptors.....	412
Figure 328: File Entries (Data Storage)—Sample File Entry.....	413
Figure 329: File Entries (Data Storage)—Sample File Entry with Additional Data Fields.....	414
Figure 330: File Entries (Data Storage)—Sample File Entry with Multiple Data Fields .....	414
Figure 331: Cross-References—Sample File Entry with Multiple Records .....	415
Figure 332: Cross-References—Sample Entry with Additional Data Fields .....	415
Figure 333: Attribute Dictionary—File Characteristics Nodes: Post-Action .....	417
Figure 334: Attribute Dictionary—File Characteristics Nodes: Data Dictionary Audit.....	417
Figure 335: Attribute Dictionary—File Characteristics Nodes: Special Lookup .....	417
Figure 336: Attribute Dictionary—File Characteristics Nodes: Field Identifiers .....	418
Figure 337: Attribute Dictionary—File Characteristics Nodes: Write Identifiers.....	418
Figure 338: Attribute Dictionary—File Characteristics Nodes: Cross-References.....	419
Figure 339: Attribute Dictionary—File Characteristics Nodes: Screens .....	419
Figure 340: Attribute Dictionary—File Characteristics Nodes: Version Number.....	419
Figure 341: Attribute Dictionary—File Characteristics Nodes: Distribution Package.....	420
Figure 342: Attribute Dictionary—File Characteristics Nodes: Package Revision Data.....	420
Figure 343: Attribute Dictionary—Field Definition 0-Node: ^DD(filename,fieldnumber Node 420	

Figure 344: Attribute Dictionary—Field Definition 0-Node: Sample Attribute Dictionary File Storage .....	421
Figure 345: Attribute Dictionary—Field Definition 0-Node: Piece 1 Sample Labels .....	421
Figure 346: Attribute Dictionary—Reading the Attribute Dictionary: Sample ^DD Nodes.....	426
Figure 347: Attribute Dictionary—Reading the Attribute Dictionary: Sample Translated Meaning .....	426
Figure 348: Attribute Dictionary—Reading the Attribute Dictionary: Sample DD Descendent Cross-references.....	426
Figure 349: Attribute Dictionary—Reading the Attribute Dictionary: Sample Subsidiary Data Dictionary .....	427
Figure 350: Attribute Dictionary—Reading the Attribute Dictionary: Sample Auxiliary User Prompts.....	427
Figure 351: Attribute Dictionary—Reading the Attribute Dictionary: Updated Data Dictionary for New Data .....	427
Figure 352: Attribute Dictionary—Reading the Attribute Dictionary: Sample User Prompt Confirming Data Entry .....	427
Figure 353: File Global Storage—Storing Data in a Global Other than ^DIZ: Sample User Prompts.....	428
Figure 354: File Global Storage—Storing Data in a Global Other than ^DIZ: Global Reference Format.....	428
Figure 355: File Global Storage—Storing Data in a Global Other than ^DIZ: Sample Global Storage Location of a Subscripted Descendent Global.....	429
Figure 356: File Global Storage—Storing Data in a Global Other than ^DIZ: Incorrect Global Storage Location of a Subscripted Descendent Global.....	429
Figure 357: Field Global Storage—Assigning a Location for Fields Stored within a Global .....	429
Figure 358: Field Global Storage—Storing Data by Position within a Node.....	430
Figure 359: Assigning Sub-Dictionary Numbers—Sample Dialogue Assigning Sub-dictionary Numbers .....	431
Figure 360: Computed Expressions—Computed Multiples: Sample Dialogue Creating a Computed Pointer from File #2 to File #200; Pointing at Last User Who Edited Patient ..	432
Figure 361: Computed Expressions—Computed Multiples: Sample Dialogue Creating a Computed Date that Gives the Patient’s Next Birthday.....	433
Figure 362: Screened Pointers and Set of Codes—Sample User Prompt .....	433
Figure 363: Screened Pointers and Set of Codes—Sample Screening Code.....	433
Figure 364: Screened Pointers and Set of Codes—Sample User Prompt on Screened Data..	434
Figure 365: Label Reference—Sample User Prompt.....	434
Figure 366: Time—Sample User Prompt.....	434
Figure 367: Year—Sample User Prompt .....	434
Figure 368: FT Pointer—Sample Use Prompts .....	434
Figure 369: FT Date—Sample User Prompts .....	435
Figure 370: Ratio—Sample User Prompts .....	435
Figure 371: INPUT Transform—Sample Code .....	436
Figure 372: INPUT Transform—Maximum (Output) Length.....	437
Figure 373: INPUT Transform—Checking for Variables .....	438
Figure 374: OUTPUT Transform—Sample Code .....	438
Figure 375: OUTPUT Transform—Sample Code with Computed Expression .....	438

Figure 376: Trigger Cross-References—Creating Trigger .....	443
Figure 377: Trigger Cross-References—SET Logic .....	443
Figure 378: Trigger Cross-References—KILL Logic .....	443
Figure 379: Trigger Cross-References—Conditions .....	444
Figure 380: Trigger Cross-References—Deletion Restrictions .....	444
Figure 381: Trigger Cross-References—Description .....	444
Figure 382: Trigger Cross-References—Confirmation.....	444
Figure 383: Trigger Cross-References—Sample Dialogue to Create a Trigger Cross-reference on a Field .....	445
Figure 384: DIALOG File—Sample Dialogue Creating a New Entry in the DIALOG (#.84) File .....	449
Figure 385: DIALOG File—Sample Dialogue to Create Non-English Text in the DIALOG (#.84) File .....	450
Figure 386: VA FileMan Functions—Sample Code that Takes an Internally Stored Format in a Variable and Transforms It .....	454
Figure 387: VA FileMan Functions—Sample Displaying Date-Valued Fields and Expressions in the DAY-MONTH-YEAR Format.....	454
Figure 388: VA FileMan Functions—Sample Function without Arguments .....	455
Figure 389: DIFROM—Entering Current Version Information: Sample Code .....	465
Figure 390: DIFROM—Using Indirection to Reference DDs Put into Place during the Init Process: Sample Code.....	466
Figure 391: DIFROM—Routines Data Transport Structure: Sample Code .....	467
Figure 392: DIFROM—Nodes Containing Security Information in the DD Structures—Sample Code .....	467
Figure 393: DIFROM—Running an Init: Sample Code .....	469
Figure 394: DIFROM—Sample HELP FRAME (#9.2) File Cross-Reference .....	475

## List of Tables

Table 1: Documentation Symbol Descriptions .....	xxix
Table 2: VA FileMan Routine Variables and Default Values .....	xxxiii
Table 3: VA FileMan Routine Global References .....	xxxiii
Table 4: Classic Calls—Category: Lookup/Adding Entries .....	5
Table 5: Classic Calls—Category: Entry Editing.....	5
Table 6: Classic Calls—Category: Prompting/Messages.....	5
Table 7: Classic Calls—Category: Printing.....	5
Table 8: Classic Calls—Category: Templates .....	6
Table 9: Classic Calls—Category: Cross-References .....	6
Table 10: Classic Calls—Category: Date/Time Utilities .....	7
Table 11: Classic Calls—Category: Utilities .....	7
Table 12: Loader—Processing Text Based on Mode .....	9
Table 13: EN^DIB: User Controlled Editing API .....	14
Table 14: ^DIC API—Variable Pointer Screen: DIC("V") Variable Y(0) Contents.....	19
Table 15: IX^DIC—Entry Points Lookups.....	29

Table 16: DIC and DIC1 Entry Point Comparison.....	32
Table 17: ^DIE API—Edit qualifiers: Interactive Syntax.....	45
Table 18: ^DIE API—Y(0) in the Code Set into the DIC(“V”) Variable.....	47
Table 19: ^DIE API—DIEFIRE Variable Settings.....	48
Table 20: ^DIK—Reindexing Quick Reference.....	50
Table 21: EN^DIK API—Reindexing Quick Reference.....	52
Table 22: EN1^DIK API—Reindexing Quick Reference.....	54
Table 23: EN2^DIK API—Reindexing Quick Reference.....	55
Table 24: ENALL^DIK API—Reindexing Quick Reference.....	57
Table 25: ENALL2^DIK API—Reindexing Quick Reference.....	58
Table 26: IX^DIK API—Reindexing Quick Reference.....	60
Table 27: IX1^DIK API—Reindexing Quick Reference.....	61
Table 28: IX2^DIK API—Reindexing Quick Reference.....	63
Table 29: IXALL^DIK API—Reindexing Quick Reference.....	64
Table 30: IXALL2^DIK API—Reindexing Quick Reference.....	65
Table 31: DIR(0)—Summary of Acceptable Types.....	93
Table 32: ^DIR: Reader Output Variables (Full Listing)—Y Processed Output.....	99
Table 33: ^DIR: Reader Output Variables (Full Listing)—Y Values upon Timeout.....	100
Table 34: ^%DT: Internal to External Date—Y2K Changes.....	119
Table 35: Database Server (DBS) API—Format and Conventions of the Calls—Acceptable vs. Unacceptable Roots.....	127
Table 36: IENS: Identify Entries and Subentries—Placeholder Codes.....	128
Table 37: Database Server (DBS) API—Database Server (DNS) Calls Cross-referenced by Category.....	137
Table 38: CREIXN^DDMOD API—Error Codes Returned.....	149
Table 39: DELIX^DDMOD API—Error Codes Returned.....	152
Table 40: DELIXN^DDMOD API—Error Codes Returned.....	155
Table 41: FILESEC^DDMOD API—Error Codes Returned.....	158
Table 42: BLD^DIALOG API—Output Variables Returned.....	159
Table 43: FIND^DIC API—Variable Pointer Screen: Y(0).....	178
Table 44: FIND^DIC API—Error Codes Returned.....	187
Table 45: \$\$FIND1^DIC API—Variable Pointer Screen: Y(0).....	197
Table 46: \$\$FIND1^DIC API—Error Codes Returned.....	199
Table 47: \$\$FIND1^DIC API—Screens Applied.....	200
Table 48: LIST^DIC API—Variable Pointer screen—Y(0).....	211
Table 49: LIST^DIC API—Error Codes Returned.....	220
Table 50: FIELD^DID API—Error Codes Returned.....	223
Table 51: FILE^DID API—Error Codes Returned.....	226
Table 52: \$\$GET1^DID API—Error Codes Returned.....	229
Table 53: CHK^DIE API—Error Codes Returned.....	231
Table 54: FILE^DIE: Filer—Error Codes Returned.....	233
Table 55: HELP^DIE API—Error Codes Returned.....	237
Table 56: \$\$KEYVAL^DIE API—Error Codes Returned.....	239
Table 57: UPDATE^DIE API—Error Codes Returned.....	244



Table 58: VAL^DIE API—Error Codes Returned.....	250
Table 59: VALS^DIE API—Error Codes Returned.....	255
Table 60: WP^DIE API—Error Codes Returned.....	257
Table 61: DT^DILF API—Error Codes Returned.....	262
Table 62: FDA^DILF API—Error Codes Returned.....	264
Table 63: \$\$HTML^DILF—Error Codes Returned.....	265
Table 64: \$\$EXTERNAL^DILFD API—Error Codes Returned.....	271
Table 65: \$\$EXTERNAL^DILFD API—VA FileMan Data Types.....	272
Table 66: \$\$FLDNUM^DILFD API—Error Codes Returned.....	274
Table 67: RECALL^DILFD API—Error Codes Returned.....	275
Table 68: \$\$ROOT^DILFD API—Error Codes Returned.....	277
Table 69: \$\$GET1^DIQ API—Error Codes Returned.....	281
Table 70: GETS^DIQ API—Error Codes Returned.....	285
Table 71: ScreenMan Forms—Variables Available in Repeating Blocks.....	291
Table 72: ScreenMan Forms—Block Properties that Apply only to Repeating Blocks.....	291
Table 73: ScreenMan Forms—Properties of Form-Only Fields.....	292
Table 74: ScreenMan Forms—Valid Formats for DD Fields.....	294
Table 75: ScreenMan Forms—Valid Formats for Form Only Fields.....	295
Table 76: ScreenMan Forms—Syntax for Computed Expression Atom that References a DD Field.....	297
Table 77: ScreenMan Forms—Syntax for Computed Expression Atom that References a Form Only Field.....	298
Table 78: ScreenMan Forms—Assumptions when Pieces of DDSBR are Null.....	299
Table 79: ScreenMan Forms—Form Properties.....	301
Table 80: ScreenMan Forms—Page Properties.....	302
Table 81: ScreenMan Forms—Block Properties: FORM File.....	304
Table 82: ScreenMan Forms—Block Properties: BLOCK File.....	305
Table 83: ScreenMan Forms—Field Properties.....	306
Table 84: ScreenMan Forms—Valid Default Values for Multiple Fields.....	307
Table 85: ScreenMan Forms—Descriptions of Field-Level Pre and Post Actions.....	310
Table 86: ScreenMan Forms—Variables Available in Field-Level Pre and Post Actions.....	310
Table 87: ScreenMan Form Editor—Navigating: Cursor Navigation to the Main Screen and the Block Viewer Screen.....	321
Table 88: ScreenMan Form Editor—Navigating: Key Sequences for Quick Page Navigation..	321
Table 89: ScreenMan Form Editor—Key Sequences to Move Screen Elements.....	322
Table 90: ScreenMan Form Editor—Key Sequences to Add, Select, and Edit.....	322
Table 91: ScreenMan Form Editor—General Key Sequences to: Exit, Quit, Save, and Obtain Help.....	324
Table 92: ScreenMan Form Editor—Navigating: Cursor Movement and Keyboard Combination.....	325
Table 93: ScreenMan Form Editor—Changing Current Page: Shortcut Keys.....	326
Table 94: ScreenMan Form Editor—General Key Sequences to: Move Screen Elements.....	328
Table 95: ScreenMan Form Editor—Shortcuts at the CAPTION Prompt.....	330
Table 96: ^DDS API—Error Codes Returned.....	340
Table 97: BROWSE^DDBR API—Error Codes Returned.....	357

Table 98: WP^DDBR API—Error Codes Returned.....	360
Table 99: DOCLIST^DDBR API—Error Codes Returned .....	362
Table 100: \$\$UTC^DIUTC API—Error Messages Returned.....	369
Table 101: FILE^DDMP API—Error Codes Returned.....	376
Table 102: EN^DIAXU—Error Codes Returned .....	387
Table 103: EXTRACT^DIAXU API—Error Codes Returned .....	392
Table 104: ^DIFG: Installer—Error Codes Returned .....	395
Table 105: ^DI API—Entry Points .....	403
Table 106: File Header—Descriptor String.....	412
Table 107: File Header—Descriptor String: Second ^Piece .....	413
Table 108: Attribute Dictionary—Characteristics, Subscripted Location, and Brief Explanation .....	417
Table 109: Attribute Dictionary—Write Identifier Nodes: M code to Produce Desired Output ..	418
Table 110: Attribute Dictionary—Field Definition 0-Node: Piece 2 Sample Strings .....	421
Table 111: Attribute Dictionary—Field Definition 0-Node: Piece 3 Data Types .....	422
Table 112: Attribute Dictionary—Other Field Definition Nodes .....	423
Table 113: Field Definition 0-Node—Pieces.....	425
Table 114: Audit Condition—Variables.....	440
Table 115: LANGUAGE (#.85) File—Language Entries .....	451
Table 116: LANGUAGE (#.85) File—Other Fields.....	452
Table 117: LANGUAGE (#.85) File—Date/Time Flags.....	452
Table 118: DIFROM—Fields Used during the Package Export Process.....	457
Table 119: DIFROM—Special Processing .....	476

# Orientation

## How to Use this Manual

The *VA FileMan Developer's Guide* provides advice and instruction about the VA FileMan database management system, Application Programming Interfaces (APIs), Direct Mode Utilities, and other developer-related information that VA FileMan 22.2 provides for overall Veterans Health Information Systems and Technology Architecture (VistA) application developers.

This manual is a full reference for all entry points in VA FileMan APIs and shows how to use features of VA FileMan that are likely to be used by developers and IRM staff. In most cases you *must* have programmer access (**DUZ(0)="@**) to use these features:

- [Classic VA FileMan API](#)
- [Database Server \(DBS\) API](#)
- [ScreenMan Forms](#)
- [ScreenMan Form Editor](#)
- [ScreenMan API](#)
- [Auditing API](#)
- [Browser API](#)
- [Coordinated Universal Time \(UTC\) API](#)
- [Data Access Control \(DAC\) API](#)
- [Import and Export Tools](#)
- [Extract Tool](#)
- [Filegrams API](#)
- [Meta Data Dictionary](#)
- [Create Sort Templates Silently API](#)
- [^DI: Programmer Access](#)
- [^DIKCBLD: Build an M Routine that Makes a Call to CREIXN^DDMOD](#)
- [LANG^DIALOGZ\(\): File Modification for Multiple Languages](#)
- [Global File Structure](#)
- [Advanced File Definition](#)
- [Trigger Cross-References](#)
- [DIALOG File](#)
- [VA FileMan Functions \(Creating\)](#)
- [DIFROM](#)
- [Appendix A—VA FileMan Error Codes](#)



**NOTE:** This document is available in Microsoft Word (.docx), Adobe Acrobat Portable Document Format (PDF), and Hypertext Markup Language (HTML) format (see the “[HTML Manuals](#)” section).



**REF:** For VA FileMan installation instructions in the VistA environment see the *VA FileMan Installation, Back-Out, and Rollback Guide* and any national patch description of the patch being released.

## HTML Manuals

Why produce an HTML (Hypertext Markup Language) edition of the VA FileMan User Manual?

- The HTML versions of the VA FileMan manuals are useful as online documentation support as you use VA FileMan. HTML manuals allow you to instantly jump (link) to specific topics or references online.
- The VA FileMan HTML manuals are “living” documents that are continuously updated with the most current VA FileMan information (unlike paper or printed documentation). They are updated based on new versions, patches, or enhancements to VA FileMan.
- Presenting manuals in an HTML format on a Web server also gives new opportunities, such as accessing embedded multimedia training material (e.g., video) directly in the manuals themselves.
- Manuals are accessible over the VA Intranet network.

## Intended Audience

The intended audience of this manual is all key stakeholders. The stakeholders include the following:

- Enterprise Program Management Office (EPMO)—VistA legacy development teams.
- Information Resource Management (IRM)—System administrators at Department of Veterans Affairs (VA) sites who are responsible for computer management and system security on the VistA M Servers.
- Information Security Officers (ISOs)—Personnel at VA sites responsible for system security.
- Product Support (PS).

# Disclaimers

## Software Disclaimer

This software was developed at the Department of Veterans Affairs (VA) by employees of the Federal Government in the course of their official duties. Pursuant to title 17 Section 105 of the United States Code this software is *not* subject to copyright protection and is in the public domain. VA assumes no responsibility whatsoever for its use by other parties, and makes no guarantees, expressed or implied, about its quality, reliability, or any other characteristic. We would appreciate acknowledgement if the software is used. This software can be redistributed and/or modified freely provided that any derivative works bear some notice that they are derived from it, and any modified versions bear some notice that they have been modified.



**CAUTION:** To protect the security of VistA systems, distribution of this software for use on any other computer system by VistA sites is prohibited. All requests for copies of Kernel for *non-VistA* use should be referred to the VistA site's local Office of Information Field Office (OIFO).

## Documentation Disclaimer

This manual provides an overall explanation of VA FileMan and the functionality contained in VA FileMan 22.0; however, no attempt is made to explain how the overall VistA programming system is integrated and maintained. Such methods and procedures are documented elsewhere. We suggest you look at the various VA Internet and Intranet Websites for a general orientation to VistA. For example, visit the Office of Information and Technology (OIT) VistA Development Intranet website.



**DISCLAIMER:** The appearance of any external hyperlink references in this manual does *not* constitute endorsement by the Department of Veterans Affairs (VA) of this Website or the information, products, or services contained therein. The VA does *not* exercise any editorial control over the information you find at these locations. Such links are provided and are consistent with the stated purpose of this VA Intranet Service.

## Documentation Conventions

This manual uses several methods to highlight different aspects of the material:

- Various symbols are used throughout the documentation to alert the reader to special information. [Table 1](#) gives a description of each of these symbols:

**Table 1: Documentation Symbol Descriptions**

Symbol	Description
	<b>NOTE / REF:</b> Used to inform the reader of general information including references to additional reading material.
	<b>CAUTION / RECOMMENDATION / DISCLAIMER:</b> Used to caution the reader to take special notice of critical information.

- Descriptive text is presented in a proportional font (as represented by this font).

- Conventions for displaying TEST data in this document are as follows:
  - The first three digits (prefix) of any Social Security Numbers (SSN) begin with either “000” or “666”.
  - Patient and user names are formatted as follows:
    - *<Application Name/Abbreviation/Namespace>PATIENT,<N>*
    - *<Application Name/Abbreviation/Namespace>USER,<N>*

Where:

- *<Application Name/Abbreviation/Namespace>* is defined in the Approved Application Abbreviations document.
- *<N>* represents the first name as a number spelled out and incremented with each new entry.

For example, in VA FileMan (FM) test patient and user names would be documented as follows:

- FMPATIENT,ONE; FMPATIENT,TWO; FMPATIENT,THREE; ... FMPATIENT,14; etc.
- FMUSER,ONE; FMUSER,TWO; FMUSER,THREE; ... FMUSER,14; etc.

- “Snapshots” of computer online displays (i.e., screen captures/dialogues) and computer source code, if any, are shown in a *non*-proportional font and enclosed within a box:
  - User’s responses to online prompts are **bold** typeface and highlighted in yellow (e.g., **<Enter>**).
  - Emphasis within a dialogue box is **bold** typeface and highlighted in blue (e.g., **STANDARD LISTENER: RUNNING**).
  - Some software code reserved/key words are **bold** typeface with alternate color font.
  - References to “**<Enter>**” within these snapshots indicate that the user should press the **Enter** key on the keyboard. Other special keys are sometimes represented within *< >* angle brackets. For example, pressing the **PF1** key can be represented as pressing **<PF1>**.
  - Author’s comments are displayed in italics or as “callout” boxes.



**NOTE:** Callout boxes refer to labels or descriptions usually enclosed within a box, which point to specific areas of a displayed image.

- This manual refers in many places to the MUMPS (M) programming language. Under the 1995 American National Standards Institute (ANSI) standard, M is the primary name of the MUMPS programming language, and MUMPS is considered an alternate name. This manual uses the name M.
- Descriptions of direct mode utilities are prefaced with the standard M “>” prompt to emphasize that the call is to be used *only in direct mode*. They also include the M command used to invoke the utility. The following is an example:

```
>D P^DI
```

- The following conventions are used with regards to APIs:
  - Headings for developer API descriptions (e.g., supported for use in applications and on the Database Integration Committee [DBIC] list) include the routine tag (if any), the caret (^) used when calling the routine, and the routine name. The following is an example:
 

```
EN^DIB
```
  - For APIs that take input parameter, the input parameter is labeled “required” when it is a required input parameter and labeled “optional” when it is an optional input parameter.
  - For APIs that take parameters, parameters are shown in lowercase and variables are shown in uppercase. This is to convey that the parameter name is merely a placeholder; M allows you to pass a variable of any name as the parameter or even a string literal (if the parameter is not being passed by reference). The following is an example of the formatting for input parameters:
 

```
HELP^DIE(file,iens,field,flags,msg_root)
```
  - Rectangular brackets [ ] around a parameter are used to indicate that passing the parameter is optional. Rectangular brackets around a leading period [.] in front of a parameter indicate that you can optionally pass that parameter by reference.
  - All APIs are categorized by function. This categorization is subjective and subject to change based on feedback from the development community. Also, some APIs could fall under multiple categories; however, they are only listed once under a chosen category.

APIs within a category are first sorted alphabetically by Routine name and then within routine name are sorted alphabetically by Tag reference. The \$\$, ^, or ^% prefixes on APIs is ignored when alphabetizing.
- All uppercase is reserved for the representation of M code, variable names, or the formal name of options, field/file names, and security keys (e.g., DIEXTRACT).



**NOTE:** Other software code (e.g., Delphi/Pascal and Java) variable names and file/folder names can be written in lower or mixed case.

## Documentation Navigation

This document uses Microsoft® Word’s built-in navigation for internal hyperlinks. To add **Back** and **Forward** navigation buttons to your toolbar, do the following:

1. Right-click anywhere on the customizable Toolbar in Word (*not* the Ribbon section).
2. Select **Customize Quick Access Toolbar** from the secondary menu.
3. Select the drop-down arrow in the “Choose commands from:” box.
4. Select **All Commands** from the displayed list.
5. Scroll through the command list in the left column until you see the **Back** command (green circle with arrow pointing left).
6. Select/Highlight the Back command and select Add to add it to your customized toolbar.
7. Scroll through the command list in the left column until you see the **Forward** command (green circle with arrow pointing right).
8. Select/Highlight the Forward command and select **Add** to add it to your customized toolbar.

9. Select **OK**.

You can now use these **Back** and **Forward** command buttons in your Toolbar to navigate back and forth in your Word document when clicking on hyperlinks within the document.



**NOTE:** This is a one-time setup and is automatically available in any other Word document once you install it on the Toolbar.

## Non-Standard M Features

Z-commands and Z-functions are avoided throughout VA FileMan routines. For certain purposes, such as allowing terminal breaking and spooling to a Standard Disk Processor (SDP) disk device, VA FileMan executes lines of *non*-standard M code out of the MUMPS OPERATING SYSTEM (#.7) file. The *non*-standard code used (if any) depends on the answer to the prompt:

**Figure 1: Type of M System Prompt**

```
TYPE OF MUMPS SYSTEM YOU ARE USING:
```

This prompt appears during the DINIT initialization routine. Answering OTHER to this question ensures that VA FileMan uses only standard M code.

VA FileMan also makes use of non-standard M code that is stored in the %ZOSF global. If VA FileMan is installed on a system that contains Kernel, it uses the %ZOSF global created by Kernel. If it is being used without Kernel (i.e., standalone), the necessary %ZOSF nodes are set for many operating systems by running DINZMGR in the manager account.



**REF:** For details, see the “System Management” section in the *VA FileMan Advanced User Manual*.

String-valued subscripts (up to 30 characters long) are used extensively but only in the \$ORDER collating sequence approved by the MUMPS Development Committee (MDC). *Non*-negative integer and fractional canonic numbers collate ahead of all other strings.

The \$ORDER function is used at several points in VA FileMan’s code. VA FileMan routines assume that reference to an undefined global subscript level sets the naked indicator to that level, rather than leaving it undefined. In all other respects, the VA FileMan code conforms to the 1995 ANSI Standard for the M language with Type A extensions.

## Routine, Variable, and Global Names

In keeping with the convention that all programs that are a part of the same application or utility package should be namespaced, all VA FileMan routine names begin with **DI** or **DD**.



**REF:** The “Device Handling for Standalone VA FileMan” section in the *VA FileMan Advanced User Manual* explains that some DI\* routines are renamed in the management account.

The DINIT routine initializes VA FileMan. The DI routine itself is the main option reader.



**REF:** For more information on the DI routine, see the “[^DI: Programmer Access](#)” section.


Except in DI, the routines do *not* contain unargumented or exclusive KILL commands. All multi-character local variable names created by VA FileMan routines begin with % or the letter **D**, or consist of one uppercase letter followed by one numeral [except that IO(0), by convention, contains the \$I value of



the signon device]. Since VA FileMan uses single character variable names extensively, do *not* use them in code that is executed from within VA FileMan programming hooks, unless their use is documented in the hook's description or you NEW them. Also, do *not* expect single character variables to return unchanged after calling a VA FileMan entry point.

[Table 2](#) lists local variables of special importance in the VA FileMan routines:

**Table 2: VA FileMan Routine Variables and Default Values**

Variable	Description	Default Value
DT	If defined, it is assumed to be the current date. For example: June 1, 1987 is DT=2870601.	Today's date; derived from \$H
DTIME	If defined, it is the integer value of the number of seconds the user has to respond to a timed read.	300
DUZ	If defined, it is assumed to be the User Number; a positive number uniquely identifying the current user.	0
DUZ(0)	If defined, it is assumed to be the VA FileMan Access code, which is a character string describing the user's security clearance with regard to files, templates, and data fields within a file.   <b>REF:</b> See the "Data Security" section in the <i>VA FileMan Advanced User Manual</i> .  Setting DUZ(0) equal to the at-sign (@) overrides all security checks and allows special developer features, which are described later. If the user's M implementation supports terminal break, a developer is allowed to break execution at any point, whereas a user who does <i>not</i> have programmer access can only break during output routines.	""
U	If defined, it is equal to a single caret (^) character.	^

[Table 3](#) lists the globals to which the VA FileMan routines explicitly refer:

**Table 3: VA FileMan Routine Global References**

Global	Description
^DD	All attribute dictionaries.
^DDA	Data dictionary audit trail.
^DI	Data types.
^DIA	Data audit trail.
^DIAR	Archival activity and Filegrams.
^DIBT	Sort templates and the results of file searches.
^DIC	Dictionary of files.
^DIE	Input templates.
^DIPT	Print templates and Filegram templates.

Global	Description
^DIST	ScreenMan forms and blocks and Alternate Editors.
^DISV	Most recent lookup value in any file or subfile (by DUZ).
^DIZ	Default location for new data files as they are created.
^DOPT	Option lists.
^DOSV	Statistical results.
^%ZOSF	M vendor-specific executable code.

The routines use the ^UTILITY and ^TMP globals for temporary scratch space. The ^XUTL global is also used if you are running some M implementations.

## Delimiters within Strings

The caret (^) character is conventionally used to delimit data elements that are strung together to be stored in a single global node. A corollary of this rule is that the routines almost never allow input data to contain carets; the user types a caret (^) to change or terminate the sequence of questions being asked. Within ^-pieces, semicolons (;) are usually used as secondary delimiters, and colons (:) as tertiary delimiters.

VA FileMan routines use the local variable U as equal to the single caret (^) character.

## Canonic Numbers

VA FileMan recognizes only canonic numbers. A canonic number is a number that does *not* begin or end with meaningless zeroes. For example, 7 is a canonic number, whereas 007 and 7.0 are not.

## How to Obtain Technical Information Online

Exported VistA M Server-based software file, routine, and global documentation can be generated through the use of Kernel, MailMan, and VA FileMan utilities.



**NOTE:** Methods of obtaining specific technical information online is indicated where applicable under the appropriate topic.

**REF:** For further information, see the *VA FileMan Technical Manual*.

## Help at Prompts

VistA M Server-based software provides online help and commonly used system default prompts. Users are encouraged to enter question marks at any response prompt. At the end of the help display, you are immediately returned to the point from which you started. This is an easy way to learn about any aspect of the software.

## Obtaining Data Dictionary Listings

Technical information about VistA M Server-based files and the fields in files is stored in data dictionaries (DD). You can use the List File Attributes option [DILIST] on the Data Dictionary Utilities menu [DI DDU] in VA FileMan to print formatted data dictionaries.



**REF:** For details about obtaining data dictionaries and about the formats available, see the “List File Attributes” section in the “File Management” section in the *VA FileMan Advanced User Manual*.

## Assumptions

This manual is written with the assumption that the reader is familiar with the following:

- VistA computing environment:
  - Kernel—VistA M Server software
  - VA FileMan data structures and terminology—VistA M Server software
- Microsoft Windows environment
- M programming language

## Reference Materials

Readers who wish to learn more about VA FileMan should consult the following:

- *VA FileMan Release Notes*
- *VA FileMan Installation, Back-Out, and Rollback Guide*
- *VA FileMan Technical Manual*
- *VA FileMan User Manual* (PDF and HTML format)
- *VA FileMan Advanced User Manual* (PDF and HTML format)
- *VA FileMan Developer’s Guide* (this manual; PDF and HTML format)



**REF:** Zip files of the VA FileMan documentation in HTML format are located on the VA FileMan Intranet Product website and VDL at: <http://www.va.gov/vdl/application.asp?appid=5>

Using a Web browser, open the **HTML** documents “table of contents” page (i.e., index.shtml). The *VA FileMan User Manual*, *VA FileMan Advanced User Manual*, and *VA FileMan Developer’s Guide* are all linked together.

VistA documentation is made available online in Microsoft Word format and in Adobe Acrobat Portable Document Format (PDF). The PDF documents *must* be read using the Adobe Acrobat Reader, which is freely distributed by Adobe® Systems Incorporated at: <http://www.adobe.com/>

VistA software documentation can be downloaded from the VA Software Document Library (VDL) at: <http://www.va.gov/vdl/>



**REF:** VA FileMan manuals are located on the VDL at: <http://www.va.gov/vdl/application.asp?appid=5>

VistA documentation and software can also be downloaded from the Product Support (PS) Anonymous Directories.

# 1 Introduction

## 1.1 What is VA FileMan?

VA FileMan creates and maintains a database management system that includes features such as:

- Report writer
- Data dictionary manager
- Scrolling and screen-oriented data entry
- Text editors
- Programming utilities
- Tools for sending data to other systems
- File archiving

VA FileMan can be used as a:

- Standalone database
- Set of interactive or “silent” routines
- Set of application utilities

In all modes, it is used to define, enter, and retrieve information from a set of computer-stored files, each of which is described by a data dictionary.

VA FileMan is a public domain software that is developed and maintained by the Department of Veterans Affairs (VA). It is widely used by VA medical centers and in clinical, administrative, and business settings in the United States of America (USA) and abroad.

## 1.2 Functional Description

VA FileMan functions as a Database Management System (DBS) with powerful Application Programming Interfaces (APIs) and provides useful utilities for application developers. VA FileMan can be used as a database management system for data entry and output and its DBS calls are used in applications with tools like Filegrams, auditing, archiving, and statistics.+

- **Database Management System (DBS)**—As a database management system (DBS), VA FileMan supports the entering, editing, printing, searching, inquiring, transferring, cross-referencing, triggering, and verifying of information. It includes special functions to:
  - Create new files
  - Modify an existing file
  - Delete entire files
  - Reindex files
  - Create or edit templates
- **Application Programming Interfaces (APIs)**—As an application programming interface (API), the Database Server routines manage interactions between the application software and the database management system “silently” (i.e., *without* writing to the current device). Application developers use DBS calls to update the database in a *non*-interactive mode. Information needed by the VA FileMan routines is passed through parameters rather than through interactive dialogue

with the user. Information to be displayed to the user is passed by VA FileMan back to the calling routine in arrays. This separation of data access from user interaction makes possible the construction of alternative front-ends to the VA FileMan database (e.g., a windowed Graphical User Interface [GUI]).

- **Utilities**—As a set of utilities, VA FileMan provides tools like:
  - **Filegram**—Tool that moves file records from one computer to another
  - **Archiving**—Tool that stores data onto an offline storage medium.
  - **Auditing**—Tool that tracks changes to data in a field or to the file’s structure (i.e., data dictionary).
  - **Statistics**—Tool that accumulates totals and subtotals of individual fields.

VA FileMan has several levels of users, ranging from a data entry person who enters, edits, inquires, or prints information, to a software application developer or system administrator who uses all of its database management system features and utilities.

Developers should consider this manual the list of VA FileMan-supported (“documented”) routines and Application Programming Interface (API) calls eligible for developer use. These routines and APIs provide the following (to list a few):

- File lookup and reindexing
- Data edit, print, display, and retrieval
- Filegrams
- File entry deletion
- Reader program
- Data dictionary deletion
- Word-processing
- Conversion of date and time values
- Software package export
- Linked option processing

## 1.3 Standalone VA FileMan

VA FileMan is designed to be used either with Kernel or as a standalone application running under a variety of implementations of ANSI standard M. If VA FileMan is used *without* Kernel, the basic DBMS features of VA FileMan all work as described in the manuals. However, there are some features (e.g., bulletin-type cross references, print queuing, and Filegrams) that do *not* work without portions of Kernel. Whenever Kernel is needed to support a particular VA FileMan feature, that fact is mentioned in the manuals.

The installation of VA FileMan 22.2 is *not* integrated with the installation of Kernel. The *VA FileMan Installation, Back-Out, and Rollback Guide* contains instructions on how to install VA FileMan, both for standalone sites and for sites running Kernel.



**REF:** For specific information regarding standalone VA FileMan (i.e., device handling, setting IO variables, manually setting ^%ZOSF nodes, and setting up a minimal NEW PERSON [#200] file), see the “FileMan System Management” section in the *VA FileMan Advanced User Manual*.



# I. Major APIs

## 2 Classic VA FileMan API

### 2.1 Introduction

Certain modules within VA FileMan are callable by other M routines. This is true of these Classic VA FileMan routines, which are referred to as “Callable Routines” and are described in this section.

Database Server (DBS) calls are also callable by other M routines. However, these “silent” calls differ from the Classic VA FileMan routines in that they separate interaction with the database from interaction with the end-user. In Classic VA FileMan’s roll-and-scroll mode, interaction with the end-user was closely tied to the code that actually changed the database, but with VA FileMan’s DBS calls no WRITES to the current device are done. Interaction with the user is managed by package developers from within their own code, calling VA FileMan whenever interaction with the database is needed.



**REF:** These DBS calls are described in the [“Database Server \(DBS\) API”](#) section.

When using both the Classic VA FileMan callable routines and the DBS calls, you *must* keep in mind the variable-naming conventions. If you have local variables that you wish to preserve by a call to any of the routines described here, you should be sure to give them multi-character names beginning with letters other than **D**.

It is the developer’s responsibility to clean up (KILL) documented input and output variables used in a VA FileMan call when the call is finished. The few situations in which your input variables are KILLED during the VA FileMan call are mentioned in the following sections. Developers also need to be alert to the fact that Classic VA FileMan APIs are *not* recursive. A classic example is situation where your routine is being called from a cross-reference, the client, and you want to alter the contents of other fields either within the parent file or fields outside the parent file, in which case the developer would use the proper Database Server (DBS) call.

After making an API call, always check for failed calls. For example, when using ^DIC for lookups, always check for the error condition **Y=-1** before doing anything else; when using the reader, always check **DUOUT**, **DIRUT**, and **DTOUT** before doing anything else. When a call provides a way to check for error conditions, it means that there are some circumstances where the call does *not* succeed! Checking for errors after such a call allows you to handle the errors gracefully.



**CAUTION: Programmer access in VistA is defined as DUZ(0)="@". It grants the privilege to become a developer in VistA. Programmer access allows you to:**

- **Work outside many of the security controls enforced by VA FileMan.**
- **Enables access to all VA FileMan files.**
- **Provides access to modify data dictionaries, etc.**

**It is important to proceed with caution when having access to the system in this way.**



## 2.2 Classic Calls Cross-Referenced by Category

**Table 4: Classic Calls—Category: Lookup/Adding Entries**

Entry Point	Description / Title
<a href="#">^DIAC</a>	File Access Determination
<a href="#">^DIC</a>	Lookup/Add Using “B” Cross-Reference
<a href="#">IX^DIC</a>	Lookup/Add Using User-Specified Cross-Reference
<a href="#">MIX^DIC1</a>	Lookup/Add Using User-Specified Set of Cross-References
<a href="#">FILE^DICN</a>	Adds New Entry to File
<a href="#">DQ^DICQ</a>	Entry Display for Lookups

**Table 5: Classic Calls—Category: Entry Editing**

Entry Point	Description / Title
<a href="#">^DIE</a>	Data Input Edit of a File
<a href="#">EN^DIB</a>	User Controlled Editing
<a href="#">^DIK</a>	Delete Entries
<a href="#">EN^DIQ1</a>	Data Retrieval
<a href="#">EN^DIWE</a>	Text Editing

**Table 6: Classic Calls—Category: Prompting/Messages**

Entry Point	Description / Title
<a href="#">^DIR</a>	Response Reader
<a href="#">EN^DDIOL</a>	Message Loader
<a href="#">WAIT^DICD</a>	Wait Messages
<a href="#">YN^DICN</a>	Reader for a YES/NO Response
<a href="#">HELP^%DTC</a>	Displays Help Prompt Based on Date

**Table 7: Classic Calls—Category: Printing**

Entry Point	Description / Title
<a href="#">EN1^DIP</a>	Print Data
<a href="#">D^DIQ</a>	Converts Internal Date to External Form
<a href="#">DT^DIQ</a>	Converts Internal Date to External Form and Writes Date
<a href="#">EN^DIQ</a>	Displays Captioned Range of Data
<a href="#">Y^DIQ</a>	Converts Internal Data to External Form

Entry Point	Description / Title
<a href="#">EN^DIS</a>	Searches File Entries
<a href="#">^DIWF</a>	Form Document Print
<a href="#">EN1^DIWF</a>	Form Document Print with Known Document
<a href="#">EN2^DIWF</a>	Form Document Print with Known Document and Entry
<a href="#">DIWP</a>	Formats and Outputs Text Lines
<a href="#">DIWW</a>	Output Remaining Text in ^UTILITY(\$J,"W") by ^DIWP

**Table 8: Classic Calls—Category: Templates**

Entry Point	Description / Title
<a href="#">^DIEZ</a>	INPUT Template Compile—User Interactive
<a href="#">EN^DIEZ</a>	INPUT Template Compile—No User Interaction
<a href="#">^DIOZ</a>	SORT Template Compile
<a href="#">^DIPT</a>	PRINT Template Display
<a href="#">DIBT^DIPT</a>	SORT Template Display
<a href="#">^DIPZ</a>	PRINT Template Compile—User Interactive
<a href="#">EN^DIPZ</a>	PRINT Template Compile—No User Interaction

**Table 9: Classic Calls—Category: Cross-References**

Entry Point	Description / Title
<a href="#">EN^DIK</a>	Reindex Field Cross-References for One File Entry—KILL and SET Logic
<a href="#">EN1^DIK</a>	Reindex Field Cross-References for One File Entry—SET Logic
<a href="#">EN2^DIK</a>	Executes KILL Logic for One or More Field Cross-References for One File Entry
<a href="#">ENALL^DIK</a>	Reindex All File Entries for Specific Field Cross-References—SET Logic
<a href="#">ENALL2^DIK</a>	Executes KILL Logic for One or More Field Cross-References for All File Entries
<a href="#">IX^DIK</a>	Reindex All File Cross-References for One File Entry—KILL and SET Logic
<a href="#">IX1^DIK</a>	Reindex All File Cross-References for One File Entry—SET Logic
<a href="#">IX2^DIK</a>	Executes KILL Logic of All Cross-References for One Entry at All File Levels at and below the One Specified in DIK
<a href="#">IXALL^DIK</a>	Reindexes All Cross-References for All File Entries—SET Logic
<a href="#">IXALL2^DIK</a>	Executes KILL Logic for All File Entries
<a href="#">^DIKZ</a>	Compiles Cross-References into M Routines

Entry Point	Description / Title
<a href="#">EN^DIKZ</a>	Recompiles a File's Cross-References—No User Intervention

**Table 10: Classic Calls—Category: Date/Time Utilities**

Entry Point	Description / Title
<a href="#">X^ADD("DD")</a>	Converts Internal to External Date Format
<a href="#">DT^DIO2</a>	Writes External Date from Internal
<a href="#">^%DT</a>	Validates Date/Time Input and Converts to Internal Format
<a href="#">DD^%DT</a>	Converts Internal to External Date Format
<a href="#">^%DTC</a>	Returns Number of Days between Two Dates
<a href="#">C^%DTC</a>	Adds/Subtracts Days and Returns VA FileMan Date and \$H Format
<a href="#">DW^%DTC</a>	Converts VA FileMan Date to \$H Format and Outputs Name of the Day
<a href="#">H^%DTC</a>	Converts VA FileMan Date to \$H Format
<a href="#">NOW^%DTC</a>	Returns Current Date/Time in VA FileMan and \$H Formats
<a href="#">S^%DTC</a>	Converts Seconds to Hours, Minutes, and Seconds into Decimal Part of VA FileMan Date
<a href="#">YMD^%DTC</a>	Converts \$H to VA FileMan Format
<a href="#">YX^%DTC</a>	Returns Printable and VA FileMan Formats from \$H

**Table 11: Classic Calls—Category: Utilities**

Entry Point	Description / Title
<a href="#">DO^DIC1</a>	File Information Setup
<a href="#">DT^DICRW</a>	FM Variable Setup
<a href="#">EN^DID</a>	Print/Display Data Dictionary Listing
<a href="#">\$\$ROUSIZE^DILF</a>	Returns Maximum Routine Size
<a href="#">^DIM</a>	Validates M Code
<a href="#">COMMA^%DTC</a>	Formats Number to String with Commas
<a href="#">EN^DIU2</a>	Delete Data Dictionary
<a href="#">%XY^%RCR</a>	Moves Arrays between Locations

## 2.3 Classic Calls Presented in Alphabetical Order

This section lists and describes the VA FileMan Classic Calls in alphabetical order. The table previous to this page cross-references the Classic Calls by category.

### 2.3.1 Introduction to Date/Time Formats: %DT



**NOTE:** This introduction pertains to all %DT calls.

%DT is used to validate date/time input and convert it to VA FileMan's conventional internal format:

***YYMMDD.HHMMSS***

Where:

- ***YYY***—Number of years since 1700 (hence always 3 digits)
- ***MM***—Month number (00-12)
- ***DD***—Day number (00-31)
- ***HH***—Hour number (00-23)
- ***MM***—Minute number (01-59)
- ***SS*** —Seconds number (01-59)

This format allows for representation of imprecise dates, such as JULY '78 or 1978, which would be equivalent to 2780700 and 2780000, respectively. Dates are always returned as a canonic number (i.e., no trailing zeroes after the decimal).

The following are the date/time-related APIs:

- [X ^DD\("DD"\): Converts Internal to External Date Format](#)
- [DT^DIO2: Writes External Date from Internal](#)
- [^%DT: Validates Date/Time Input and Converts to Internal Format](#)
- [DD^%DT: Converts Internal to External Date Format](#)
- [^%DTC: Returns Number of Days between Two Dates](#)
- [C^%DTC: Adds/Subtracts Days and Returns VA FileMan Date and \\$H Format](#)
- [DW^%DTC: Converts VA FileMan Date to \\$H Format and Outputs Name of the Day](#)
- [H^%DTC: Converts VA FileMan Date to \\$H Format](#)
- [NOW^%DTC: Returns Current Date/Time in VA FileMan and \\$H Formats](#)
- [S^%DTC: Converts Time into Decimal Part of VA FileMan Internal Date](#)
- [YMD^%DTC: Converts \\$H to VA FileMan Format](#)
- [YX^%DTC: Returns Printable and VA FileMan Internal Formats from \\$H](#)
- [DT^DILF\(\): Date Converter](#)

## 2.3.2 X ^DD("DD"): Converts Internal to External Date Format

There are two ways to convert a date from VA FileMan internal format (*YYMMDD*) to external format:

- X ^DD("DD") (this call)
- [DD^%DT](#)

This is the reverse of what [%DT](#) does. Simply set the variable **Y** equal to the internal date and execute ^DD("DD").

### Input Variable

**Y:** (Required) This contains the internal date to be converted. If this has five or six decimal places, seconds are automatically returned.

### Output Variable

**Y:** Y is returned as the external form of the date.



**REF:** See also the [DT^DIO2](#): API, which takes an internal date in the variable **Y** and *writes out* its external form.

### 2.3.2.1 Example

Figure 2: X ^DD("DD") API—Example

```
>S Y=2690720.163 X ^DD("DD") W Y
JUL 20,1969@1630
```

This results in **Y** being equal to JUL 20,1969@16:30. (No space before the 4-digit year.)

## 2.3.3 EN^DDIOL(): Message Loader

The EN^DDIOL API is designed as a replacement for simple WRITE statements in any part of the data dictionary that has a programming “hook” (e.g., executable help).

As alternate user interfaces are developed for accessing VA FileMan databases, developers are faced with the issue of removing embedded WRITE statements from their data dictionaries. Direct WRITES should be removed, since they might cause the text to display improperly in the new interface. This separation of the user interface from the database definition helps you to prepare your databases for access by any new interface, such as a Graphical User Interface (GUI).

The environment in which the Loader is called determines how it processes the text it is passed.

Table 12: Loader—Processing Text Based on Mode

Mode	How the Text Is Processed
Scrolling	Text is written to the screen.
ScreenMan	Text is written in ScreenMan’s Command Area.
DBS	Text is loaded into an array.

In DBS mode, the specific array where the text is placed depends on which DBS call is made and whether an output array was specified in the DBS call.

For example, if a call is made to the Validator ([VAL^DIE](#)), and the INPUT transform of the field makes a call to the Loader, the text is placed into ^TMP(“DIMSG”,\$J). If a call is made to the Helper ([HELP^DIE](#)), and the executable help of the field makes a call to the Loader, the text is placed into ^TMP(“DIHELP”,\$J). If the call to Validator or the Helper uses the **msg\_root** parameter, the text is placed in the array specified by **msg\_root**.



**RECOMMENDATION: No line of text passed to the Loader should exceed 70 characters in length.**

## Formats

1. EN^DDIOL(value, “”, format)
2. EN^DDIOL(.array)
3. EN^DDIOL(“”, global\_root)

## Input Parameters

**value:** (Optional) If there is just one line of text to output, it can be passed in the first parameter.

**.array:** (Optional) If there is more than one line of text to output, stored in a local array, then the first parameter of the call is the name of the local array passed by reference and that contains string or numeric literals, where:

**Figure 3: EN^DDIOL API—Sample .array Input Parameter Array Name**

```
ARRAY(1) = string 1
ARRAY(2) = string 2 ...
ARRAY(n) = string n
```

Formatting instructions can also be included in this array.



**REF:** See “[Formatting for Arrays](#)” in the “[Details and Features](#)” section.

**global\_root:** (Optional) An alternate way to pass the text to the call is in a global root. In that case, the first parameter is null, and the second parameter contains the name of the global root that contains string or numeric literals, where:

**Figure 4: EN^DDIOL API—Sample global\_root Input Parameter (1 of 2)**

```
@GLOBAL_ROOT@(1,0) = string 1
@GLOBAL_ROOT@(2,0) = string 2 ...
@GLOBAL_ROOT@(n,0) = string n
```

Or:

**Figure 5: EN^DDIOL API—Sample global\_root Input Parameter (2 of 2)**

```
@GLOBAL_ROOT@(1) = string 1
@GLOBAL_ROOT@(2) = string 2 ...
@GLOBAL_ROOT@(n) = string n
```

Formatting instructions can also be included in this global array.



REF: See “[Formatting for Arrays](#)” section.

format:

(Optional) Formatting instructions controlling how the string is written or placed in the array. You can specify:

- One or more new lines before the string (!, !!, !!!, etc.)
- Horizontal position of string (?n)
- Can be any number of ! characters optionally followed by ?n, where n is an integer expression.

The default FORMAT is !.

This parameter can only be used when call format is used to pass a *single* string or numeric literal to EN^DDIOL. To pass formatting instructions when text is passed as an *array* or *global* to EN^DDIOL.



REF: See “[Formatting for Arrays](#)” section.

### 2.3.3.1 Examples

#### 2.3.3.1.1 Example 1

Suppose a Write Identifier node contains the following WRITE statement, as shown in [Figure 6](#):

**Figure 6: EN^DDIOL—Example: Write Identifier Node**

```
^DD(filenum,0,"ID","W1")=W "    ",$P(^0),U,2)
```

An equivalent statement converted to use EN^DDIOL is shown in [Figure 7](#):

**Figure 7: EN^DDIOL—Example: Write Identifier Node Converted**

```
^DD(filenum,0,"ID","W1")=D EN^DDIOL("    _$P(^0),U,2)","","?0")
```

#### 2.3.3.1.2 Example 2

The executable help of a field passes one line of text by value to the Loader as illustrated in [Figure 8](#):

**Figure 8: EN^DDIOL—Example: Input**

```
>D EN^DDIOL("This is one line of text.",",", "!?12")
```

If the call is made in scroll mode (e.g., ^DIE executes the executable help), [Figure 9](#) is an example of what the Loader writes to the screen:

**Figure 9: EN^DDIOL—Example: Output in Scroll Mode**

```
This is one line of text.
```

If the call is made in DBS mode, the Helper (HELP^DIE) executes the executable help. The text is placed into the ^TMP global as shown in [Figure 10](#):

**Figure 10: EN^DDIOL—Example: Output in DBS Mode**

```
^TMP("DIHELP", $J, 1) = ""
^TMP("DIHELP", $J, 2) = "        This is one line of text."
```

### 2.3.3.1.3 Example 3

[Figure 11](#) is an example of passing an array of text to the Loader:

**Figure 11: EN^DDIOL—Example: Input Passing a Text Array**

```
>S A(1)="First line."
>S A(2)="Second line, preceded by one blank line or node."
>S A(2,"F")="!!!"
>S A(3)="More text on second line."
>S A(3,"F")="??55"
>D EN^DDIOL(.A)
```

### 2.3.3.1.4 Example 4

[Figure 12](#) is an example of passing a global that contains text to the Loader:

**Figure 12: EN^DDIOL—Example: Input Passing a Global Containing Text**

```
S ^GLB(1)="First line."
S ^GLB(2)="Second line, preceded by one blank line or node."
S ^GLB(2,"F")="!!!"
S ^GLB(3)="More text on second line."
S ^GLB(3,"F")="??55"
D EN^DDIOL("", ^GLB)
```

## 2.3.3.2 Details and Features

### 2.3.3.2.1 Formatting for Arrays

When you pass an array or a global to EN^DDIOL, you can also pass formatting instructions for each line of text in your array or global. These instructions control how the string is written or placed in the output array. You can specify:

- One or more new lines before the string (!, !!, !!!, etc.)
- Horizontal position of string (?*n*)

Place the formatting instructions for a line of text in an “F” node descendent from the node containing the text. The value of each “F” node can be any number of ! characters optionally followed by ?*n*, where *n* is an integer expression. The default is !.



For example:

**Figure 13: EN^DDIOL—Sample Formatting for Arrays**

```
A(1) = string 1
A(1,"F") = format (e.g., "!?35", "?10", etc.)
^G(1,0) = string 1

^G(1,"F") = format
^G(1) = string 1
^G(1,"F") = format
```



**NOTE:** If you use format (1) to pass a single string of text to EN^DDIOL, you can pass the formatting instructions in the third parameter, **format**.

### 2.3.4 ^DIAC: File Access Determination

The ^DIAC API determines if a user has access to a file.

#### Input Variables

- DIFILE: (Required) The file number of the file on which you want to verify file access.
- DIAC: (Required) Use one of the values listed below to verify the specified type of file access:
- **“RD”**—Verify READ access to a specific file.
  - **“WR”**—Verify WRITE access to a specific file.
  - **“AUDIT”**—Verify AUDIT access to a specific file.
  - **“DD”**—Verify DD access to a specific file.
  - **“DEL”**—Verify DELETE access to a specific file.
  - **“LAYGO”**—Verify LAYGO access to a specific file.

#### Output Variables

- DIAC: DIAC returns either a **0** or a **1**:
- **1**—Indicates that the user has that type of access to the file.
- 
- NOTE:** If the user's **DUZ(0)**="@", the value **1** is always returned.
- **0**—Indicates that the user does *not* have access of that type to the file.

%: The % variable returns exactly the same values as DIAC.

### 2.3.5 EN^DIB: User Controlled Editing

The EN^DIB API invokes the Enter or Edit File Entries option [DIEDIT] of VA FileMan to edit records in a given file, allowing the user to select the fields to edit.

#### Input Variables

DIE: (Required) The global root of the file in any of the following forms:

- ^GLOBAL(
- ^GLOBAL(#
- Number of the file

DIE("NO^"): (Optional) Allows the developer control of the use of the caret (^) in an edit session. If this variable does *not* exist, unrestricted use of the caret for jumping and exiting is allowed.

The variable can be set to one of the following:

**Table 13: EN^DIB: User Controlled Editing API**

Set To	Description
"OUTOK"	Allows exiting and prevents all jumping.
"BACK"	Allows jumping back to a previously edited field and does <i>not</i> allow exiting.
"BACKOUTOK"	Allows jumping back to a previously edited field and allows exiting.
"Other value"	Prevents <i>all</i> jumping and does <i>not</i> allow exiting.

DIDEL: (Optional) Allows you to override the Delete Access on a file or subfile. Setting DIDEL equal to the number of the file before calling DIE allows the user to delete an entire entry from that file even if the user does *not* normally have the ability to delete. This variable does *not* override the DEL-nodes described in the ["Global File Structure"](#) section.

### 2.3.6 ^DIC: Lookup/Add with "B" Cross-References

Given a lookup value, the ^DIC API searches a file and does the following:

- Finds a matching entry.
- Adds an entry.
- Returns a condition indicating that the lookup was unsuccessful.



**REF:** For a comparison of how they each perform lookups, see the [IX^DIC: Lookup/Add](#) and [MIX^DIC1: Lookup/Add](#) APIs.

Except for the **DIC("W")** variable, which is KILLED, the **DIC** input array is left unchanged by ^DIC.

## Input Variables

**DIC:** (Required) The file number or an explicit global root in either of the following forms:

- ^GLOBAL(
- ^GLOBAL(X,Y,

**DIC(0):** (Optional) A string of alphabetic characters that alter how DIC responds. At a minimum, this string *must* be set to null. A detailed description of these characters can be found in the "[DIC\(0\) Input Variables in Detail](#)" section.



**NOTE:** If **DIC(0)** is null or undefined, no terminal output is generated by the DIC routine.

The acceptable characters are:

- **A**—Ask the entry; if erroneous, ask again.
- **B**—Only the “**B**” index is used when doing lookup to files pointed-to by starting file.
- **C**—Cross-reference suppression is turned off.
- **E**—Echo information.
- **F**—Forget the lookup value.
- **I**—Ignore the special lookup program.
- **K**—Primary **Key** is used as starting index for the lookup.
- **L**—Learning a new entry is allowed.
- **M**—Multiple-index lookup allowed.
- **N (Uppercase)**—Internal Number lookup allowed (but *not* forced).
- **n (Lowercase)**—Partial matching on pure **numeric** entries.
- **O**—Only find **One** entry if it matches exactly.
- **Q**—Question erroneous input (with two ??).
- **S**—Suppresses display of **.01** (except “**B**” cross-reference match) and of any Primary Key fields.
- **T**—ConTinue searching all indexes until user selects an entry or enters two carets (^ ^) to get out.
- **U**—Untransformed lookup.
- **V**—Verify that looked-up entry is OK.
- **X**—EXact match required.

- **Z**—Zero node returned in **Y(0)** and external form in **Y(0,0)**.

**X:** (Optional) If **DIC(0)** does *not* contain an **A**, then the variable **X** *must* be defined equal to the value you want to find in the requested indexes.

If a lookup index is on a **POINTER** or **VARIABLE POINTER** field, VA FileMan searches the “**B**” index on the pointed-to file for a match to the lookup value **X** [unless the developer uses the **DIC(“PTRIX”)** array to direct the search to a different index on the pointed-to file].

If the lookup index is compound (i.e., has more than one data subscript), then **X** can be an array **X(n)** where **n** represents the position in the subscript. For example, if **X(2)** is defined, it is used as the lookup value to match to the entries in the second subscript of the index. If only the lookup value **X** is passed, it is assumed to be the lookup value for the first subscript in the index, **X(1)**.

**DIC(“A”):** (Optional) A prompt that is displayed prior to the reading of the **X** input. If **DIC(“A”)** is *not* defined, the following prompt contents are displayed:

- The word **Select**.
- The name of the file [i.e., **\$P(^GLOBAL(0),“^”,1)**].
- A space.
- The **LABEL** of the **.01** field.
- A colon (:).

If the file name is the same as the **LABEL** of the **.01** field, then only the file name is displayed. **DIC(0)** *must* contain an **A** for this prompt to be issued.

For example, if the (fictitious) **EMPLOYEE** file had a **.01** field with the **LABEL** of **NAME**, VA FileMan would issue the following prompt:

```
Select EMPLOYEE NAME :
```

By setting **DIC(“A”)="Enter Employee to edit: "**, the prompt would be:

```
Enter Employee to edit :
```

Notice that it is necessary for the prompt in **DIC(“A”)** to include the colon and space at the end of the prompt if you want those to be displayed.

If the lookup index is compound (i.e., has more than one data subscript), then **DIC(“A”)** can be an array **DIC(“A”,n)** where **n** represents the position in the subscript. For example, **DIC(“A”,2)** is used as the prompt for the second subscript in the index. If only the single prompt **DIC(“A”)** is passed, it is assumed to be the prompt for the first subscript in the index **DIC(“A”,1)**.

If **DIC(“A”,n)** is undefined for the **n**th subscript, then the “Lookup Prompt” field for that subscript from the **INDEX (#.11)** file is used as the prompt, or if it is null, the **LABEL** of the field from the data dictionary.

**DIC(“B”):** (Optional) The default answer that is presented to the user when the lookup prompt is issued. If a terminal user simply presses the **Enter** key, the **DIC(“B”)** default value is used, and returned in **X**. **DIC(“B”)** is only used if it is *non-null*.

If the lookup index is compound (i.e., has more than one data subscript), then **DIC("B")** can be an array **DIC("B",*n*)** where *n* represents the position in the subscript. For example, **DIC("B",2)** is used as the default answer for the prompt for the second subscript in the index. If only the single default answer **DIC("B")** is passed, it is assumed to be the default answer for the prompt for the first subscript in the index **DIC("B",1)**.

DIC("DR"):

(Optional) When calling DIC with LAYGO allowed, you can specify that a certain set of fields is asked for in the case where the user enters a new entry. This list is specified by setting the variable **DIC("DR")** equal to a string that looks exactly like the **DR** string of fields that is specified when calling [^DIE](#). Such a list of what VA FileMan calls forced identifiers overrides any identifiers that would normally be requested for new entries in this file.

DIC("P")

(Optional) The developer is no longer required to set **DIC("P")**. The only exception to this is for a few files that are *not* structured like a normal VA FileMan file; where the first subscript of the data is variable in order to allow several different "globals" to use the same DD. An example of this is the VA FileMan Audit files; where the first subscript is the file number of the file being audited.

This variable is needed to successfully add the FIRST subentry to a Multiple when the descriptor (or header) node of the Multiple does *not* exist. In that situation, **DIC("P")** should be set equal to the subfile number and subfile specifier codes for the Multiple.



**REF:** See the "[File Header](#)" section.

If the descriptor node for the Multiple already exists, **DIC("P")** has no effect.

In order to automatically include any changes in the field's definition in **DIC("P")**, it is best to set this variable to the second ^-piece of the 0-node of the Multiple field's definition in the DD.



**REF:** See the "[Field Definition 0-Node](#)" section.

Thus, for example, if File #16150 had a Multiple Field #9, set DIC("P") like this:

```
>S DIC("P")=$P(^DD(16150,9,0),"^",2)
```



**REF:** For more information, see the "[Adding New Subentries to a Multiple](#)" section.

DIC("PTRIX",f,p,t)=d: (Optional) Where:

- **f**—from (pointing) file number.
- **p**—pointer field number.
- **t**—pointed-to file number.
- **d**—caret (^)-delimited list of index names.

When doing a lookup using an index for a POINTER or VARIABLE POINTER field, this new array allows the user to pass a list of indexes that is used when searching the pointed-to file for matches to the lookup value.

For example, if the (fictitious) File #662001 has a pointer Field #5 to File #200 (NEW PERSON), and you wanted the lookup on File #200 to be either by name (“B” index), or by the first letter of the last name concatenated with the last 4 digits of the social security number (“BS5” index):

```
DIC("PTRIX",662001,5,200)="B^BS5"
```

If the call allows records to be added to a pointed-to file, then the list in the “PTRIX” entry should contain the “B” index. However, the “B” index would *not* need to be included in the list if the first index in the “PTRIX” array entry is a compound index whose first subscript is the .01 field.

DIC(“S”):

(Optional) **DIC(“S”)** is a string of M code that DIC executes to screen an entry from selection. **DIC(“S”)** *must* contain an **IF** statement to set the value of **\$T**. Those entries that the **IF** sets as **\$T=0** are *not* displayed or selectable. When the **DIC(“S”)** code is executed, the local variable **Y** is the internal number of the entry being screened and the M Naked Indicator is at the global level **@(DIC\_“Y,0”)**. Therefore, to use the previous example again, if you wanted to find a male employee whose name begins with FMEMPLOYEE, you would:

```
S DIC="^EMP( ",DIC(0)="QEZ",X="FMEMPLOYEE"  
S DIC("S")="I $P(^(),U,2)="M" "  
D ^DIC
```

DIC(“T”):

(Optional) Present every match to the lookup value, quitting only when user either selects one of the presented entries, enters two carets (^ ^) to quit, or there are no more matching entries found.

Currently, if one or more matches are found in the first pass through the indexes, then VA FileMan quits the search, whether or not one of the entries is selected. Only if no matches are found in the first pass does VA FileMan continue on to try transforms to the lookup value. This includes transforms to find internal values of pointers, variable pointers, dates, or sets.

Another feature of the **T** flag is that indexes are truly searched in the order requested. If, for example, an index on a pointer field comes before an index on a free-text field, matches from the pointer field are presented to the user before matches to the free-text field.

When used in combination with the **O** flag, all indexes are searched for an exact match. Then, only if none are found, does VA FileMan make a second pass through the indexes looking for partial matches.

DIC(“V”):

(Optional) If the .01 field is a VARIABLE POINTER, it can point to entries in more than one file. You can restrict the user’s ability to input entries from certain files by using the **DIC(“V”)** variable. It is used to screen files from the user. Set the **DIC(“V”)** variable to a line of M code that returns a truth value when executed. The code is executed after someone enters data into a VARIABLE

POINTER field. If the code tests **false**, the user's input is rejected; VA FileMan responds with ?? and an audible sound ("beep").

If the lookup index is compound (i.e., has more than one data subscript), and if any of the subscripts index VARIABLE POINTER fields, then **DIC("V",n)** can be passed where "n" represents the subscript position of the VARIABLE POINTER field in the index. For example, if **DIC("V",2)** is passed in, it is used as the screen for files pointed-to by the VARIABLE POINTER field indexed in the second subscript of the index. If only the entry **DIC("V")** is passed, it is assumed to be the variable pointer file screen for the first subscript in the index, **DIC("V",1)**.

When the user enters a value at a VARIABLE POINTER field's prompt, VA FileMan determines in which file that entry is found. The variable **Y(0)** is set equal to information for that file from the data dictionary definition of the VARIABLE POINTER field. You can use **Y(0)** in the code set into the **DIC("V")** variable. **Y(0)** contains:

**Table 14: ^DIC API—Variable Pointer Screen: DIC("V") Variable Y(0) Contents**

^-Piece	Contents
Piece 1	File number of the pointed-to file.
Piece 2	Message defined for the pointed-to file.
Piece 3	Order defined for the pointed-to file.
Piece 4	Prefix defined for the pointed-to file.
Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.
Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed to file.

All of this information was defined when that file was entered as one of the possibilities for the VARIABLE POINTER field.

For example, suppose your **.01** field is a variable pointer pointing to (fictitious) Files #1000, #2000, and #3000. If you only want the user to be able to enter values from Files #1000 or #3000, you could set up **DIC("V")** like this:

```
S DIC("V")="I +Y(0)=1000!(+Y(0)=3000)"
```

**DIC("W"):**

(Optional) An M command string that is executed when DIC displays each of the entries that match the user's input. The condition of the variable **Y** and of the naked indicator is the same as for **DIC("S")**. If **DIC("W")** is defined, it overrides the display of any identifiers of the file. Thus, if **DIC("W")=""**, the display of identifiers are suppressed.



**NOTE:** **DIC("W")** is KILLED by ^DIC calls.

**DIC("?N",file#)=n:**

(Optional) The number "**n**" should be an integer set to the number of entries to be displayed on the screen at one time when using **?-help** in a lookup. Usually, file#

is the number of the file on which you are doing the lookup. However, if doing a lookup using an index on a pointer field, and if DIC(0) contains **L**, then the user also is allowed to see a list of entries from the pointed-to file, so in that case file# could be the number of that pointed-to file. For example, when doing a lookup in test File #662001, if the developer wants only five entries at a time to be displayed in question-mark help, set DIC(“?N”,662001)=5.

DIC(“?PARAM”, file#,”INDEX”)=Index name:

(Optional) Used to control entries displayed during online ?-help only. If provided, this index is used to display the entries from the file specified by file#. Otherwise, VA FileMan uses the first lookup index specified for the ^DIC call. This value is used as the **index** parameter to the Lister call to display the entries.



**REF:** For detailed information, see the [LIST^DIC\(\): Lister API](#).

DIC(“?PARAM”, file#,”FROM”,n)=value:

(Optional) Used to control entries displayed during online ?-help only. This array can be set to define a starting value for an entry in the lookup index used to list entries from the file. Integer value “n” is associated with the “n<sup>th</sup>” data value subscript in the index (e.g., regular old-style indexes always have just one indexed data value, so “n” would be **1**). If a starting value is defined for subscript “n,” then starting values *must* also be defined for all of the subscripts preceding “n.”

This information is used to set the **from** parameter for a call to [LIST^DIC](#) in order to display the entries in the file specified by file#. Therefore, the entries *must* meet the same rules as the **from** parameter described in the [LIST^DIC](#) call.



**REF:** For detailed information, see the [LIST^DIC\(\): Lister API](#).

If DIC(0) contains an **L** and the first indexed field is a pointer, then after displaying the current entries on the file, VA FileMan allows the user to see entries on the pointed-to file. In that case, the developer can request starting values for any pointed-to file in the pointer chain. If the user enters “^value” when asked whether they wish to see the entries in the file, the value entered by the user overrides the starting list value passed by the developer in this array.

DIC(“?PARAM”, file#,”PART”,n)=value:

(Optional) Used to control entries displayed during online ?-help only. This array can be set to define partial match values for each of the “n” subscripts on the lookup index used during online help. The information is used to set the **part** parameter for a Lister call to display the entries.



**REF:** For detailed information, see the [LIST^DIC\(\): Lister API](#).

As with DIC(“?PARAM”,file#,”FROM”,n), if DIC(0) contains **L**, the developer can define partial match values for any pointed-to file in the pointer chain.

DLAYGO:

(Optional) If this variable is set equal to the file number, then the user is able to add a new entry to the file, whether or not they have LAYGO access to the file. This variable, however, does *not* override any LAYGO node that may exist on



the **.01** field [i.e., `^DD(file#,.01,"LAYGO",#,0)`]. M code in the LAYGO node is still executed, and *must* set the truth value to **TRUE** for an entry to be added.



**NOTE:** In addition, **DIC(0)** *must* contain **L** to allow addition of entries to the file.

**DINUM:** (Optional) This input variable identifies the subscript at which the data is to be stored. This means **DINUM** *must* be a canonic number and that no data exists in the global at that subscript location [e.g., `$D(@ (DIC_DINUM_"))=0`].

## Output Variables

**Y:** DIC always returns the variable **Y**. The variable **Y** is returned with one of these three formats:

- **Y=-1**—The lookup was unsuccessful.
- **Y=N^S**—**N** is the internal number of the entry in the file and **S** is the value of the **.01** field for that entry.
- **Y=N^S^1**—**N** and **S** are defined as above and the **1** indicates that this entry was just added to the file.

**Y(0):** This variable is only set if **DIC(0)** contains a **Z**. When the variable is set, it is equal to the entire zero node of the entry that was selected.

**Y(0,0):** This variable also is only set if **DIC(0)** contains a **Z**. When the variable is set, it is equal to the external form of the **.01** field of the entry.

The following are examples of returned **Y** variables based on a call to the (fictitious) EMPLOYEE file stored in the (fictitious) ^EMP( global:

```
>S DIC="^EMP( ",DIC(0)="QEZ",X="FMEMPLOYEE"  
>D ^DIC
```

Returned are:

```
Y      = "7^FMEMPLOYEE,ONE"  
Y(0)  = "FMEMPLOYEE,ONE^M^2231109^2"  
Y(0,0) = "FMEMPLOYEE,ONE"
```

If the lookup had been done on a file whose **.01** field points to the (fictitious) EMPLOYEE file, the returned variables might look like this:

```
Y      = "32^7" [ Entry #32 in this file and #7  
              in EMPLOYEE file.]  
Y(0)  = "7^RX 2354^ON HOLD"  
Y(0,0) = "FMEMPLOYEE,ONE" [.01 field of entry 7  
              in EMPLOYEE file]
```

**X** Contains the value of the field where the match occurred.

If the lookup index is compound (i.e., has more than one data subscript), and if **DIC(0)** contains **A** so that the user is prompted for lookup values, then **X** is output as an array **X(n)** where **n** represents the position in the subscript and contains the values from the index on which the entry was found. Thus, **X(2)**

would contain the value of the second subscript in the index. If possible, the entries are output in their external format (i.e., if the subscript is *not* computed and does *not* have a transform). If the entry is *not* found on an index (e.g., when lookup is done with **X**=“ ” [the <Spacebar><Enter> feature]), then **X** and **X(1)** contain the user input, but the rest of the **X** array is undefined.

DTOUT: This is only defined if DIC has timed-out waiting for input from the user.

DUOUT: This is only defined if the user entered a caret (^).

### 2.3.6.1 DIC(0) Input Variables in Detail

The effects of the various characters that can be contained in **DIC(0)** are described below:

- A** DIC asks for input from the terminal and asks again if the input is erroneous. A response of null or a string containing a caret (^) is accepted. Input is returned in **X** when DIC quits. If **DIC(0)** does *not* contain the character **A**, the input to DIC is assumed to be in the local variable **X**.
- B** Without the **B** flag, if there are cross-referenced **POINTER** or **VARIABLE POINTER** fields in the list of indexes to use for lookup and if **DIC(0)** contains **M** and there is no screening logic on the pointer that controls the lookup on the pointed-to file, then:
  - For each cross-referenced pointer field, VA FileMan checks *all* lookup indexes in each pointed-to file for a match to **X** (time-consuming).
  - If **X** matches any value in any lookup index (not just the “**B**” index) on the pointed-to file and the IEN of the matched entry is in the home file’s pointer field cross-reference, VA FileMan considers this a match. This perhaps may *not* be the lookup behavior you wanted (see “[Examples](#)”).The **B** flag prevents this behavior by looking for a match to **X** only in the “**B**” index (**.01** field) of files pointed to by cross-referenced **POINTER** or **VARIABLE POINTER** fields. This makes lookups quicker and avoids the risk of VA FileMan matching an entry in the pointed-to file based on some unexpected indexed field in that file.
- C** Normally, when DIC does a lookup and finds an entry that matches the input, that entry is presented to the user only once, even if the entry appears in more than one cross-reference. This is called cross-reference suppression and can be overridden by including a **C** in **DIC(0)**. If, for example, a person with the name **FMPATIENT,20** is an entry in a file, then his name appears in the “**B**” cross-reference of the file. If he has a nickname of **20**, which is in the “**C**” cross-reference of the file, then when a user enters **20** as a lookup value, the name, **FMPATIENT,20**, appears only once in the choices. But if there is a “**C**” in **DIC(0)**, then **FMPATIENT,20** appears twice in the choices; once as a hit in the “**B**” cross-reference and again as a hit in the “**C**” cross-reference.
- E** The file entry names that match the inputs are echoed back to the terminal screen; and if there is more than one such name, the user is asked to choose which entry is wanted. **E** is important, because it is the way to tell DIC that you are in an interactive mode and are expecting to be able to receive input from the user.
- F** Prevents saving the entry number of the matched entry in the **^DISV** global. Ordinarily, the entry number is saved at **^DISV(DUZ,DIC)**. This allows the user to do a subsequent lookup of the same entry simply by pressing the **Spacebar**

and **Enter** keys (<Spacebar><Enter>). To avoid the time cost of setting this global, include an **F** in **DIC(0)**.

**I** If **DIC(0)** contains **I**, any special user-written lookup program for a file is ignored and DIC proceeds with its normal lookup process.

You can write a special lookup program to be used to find entries in a particular file. This special program can be defined by using the Edit File option [DIEDFILE] of the Utility Functions menu [DIUTILITY].



**REF:** For more information, see the “[Special Lookup Programs](#)” section in the “[Advanced File Definition](#)” section.

When a lookup program is defined, VA FileMan bypasses the normal lookup process of DIC and branch to the user-written program. This user-written lookup program *must* respond to the variables documented in this section and provide the functionality of DIC as they pertain to the file.

**K** The **K** flag causes ^DIC to use the Uniqueness index for the Primary Key as the starting index for the lookup, rather than starting with the “**B**” index. (If developers want to specify some other index as the starting index, then they can specify the index by using the **D** input variable, and either the [IX^DIC: Lookup/Add](#) or [MIX^DIC1: Lookup/Add](#) APIs instead of ^DIC.)

**L** If **DIC(0)** contains **L** and the user’s input is in valid format for the file’s **.01** field, then DIC allows the user to add a new entry to the file at this point (LAYGO: Learn-As-You-GO), as long as at least one of these four security-check conditions is true:

- The local variable **DUZ(0)** is equal to the at-sign (@).
- If Kernel’s File Access Security System (formerly known as Kernel Part 3) is being used for security, the file is listed in the user’s record of accessible files with LAYGO access allowed.
- If file access management is *not* being used, a character in **DUZ(0)** matches a character in the file’s LAYGO access code or the file has no LAYGO access code.
- The variable DLAYGO is defined equal to the file number.



**NOTE:** Even if **DIC(0)** contains **L** and one of these security checks is passed, LAYGO is *not* allowed if a test in the data dictionary’s LAYGO node fails.

**M** If **DIC(0)** contains **M**, DIC does a multiple lookup on all of the file’s cross-references from “**B**” on to the end of the alphabet. For example, if a given file is cross-referenced both by Name and by Social Security Number, and the user inputs 000-45-6789, DIC, failing to find this input as a Name, automatically goes on to look it up as a Social Security Number.



**REF:** For finer control in specifying the indexes used for lookup, see the alternate lookup entry points [IX^DIC: Lookup/Add](#) and [MIX^DIC1: Lookup/Add](#) APIs.

**N** If **DIC(0)** contains uppercase **N**, the input is allowed to be checked as an internal entry number, even if the file in question is not normally referenced by number. However, input is only checked as an IEN if no other matches are found during regular lookup.

If **DIC(0)** does *not* contain an uppercase **N**, the user is still allowed to select by entry number by preceding the number with the grave accent (`) character. When a ` is used, the lookup is limited to internal entry numbers only.

Placing an uppercase **N** in **DIC(0)** does *not* force IEN interpretation; it only permits it. In order to force IEN interpretation, you *must* use the grave accent (`) character.



**NOTE:** With this flag, when **DIC(0)** contains an **L**, users may be allowed to force the internal entry number when adding new entries to the file. If the user enters a number **N** that is *not* found on any of the cross-references, and if the **.01** field is *not* numeric, and the file is *not* DINUMed, and if VA FileMan can talk to the users (**DIC(0)**["**E**"]), then the user is asked whether they want to add the new entry, and are prompted for the value of the **.01** field. The entry is added at the record number **N** that was originally entered by the user.

If there is a **.001** field on the file, the number **N** *must* also pass the INPUT transform for the **.001** field.

**n** If the lowercase **n** flag is put into **DIC(0)**, then if the lookup value is numeric and if a lookup is done on a free text or set of codes field, partial matches on pure numerics are found. Suppose a free text field has records with the values 2, 223, and 22A, and the lookup value is 2. Without the lowercase **n** flag, only the records with the values 2 and 22A are found. With the lowercase **n** flag, all three are found.

**O** If **DIC(0)** contains the letter **O**, then for each index searched, VA FileMan looks first for exact matches to the lookup value before looking for partial matches. If an exact match is found, then VA FileMan returns only that match and none of the partial matches on the index. Thus, if an index contained the entries "FMEMPLOYEE,ONE" and "FMEMPLOYEE,ONENESS" and if the user typed a lookup value of "FMEMPLOYEE,ONE," then only the "FMEMPLOYEE,ONE" entry would be selected, and the user would never see the entry "FMEMPLOYEE,ONENESS."



**NOTE:** If partial matches but no exact matches are found in the first indexes searched, and if exact matches are found in an index searched later, then the partial matches from the first indexes are returned along with the exact match from the later indexes.

**Q** If **DIC(0)** contains **Q** and erroneous input is entered, two question marks (??) are displayed and the user hears an audible sound ("beep").

**S** If **DIC(0)** does *not* contain **S**, the value of the **.01** field and Primary Key fields (if the file has a Primary Key) is displayed for all matches found in any cross-reference. If **DIC(0)** does contain **S**, the **.01** field and Primary Key fields are *not*

displayed unless they are one of the indexed fields on which the match was made.

- T** **T** flag in **DIC(0)**. Present every match to the lookup value, quitting only when:
- User selects one of the presented entries.
  - User enters two carets (^ ^) to quit.
  - There are no more matching entries found.

Currently, if one or more matches are found in the first pass through the indexes, then VA FileMan quits the search, whether or not one of the entries is selected. Only if no matches are found in the first pass does VA FileMan continue on to try transforms to the lookup value. This includes transforms to find internal values of pointers, variable pointers, dates, or sets.

Another feature of the **T** flag is that indexes are truly searched in the order requested. If, for example, an index on a pointer field comes before an index on a free-text field, matches from the pointer field are presented to the user before matches to the free-text field. When used in combination with the **O** flag, all indexes are searched for an exact match. Then, only if no matches are found, does VA FileMan make a second pass through the indexes looking for partial matches.

- U** Normally, the lookup value is expected to be in external format (for dates, pointers, etc.). VA FileMan first searches the requested index for a match to the user input as it was typed in. Then, if no match is found, VA FileMan automatically tries certain transforms on the lookup value.

For instance, if one of the lookup indexes is on a date field, VA FileMan tries to transform the lookup value to an internal date, and then checks the index again. The **U** flag causes VA FileMan to look for an exact match on the index and to skip any transforms. Thus, the lookup value *must* be in VA FileMan internal format. This is especially useful for lookups on indexed pointer fields, where the internal entry number (i.e., internal pointer value) from the pointed-to file is already known.

Ordinarily, this flag would not be used along with the **A**, **B**, **M**, **N**, or **T** flags. In many cases it makes sense to combine this with the **X** flag.

- V** If **DIC(0)** contains **V** and only one match is made to the user's lookup value, then they are asked "OK?", and they have to verify that the looked-up entry is the one they wanted. This is an on-the-fly way of getting behavior similar to the permanent flag that can be set on a file by answering "**YES**" to the question "ASK 'OK' WHEN LOOKING UP AN ENTRY?".



**REF:** For more information, see the Edit File option [DIEDFILE], available on the FileMan UTILITY Functions menu [DIUTILITY], which is described in the *VA FileMan Advanced User Manual*.

- X** If **DIC(0)** contains **X**, for an exact match, the input value *must* be found exactly as it was entered. Otherwise, the routine looks for any entries that begin with the input **X**. Unless "X-act match" is specified, lowercase input that fails in the lookup is automatically converted to uppercase, for a second lookup attempt. The difference between **X** and **O** (described above) is that **X** requires an exact match.

If there is *not* one, either DIC exits or tries to add a new entry. With **O**, if there is *not* an exact match, DIC looks for a partial match beginning with the input.

- Z** If **DIC(0)** contains **Z** and if the lookup is successful, then the variable **Y(0)** is also returned. It is set equal to the entire zero node of the entry that has been found. Another array element, **Y(0,0)**, is also returned and is set equal to the printable expression of the **.01** field of the entry selected. This has no use for DATA Type fields with values of FREE TEXT and NUMERIC unless there is an OUTPUT transform. However, for DATE/TIME, SET OF CODES, and POINTER field types, **Y(0,0)** contains the external format.

### 2.3.6.1.1 Adding New Subentries to a Multiple

You can use ^DIC or [FILE^DICN](#) to add new subentries to a Multiple. In order to add a subentry, the following variables need to be defined:

- DIC: (Required) Set to the full global root of the subentry. For example, if the Multiple is one level below the top file level: file's\_root,entry#,Multiple\_field's\_node.
- DIC(0): (Required) *Must* contain **L** to allow LAYGO.
- DIC("P"): (Required) Set to the 2nd piece of **0**-node of the Multiple field's DD entry.



**NOTE:** The developer is no longer required to set **DIC("P")**. The only exception to this is for a few files that are *not* structured like a normal VA FileMan file, where the first subscript of the data is variable in order to allow several different “globals” to use the same DD. An example of this is the VA FileMan Audit files where the first subscript is the file number of the file being audited.

- DA(1)... DA(n): (Required) Set up this array such that:
- **DA(1)**—IEN at the next higher file level above the Multiple in which the lookup is being performed.
  - **DA(2)**—IEN at the next higher file level (if any), etc.
  - **DA(n)**—IEN at the file's top-level.



**RECOMMENDATION:** The value of the unsubscripted DA node should *not* be defined when doing lookups in a subfile (i.e., the value you are trying to obtain)!

## 2.3.6.2 Examples

### 2.3.6.2.1 Example 1

[Figure 14](#) is an example of code that:

- Uses ^DIC to interactively select a top-level record.
- Uses ^DIC to select or create a subentry in a Multiple in that record.
- Uses ^DIE to edit fields in the selected or created subentry.

The file's root in this example is "**^DIZ(16150,**", the Multiple's field number is **9**, and the Multiple is found on node **4**. The code for this example is shown in [Figure 14](#):

**Figure 14: ^DIC—Sample Code to: Use ^DIC to Interactively Select a Top-level Record, Create a Subentry; and Use ^DIE to Edit Fields in the Subentry**

```

; a call is made to DIC so the user can select an entry in the file
;
S DIC="^DIZ(16150," ,DIC(0)="QEAL" D ^DIC
I Y=-1 K DIC Q ;quit if look-up fails
;
; a second DIC call is set up to select the subentry
;
S DA(1)=+Y ;+Y contains the internal entry number of entry chosen
S DIC=DIC_DA(1)_"",4," ;the root of the subfile for that entry
S DIC(0)="QEAL" ;LAYGO to the subfile is allowed
S DIC("P")=$P(^DD(16150,9,0),"^",2) ;returns the subfile# and specifiers
D ^DIC I Y=-1 K DIC,DA Q ;user selects or adds subentry
;
; a DIE call is made to edit fields in subfile
;
S DIE=DIC K DIC ;DIE now holds the subfile's root
S DA=+Y ;+Y contains the internal entry number of subentry chosen
S DR="1;2" D ^DIE ;edit fields number 1 and 2
K DIE,DR,DA,Y Q

```

### 2.3.6.2.2 Example 2

File #662002 has a **.01** field that points to the NEW PERSON (#200) file. In this example, you will use input arrays in DIC("PARAM",662002,"FROM",1) to start the list of entries in the "**B**" index of (fictitious) File #662002 with the letter **M**. Since **DIC(0)** contains **L** (user can add entries to the pointed-to File #200), VA FileMan also displays entries from the NEW PERSON (#200) file, so you use DIC("PARAM",200,"PART",1) to display only entries that start with the letter **S**.

**Figure 15: ^DIC—Sample Code to Display a List of Entries from two Different Files Starting with Different Letters (1 of 2)**

```

S DIC=^DIZ(662002,DIC(0)="AEQZL"
S DIC("PARAM",200,"PART",1)="S"
S DIC("PARAM",662002,"FROM",1)="M"

>D ^DIC

```

**Figure 16: ^DIC—Sample Code to Display a List of Entries from two Different Files Starting with Different Letters (2 of 2)**

```
Select FMEMPLOYEE,NINETY POINT TO NEW PERSON PERSON NAME: ??

Choose from:
FMEMPLOYEE,NINE MAR 02, 1948 DEVELOPER NF OIFO DEVELOPER
FMEMPLOYEE,FIVE APR 03, 1948 TEAM LEAD FF DEVELOPER
FMEMPLOYEE,EIGHT AUG 28, 1948 PROJECT MANAGER EF DEVELOPER
FMEMPLOYEE,SEVEN AUG 28, 1949 COMPUTER SPECIALIST SF DEVELOPER
FMEMPLOYEE,SIX JUN 12, 1955 COMPUTER SPECIALIST SF DEVELOPER
FMEMPLOYEE,ONE NOV 11, 1961 SYSTEMS ANALYST OF DEVELOPER
FMEMPLOYEE,THREE MAY 05, 1965 TEAM LEAD SF DEVELOPER
FMEMPLOYEE,FOUR JAN 01, 1969 COMPUTER SPECIALIST FF
FMEMPLOYEE,TWO JUL 07, 1977 COMPUTER SPECIALIST SF DEVELOPER

You may enter a new FMEMPLOYEE,NINETY POINT TO NEW PERSON, if you wish

Choose from:
SHARED,MAIL
FMEMPLOYEE,FOURTY
FMEMPLOYEE,TEN
FMEMPLOYEE,THIRTY
```

### 2.3.6.2.3 Example 3

In this example, you are using the same files as in [“Example 2”](#); you are displaying entries from the pointing (fictitious) File #662002, using the “AC” index, which sorts the entries by TITLE, and then by NAME. In this case, you limit the number of entries displayed at one time from both File #662002 and File #200 to 5.

**Figure 17: ^DIC—Example: Input to Display Entries from the Pointing File Using the “AC” Index**

```
S DIC="^DIZ(662002," ,DIC(0)="AEQZL"
S DIC("PARAM",662002,"INDEX")="AC"
S DIC("N",662002)=5
S DIC("N",200)=5

>D ^DIC
```



**Figure 18: ^DIC—Example: Output Prompts**

```
Select FMEMPLOYEE,NINETY POINT TO NEW PERSON PERSON NAME: ??

Choose from:
TEAM LEAD FMEMPLOYEE,SIXTY MAR 01, 1875 TEAM LEAD SF DEVELOPER
SYSTEMS ANALYST FMEMPLOYEE,ONE NOV 11, 1961 SYSTEMS ANALYST OF DEVELOPER
TEAM LEAD FMEMPLOYEE,SEVENTY FEB 05, 1950 TEAM LEAD SF
COMPUTER SPECIALIST FMEMPLOYEE,SEVEN AUG 28, 1949 COMPUTER SPECIALIST SF
COMPUTER SPECIALIST FMEMPLOYEE,FOUR JAN 01, 1969 COMPUTER SPECIALIST FF

You may enter a new FMEMPLOYEE,NINETY POINT TO NEW PERSON, if you wish

Answer with NEW PERSON NAME
Do you want the entire NEW PERSON List? Y <Enter> (Yes)
Choose from:
FMEMPLOYEE,EIGHTY EF DEVELOPER
FMEMPLOYEE,SIXTY SF DEVELOPER
FMEMPLOYEE,FORTY FF DEVELOPER
FMEMPLOYEE,SEVENTY SF DEVELOPER
FMEMPLOYEE,FIFTY FF DEVELOPER
```

### 2.3.7 IX^DIC: Lookup/Add Using User-Specified Cross-Reference

The IX^DIC API is similar to the ^DIC and MIX^DIC1 APIs, except for the way it uses cross-references to do a lookup. The three APIs that perform lookups are listed in [Table 15](#):

**Table 15: IX^DIC—Entry Points Lookups**

API Entry Point	Description
<a href="#">^DIC</a>	Lookup/Add Using “B” Cross-Reference: Starts with the “B” cross-reference or uses only the “B” cross-reference [unless K is passed in DIC(0)].
<b>IX^DIC</b>	Lookup/Add Using User-Specified Cross-Reference: Starts with the cross-reference you specify, or uses only the cross-reference you specify.
<a href="#">MIX^DIC1</a>	Lookup/Add Using User-Specified Set of Cross-References: Uses the set of cross-references you specify.

#### Input Variables (Required)



**NOTE:** All of the input variables described in [^DIC](#) can be used in the IX^DIC: Lookup/Add API

The following variables are required:

- DIC: (Required) The global root of the file (e.g., ^DIZ(16000.1)).
- DIC(0): (Required) The lookup parameters as previously described for [^DIC](#).
- D: (Required) The cross-reference in which to start looking. If DIC(0) contains M, then DIC continues the search on all other lookup cross-references, in alphabetical order. If it does *not*, then the lookup is only on the single cross-reference. This variable is KILLED by VA FileMan; it is undefined when the IX^DIC call is complete.

If **DIC(0)** contains **L**, (i.e., user is allowed to add a new entry to the file), then choose one of the following:

- **D** should be set to “**B**”.
- **D** should be set to an index that alphabetically comes before “**B**” and **DIC(0)** should contain **M**.
- **D** should contain the name of a compound index.

**X:** (Required) If **DIC(0)** does *not* contain an **A**, then the variable **X** *must* be defined equal to the value you want to look up.

If the lookup index is compound (i.e., has more than one data subscript), then **X** can be an array **X(n)**; where “**n**” represents the position in the subscript. For example, if **X(2)** is passed in, it is used as the lookup value to match to the entries in the second subscript of the index. If only the lookup value **X** is passed, it is assumed to be the lookup value for the first subscript in the index, **X(1)**.

### Input Variables (Optional)

All of the [^DIC](#) input variables can be used in the IX^DIC call. The following variables are optional:

DIC(“A”): (Optional This set of input variables affects the behavior of lookup as described for ^DIC.

DIC(“B”)

DIC(“DR”)

DIC(“P”)

DIC(“PTRIX”,f,p,t)=d DIC(“S”)

DIC(“V”)

DIC(“W”)

DIC(“?N”,file#)=n

### Output Variables

**Y:** DIC always returns the variable **Y**. The variable **Y** is returned in one of these three formats:

- **Y=-1**—The lookup was unsuccessful.
- **Y=N^S**—**N** is the Internal Entry Number of the entry in the file and **S** is the value of the **.01** field for that entry.
- **Y=N^S^1**—**N** and **S** are defined as above and the **1** indicates that this entry was just added to the file.

**Y(0):** This variable is only set if **DIC(0)** contains a **Z**. When the variable is set, it is equal to the entire zero node of the entry that was selected.

**Y(0,0):** This variable also is only set if **DIC(0)** contains a **Z**. When the variable is set, it is equal to the external form of the **.01** field of the entry.

The following are examples of returned **Y** variables based on a call to the (fictitious) EMPLOYEE file stored in the (fictitious) ^EMP( global:

```
>S DIC="^EMP(",DIC(0)="QEZ",X="FMEMPLOYEE"  
>D ^DIC
```

Returned is:

```
Y      = "7^FMEMPLOYEE,ONE"  
Y(0)  = "FMEMPLOYEE,ONE^M^2231109^2"  
Y(0,0) = "FMEMPLOYEE,ONE"
```

If the lookup had been done on a file whose **.01** field points to the (fictitious) EMPLOYEE file, the returned variables might look like this:

```
Y      = "32^7" [ Entry #32 in this file and #7 in  
                EMPLOYEE file.]  
Y(0)  = "7^RX 2354^ON HOLD"  
Y(0,0) = "FMEMPLOYEE,ONE" [.01 field of entry 7 in  
                EMPLOYEE file]
```

**X:** Contains the value of the field where the match occurred.

If the lookup index is compound (i.e., has more than one data subscript), and if **DIC(0)** contains an **A** so that the user is prompted for lookup values, then **X** is output as an array **X(n)**; where "**n**" represents the position in the subscript and contains the values from the index on which the entry was found. Thus, **X(2)** would contain the value of the second subscript in the index. If possible, the entries are output in their external format (i.e., if the subscript is *not* computed and does *not* have a transform). If the entry is *not* found on an index (e.g., when lookup is done with **X=" "** [the "**Spacebar Enter**" feature]), then **X** and **X(1)** contain the user input, but the rest of the **X** array is undefined.

**DTOUT:** This is only defined if DIC has timed-out waiting for input from the user.

**DUOUT:** This is only defined if the user entered a caret (^).

### 2.3.8 DO^DIC1: File Information Setup

The DO^DIC1 API retrieves a file's:

- File header node.
- Code to execute its identifiers.
- Its screen (if any).

It puts them into local variables for use during lookup into a file.

If **\$D(DO)** is greater than zero, DO^DIC1 quits *immediately*. If **DIC("W")** is defined before calling DO^DIC1, it is *not* changed.


#### Input Variables

**DIC:** The global root of the file [e.g., ^DIZ(16000.1,)].

**DIC(0):** The lookup parameters as previously described for [^DIC](#).

## Output Variables


DO: File **name**^**file** number and specifiers. This is the file header node.

 **NOTE:** Use the letter **O** (*not* the number zero) in this variable name.

DO(2): File number and specifiers. This is the second ^piece of **DO**. The **+DO(2)** always equals the file number.

DIC("W"): This is an executable variable that contains the write logic for identifiers. When an entry is displayed, the execution of this variable shows other information to help identify the entry. This variable is created by **\$ORDERing** through the data dictionary ID level. For example:

```
^DD(+DO(2),0,"ID",value)
```

 **NOTE:** The specifier, **I**, *must* be in **DO(2)** for VA FileMan to even look at the ID-nodes.

DO("SCR"): An executable variable that contains a file's screen (if any). The screen is an **IF** statement that can screen out certain entries in the file. This differs from **DIC("S")** in that it is used on every lookup regardless of input or output (i.e., the screen is applied to inquiries and printouts as well as to lookups). The value for this variable comes from **^DD(+DO(2),0,"SCR")** and the specifier "**s**" *must* be in **DO(2)**.

### 2.3.9 MIX^DIC1: Lookup/Add Using User-Specified Set of Cross-References

The MIX^DIC1 API is similar to the [^DIC](#) and [IX^DIC](#) APIs, except for the way it uses cross-references to do a lookup. The three entry points that perform lookups are listed in [Table 16](#):

**Table 16: DIC and DIC1 Entry Point Comparison**

API Entry Point	Description
<a href="#">^DIC</a>	Lookup/Add Using "B" Cross-Reference: Starts with the "B" cross-reference or uses only the "B" cross-reference [unless <b>K</b> is passed in <b>DIC(0)</b> ].
<a href="#">IX^DIC</a>	Lookup/Add Using User-Specified Cross-Reference: Starts with the cross-reference you specify or uses only the cross-reference you specify.
MIX^DIC1	Lookup/Add Using User-Specified Set of Cross-References: Uses the set of cross-references you specify.

## Input Variables (Required)



**NOTE:** All of the input variables described in ^DIC can be used in the MIX^DIC1 call.

The following variables are required.

DIC: (Required) The global root of the file [e.g., ^DIZ(16000.1,].  
DIC(0): (Required) The lookup parameters as previously described for [^DIC](#).  
D: (Required) The list of cross-references, separated by carets (^), to be searched (e.g., D="SSN^WARD^B"). If **DIC(0)** contains **L**, meaning that the user can add a new entry to the file, do either of the following:

- Include the “**B**” index in the list contained in **D**.
- Set **D** to the name of a compound index.

Make sure **DIC(0)** contains **M**; otherwise, only the first cross-reference in **D** is used for the lookup.

X: (Required) If **DIC(0)** does *not* contain an **A**, then the variable **X** *must* be defined equal to the value you want to look up.

If the lookup index is compound (i.e., has more than one data subscript), then **X** can be an array **X(n)**; where “**n**” represents the position in the subscript. For example, if **X(2)** is passed in, it is used as the lookup value to match to the entries in the second subscript of the index. If only the lookup value **X** is passed, it is assumed to be the lookup value for the first subscript in the index, **X(1)**.

## Input Variables (Optional)

All of the [^DIC](#) input variables can be used in the MIX^DIC1 call.

The following variables are optional:

DIC(“A”): (Optional) This set of input variables affects the behavior of lookup as described for [^DIC](#).

DIC(“B”)

DIC(“DR”)

DIC(“P”)

DIC(“PTRIX”,f,p,t)=d

DIC(“S”)

DIC(“V”)

DIC(“W”)

DIC(“?N”,file#)=n

## Output Variables

**Y:** DIC always returns the variable **Y**. The variable **Y** is returned in one of the three following formats:

- **Y=-1**—The lookup was unsuccessful.
- **Y=N^S**—**N** is the Internal Entry Number of the entry in the file and **S** is the value of the **.01** field for that entry.
- **Y=N^S^1**—**N** and **S** are defined as above and the **1** indicates that this entry was just added to the file.

**Y(0):** This variable is only set if **DIC(0)** contains a **Z**. When the variable is set, it is equal to the entire zero node of the entry that was selected.

**Y(0,0):** This variable also is only set if **DIC(0)** contains a **Z**. When the variable is set, it is equal to the external form of the **.01** field of the entry.

The following are examples of returned **Y** variables based on a call to the (fictitious) **EMPLOYEE** file stored in the (fictitious) **^EMP(** global:

```
>S DIC="^EMP( ",DIC(0)="QEZ",X="FMEMPLOYEE"  
>D ^DIC
```

Returned:

```
Y      = "7^FMEMPLOYEE,ONE"  
Y(0)  = "FMEMPLOYEE,ONE^M^2231109^2"  
Y(0,0) = "FMEMPLOYEE,ONE"
```

If the lookup had been done on a file whose **.01** field points to the (fictitious) **EMPLOYEE** file, the returned variables might look like this:

```
Y      = "32^7" [ Entry #32 in this file and #7 in  
                EMPLOYEE file.]  
Y(0)  = "7^RX 2354^ON HOLD"  
Y(0,0) = "FMEMPLOYEE,ONE" [.01 field of entry 7 in  
                EMPLOYEE file]
```

**X:** Contains the value of the field where the match occurred.

If the lookup index is compound (i.e., has more than one data subscript), and if **DIC(0)** contains an **A** so that the user is prompted for lookup values, then **X** is output as an array **X(n)**; where “**n**” represents the position in the subscript and contains the values from the index on which the entry was found. Thus, **X(2)** would contain the value of the second subscript in the index. If possible, the entries are output in their external format (i.e., if the subscript is *not* computed and does *not* have a transform). If the entry is *not* found on an index (e.g., when lookup is done with **X=“ ”** [the “**Spacebar Enter**” feature]), then **X** and **X(1)** contain the user input, but the rest of the **X** array is undefined.

**DTOUT:** This is only defined if DIC has timed-out waiting for input from the user.

**DUOUT:** This is only defined if the user entered a caret (^).

### 2.3.10 WAIT^DICD: Wait Messages

Use the WAIT^DICD API to display VA FileMan’s informational messages telling users that the program is working and they *must* wait a while. The selection of the phrase is random. There are no input or output variables.

Some sample messages are:

**Figure 19: WAIT^DICD API—Sample VA FileMan Informational Messages: “Wait” Type Messages**

```
...EXCUSE ME, I'M WORKING AS FAST AS I CAN...  
...SORRY, LET ME THINK ABOUT THAT A MOMENT...
```

### 2.3.11 FILE^DICN: Adds New Entry to File

The FILE^DICN API adds a new entry to a file. The INPUT transform is *not* used to validate the value being added as the .01 field of the new entry. This call does *not* override the checks in the LAYGO nodes of the data dictionary; they *must* still prove true for an entry to be added.

FILE^DICN can also be used to add subentries in Multiples.



**REF:** See the “[Adding New Subentries to a Multiple](#)” section in the description of [^DIC](#).

#### Variables to Kill

DO:

If **DO** is set, then VA FileMan assumes that all of the variables described as output in the call to [DO^DIC1](#) have been set as well, and that they describe the file to which you wish to add a new record. If you are *not* sure, then **DO** should be **KILLED** and the call sets it up for you based on the global root in **DIC**.



**NOTE:** This variable is **D** with the letter **O** (*not* the number zero).

#### Input Variables

DIC:

(Required) The global root of the file.

DIC(0):

(Required) A string of alphabetic characters that alter how DIC responds. At a minimum, this string *must* be set to null. The characters you can include are:

- **E**—Echo back information. This tells DIC that you are in an interactive mode and are expecting to be able to receive input from the user. If there are identifiers when adding a new entry, for example, the user can edit them as the entry is added if the **E** flag is used.
- **F**—Prevents saving the entry number of the matched entry in the **^DISV** global. Ordinarily, the entry number is saved at **^DISV(DUZ,DIC)**. This allows the user to do a subsequent lookup of the same entry simply by pressing the **Spacebar and Enter** keys (<**Spacebar**><**Enter**>). To avoid the time cost of setting this global, include an **F** in **DIC(0)**.
- **Z**—Zero node returned in **Y(0)** and external form in **Y(0,0)**.

DIC("P"): (Optional) The developer is no longer required to set **DIC("P")**. The only exception to this is for a few files that are *not* structured like a normal VA FileMan file, where the first subscript of the data is variable in order to allow several different "globals" to use the same DD. An example of this is the VA FileMan Audit files, where the first subscript is the file number of the file being audited.

Used when adding subentries in Multiples.



**REF:** See the description in the "[^DIC: Lookup/Add](#)" section.

DA: (Optional) Array of entry numbers.



**REF:** See the "[Adding New Subentries to a Multiple](#)" section in the description of [^DIC](#).

X: (Required) The internal value of the **.01** field, as it is to be added to the file. The developer is responsible for ensuring that *all* criteria described in the INPUT transform have been met. That means that the value **X** *must* be in VA FileMan internal format as it would be after executing the input transform. For example, a date *must* be in VA FileMan internal format "2690302", not "March 02, 1969". Also, local variables set by the input transform code *must* be set. For example, if the input transform sets **DINUM**, then **DINUM** *must* be set to the record number at which the entry *must* be added.

DINUM: (Optional) Identifies the subscript at which the data is to be stored (i.e., the internal entry number of the new record, shown as follows). This means that **DINUM** *must* be a canonic number and that no data exists in the global at that subscript location.

```
$D(@ (DIC_DINUM_ " " ) ) = 0
```

If a record already exists at the **DINUM** internal entry number, no new entry is made. The variable **Y** is returned equal **-1**.

DIC("DR"): (Optional) Used to input other data elements at the time of adding the entry. If the user does *not* enter these elements, the entry is *not* added. The format of **DIC("DR")** is the same as the variable **DR** described under the discussion of [^DIE](#).

If there are any required Identifiers for the file or if there are security keys defined for the file (in the KEY [#.31] file), and if **DIC(0)** does *not* contain an **E**, then the identifier and key fields *must* be present in **DIC("DR")** in order for the record to be added. If **DIC(0)** contains **E**, the user is prompted to enter the identifier and key fields, whether or not they are in **DIC("DR")**.

## Output Variables

Y: DIC always returns the variable **Y**, which can be in one of the two following values:

- **Y=-1**—Indicates the lookup was unsuccessful; no new entry was added.
- **Y=N^S^1**—**N** is the internal number of the entry in the file, **S** is the value of the **.01** field for that entry, and the **1** indicates that this entry was just added to the file.



Y(0):	This variable is only set if <b>DIC(0)</b> contains a <b>Z</b> . When it is set, it is equal to the entire zero node of the entry that was selected.
Y(0,0):	This variable is also only set if <b>DIC(0)</b> contains a <b>Z</b> . When it is set, it is equal to the external form of the <b>.01</b> field of the entry.
DTOUT:	This is only defined if DIC has timed-out waiting for input from the user.
DUOUT:	This is only defined if the user entered a caret (^).
X:	The variable <b>X</b> is returned unchanged from the input value.

### 2.3.12 YN^DICN: Reader for a Yes/No Response

The YN^DICN API is a reader for a **YES/NO** response. You *must* display the prompt yourself before calling YN^DICN. YN^DICN does the following:

1. Displays the question mark and the default response.
2. Reads and processes the response.
3. Returns %.



**RECOMMENDATION:** Instead of using this entry point, it is suggested that you use the generalized response reader [^DIR](#). [^DIR](#) gives you greater flexibility in displaying prompts and help messages and also presents more information about the user's response.

#### Input Variables

%:	(Optional) Determines the default response as follows: <ul style="list-style-type: none"> <li>• % = <b>0 (zero)</b>—No default</li> <li>• % = <b>1—YES</b></li> <li>• % = <b>2—NO</b></li> </ul>
----	--

#### Output Variables

%:	The processed user's response. It can be one of the following: <ul style="list-style-type: none"> <li>• % = <b>-1</b>—The user entered a caret (^).</li> <li>• % = <b>0 (zero)</b>—The user pressed the <b>Enter</b> key when no default was presented <i>or</i> the user entered a <b>?</b> (question mark).</li> <li>• % = <b>1</b>—The user entered a <b>YES</b> response.</li> <li>• % = <b>2</b>—The user entered a <b>NO</b> response.</li> </ul>
% Y:	The actual text that the user entered.

### 2.3.13 DQ^DICQ: Entry Display for Lookups

The DQ^DICQ API displays the list of entries in a file a user can see. It can be used to process question mark responses directly. If **DO** is *not* defined, the first thing that DQ^DICQ does is call [DO^DICI](#) to get the characteristics of the selected file.

#### Input Variables

- DIC: (Required) The global root of the file.
- DIC(0): (Required) The lookup input parameter string as described for [^DIC](#).
- DIC("S"): (Optional) Use this variable in the same way as it is described as an input variable for [^DIC](#).
- DIC("?N",file#)=n: (Optional) Use this variable in the same way it is described as input to [^DIC](#).
- DIC("?PARAM", file#,"INDEX")=index name:  
(Optional) Use this input array in the same way it is described as input to [^DIC](#).
- DIC("?PARAM", file#,"FROM",n)=value:  
(Optional) Use this input array in the same way it is described as input to [^DIC](#).
- DIC("?PARAM", file#,"PART",n)=value:  
(Optional) Use this input array in the same way it is described as input to [^DIC](#).
- D: (Required) Set to "**B**".
- DZ: (Required) Set to **??**. This is set in order to prevent VA FileMan from issuing the "DO YOU WANT TO SEE ALL *nm* ENTRIES?" prompt.

### 2.3.14 DT^DICRW: FM Variable Setup

The DT^DICRW API sets up the required VA FileMan variables. There are no input variables; simply call this API.



**NOTE:** This API KILLS the **DIC** and **DIK** variables.

#### Output Variables

- DUZ: Set to zero if it is *not* already defined.
- DUZ(0): Set to null if *not* already defined. If **DUZ(0)="@**", this subroutine enables terminal break if the operating system supports such functionality.
- IO(0): Set to **\$I** if **IO(0)** is *not* defined. Therefore, this program should *not* be called if the user is on a device different from the home terminal and **IO(0)** is undefined.
- DT: Set to the current date, in VA FileMan format.
- U: Set to the caret (^).

### 2.3.15 EN^DID: Print/Display Data Dictionary Listing

The EN^DID API prints and/or displays a file's data dictionary listing by setting the input variables (the same as the output from the List File Attributes option [DILIST] described in the *VA FileMan Advanced User Manual*).

#### Input Variables

- DIC: (Required) Set to the data dictionary number of the file to list.
- DIFORMAT: (Required) Set to the desired data dictionary listing format. It *must* be one of the following strings:
- STANDARD
  - BRIEF
  - MODIFIED STANDARD
  - TEMPLATES ONLY
  - GLOBAL MAP
  - CONDENSED
  - INDEXES ONLY
  - KEYS ONLY

### 2.3.16 ^DIE: Data Input Edit of a File

The ^DIE API handles input of selected data elements for a given file entry. You should use ^DIE only to edit *existing* records.



**NOTE:** When you call the ^DIE API, it does *not* lock the record; you *must* do that yourself.



**REF:** See the "[Locking](#)" section.

To allow the user to interactively choose the fields to edit, use the [EN^DIB](#) entry point instead.

#### Input Variables

- DIE: (Required) The global root of the file in the form:
- ^GLOBAL(
  - ^GLOBAL(#
  - The number of the file

If you are editing a subfile, set **DIE** to the full global root leading to the subfile entry, including all intervening subscripts and the terminating comma, up to but *not* including the IEN of the subfile entry to edit.

- DA: (Required) If you are editing an entry at the *top-level* of a file, set **DA** to the internal entry number of the file entry to be edited.

If you are editing an entry in a *subfile* (Multiple), set up **DA** as an array, where:

- **DA**—Entry number in the subfile to edit.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.



**REF:** For more information, see the “[Editing a Subfile Directly](#)” section.



**NOTE:** The variable **DA** is KILLED if an entry is deleted within DIE. This can happen if the user answers with the at-sign (@) when editing the entry’s **.01** field.

**DR:**

(Required) A string specifying which data fields are asked for the given entry. The fields specified by **DR** are asked whether or not VA FileMan WRITE access security protection has been assigned to the fields.

You can include the following in the **DR**-string:

- **Field number**—The internal number of a field in a file.
- **Field with Default Value**—A field number followed by // (two slashes), followed by a *default value*. You can make a field with no current data value default to a particular data value you specify. For example, if there is a file entry stored descendent from (fictitious) ^FILE(777), and Field #27 for this file is DATE OF ADMISSION, and you want the user to see:

```
DATE OF ADMISSION: TODAY//
```

Then, the calling program should be:

```
S DR="27//TODAY",DIE="^FILE(",DA=777
D ^DIE
```

If the user just presses the **Enter** key when seeing the prompt, DIE acts as though the user typed in the word **TODAY**.

- **Stuff a Field Value (Validated)** —A field number followed by /// (three slashes), followed by a value. The value should be the *external* form of the field’s value (i.e., the format that would be acceptable as a user’s response). The value is *automatically inserted* into the database after passing through the INPUT transform. For example:

```
S DR="27///TODAY",DIE="^FILE(",DA=777
D ^DIE
```

The user sees no prompts, and the current date is automatically stuffed into Field #27 of entry #777, *even if other data previously existed* there.

In the course of writing a routine, you can pass the value contained in a variable to DIE and automatically insert the value into a field. In that case, you would write:

```
S DR="27///^S X=VAR"
```

You can also use the three-slash stuff to automatically add or select an entry in a Multiple. For example, if Field #60 is a Multiple field, and you write:

```
S DR="60///TODAY"
```

The entry in the subfile corresponding to **TODAY** would be selected, or added if it did *not* already exist.



**NOTE:** If **TODAY** did *not* already exist in the file, but could *not* be added (e.g., because LAYGO was *not* allowed), or if more than one **TODAY** entry already existed in the file (i.e., the lookup value was ambiguous), ^DIE prompts the user to select an entry in the subfile. To add entries or edit existing entries *non-interactively*, consider using [UPDATE^DIE](#) and [FILE^DIE](#) instead.

- **Stuff a Field Value (Unvalidated)**—A field number followed by *////* (four slashes), followed by a value. The value is *automatically inserted without validation* into the database. For example:

```
S DR="27////2570120",DIE="^FILE(",DA=777
D ^DIE
```

In this example the user sees no prompts, and the value **2570120** is put into (fictitious) Field #27 in File #777 without going through the INPUT transform. When using this form, the data after the four slashes *must* already be in its internally stored form. *This cannot be used for .01 fields due to the differences between DIE and DIC.*



**NOTE:** Key uniqueness is *not* enforced when a 4-slash stuff is used.

- **Field Value Deletion**—A field number followed by three or four slashes (*///* or *////*) and an at-sign (@). This *automatically deletes the field value*. For example:

```
S DR="27///@"
```

In this example, the user does *not* see any prompts, and the value for (fictitious) Field #27 is deleted.



**NOTE:** You *cannot* use this method to delete the value for the following:

- Required field
  - Uneditable field
  - Key field
  - Field to which the user does *not* have Delete access.
- **Field Number Range**—A range of field numbers, in the form:

*M:N*

Where *M* is the first and *N* the last number of the *inclusive range*. All fields whose numbers lie within this range are asked.

- **Placeholder for Branching**—A placeholder like @1.



**REF:** See the “[Branching](#)” section.

- **M Code**—A line of M code.
- **Combination**—A sequence of any of the above types, separated by semicolons. For example, if field numbers **.01, 1, 2, 4, 10, 11, 12, 13, 14, 15,** and **101** exist for the file stored in **^FILE**, and you want to have Fields **4, .01, 10** through **15,** and **101** asked in that order for entry number 777, you simply write:

```
S DIE="^FILE( ",DA=777,DR="4;.01;10:15;101"
D ^DIE
```



**NOTE:** The **DR**-string contains the semicolon (;) delimiter to specify field numbers and the colon (:) to specify a range of fields. This prevents these two characters from being used as defaults. They can, however, be placed in a variable that is then used as the default instead of a literal. For example:

```
S DR="27///^S X=VAR"
```

- **INPUT template**—An INPUT template name, preceded by an open bracket (I) and followed by a closed bracket (J). All the fields in that template are asked.

DIE("NO^"):

(Optional) Controls the use of the caret (^) in an edit session. If this variable does *not* exist, unrestricted use of the caret for jumping and exiting is allowed.

The variable can be set to one of the following:

- **“OUTOK”**—Allows exiting and prevents all jumping.
- **“BACK”**—Allows jumping back to a previously edited field and does *not* allow exiting.
- **“BACKOUTOK”**—Allows jumping back to a previously edited field and allows exiting.
- **“Other value”**—Prevents all jumping and does *not* allow exiting.

DIE("PTRIX",f,p,t)=d: (Optional) Where:

- **f** = From (pointing) file number.
- **p** = Pointer field number.
- **t** = Pointed-to file number.
- **d** = Caret (^)-delimited list of index names.

This optional input array allows you to control how lookups are done on both Multiple and *non*-Multiple pointer and variable pointer fields. Each node in this array is set to a list of index names, separated by carets (^). When the user edits a pointer or variable pointer field, only those indexes in the list are used when searching the pointed-to file for matches to the lookup value.

For example, if your input template contains a Field #5 on File #16100 that is a pointer to the NEW PERSON (#200) file, and you want the lookup on the NEW PERSON (#200) file to be by name (“**B**” index), or by the first letter of the last name concatenated with the last four digits of the social security number (“**BS5**” index), you would set the following node before the ^DIE call:

```
DIE ("PTRIX" , 16100 , 5 , 200) = "B^BS"
```



**NOTE:** If you allow records to be added to the pointed-to file, you should include a “**B**” in the list of indexes, since when ^DIE adds an entry, it assumes the **.01** field for the new entry is the lookup value. However, the “**B**” index would *not* need to be included if the first index in the “**PTRIX**” node is a compound index whose first subscript is the **.01** field.

DIDEL:

(Optional) Overrides the **DELETE** access on a file or subfile. Set **DIDEL** equal to the number of the file before calling DIE to allow the user to delete an entire entry from that file, even if the user does *not* normally have the ability to delete. This variable does *not* override the “**DEL**”-nodes described in the “[Other Field Definition Nodes](#)” in the “[Global File Structure](#)” section.

## Output Variables

DTOUT: Is set when a time-out has occurred.



**NOTE:** **DA**, **DIE**, **DR**, **DIE**("NO^"), and **DIDEL** are *not* KILLED by DIE; however, the variable **DA** is KILLED if the entry is deleted within DIE. This can happen if the user answers with an at-sign (@) when editing the entry's **.01** field.

### 2.3.16.1 Details and Features of Data Editing

1. [Locking](#)
2. [Edit Qualifiers](#)
3. [Branching](#)
4. [Specific Fields in Multiples](#)
5. [Continuation DR-Strings](#)
6. [Detecting Exits](#) (by using the caret character; ^)
7. [Editing a Subfile Directly](#)
8. [Screening Variable Pointers](#)
9. [Filing](#)
10. [New-Style Compound Indexes and Keys](#)

#### 2.3.16.1.1 Locking

If you want to ensure that two users *cannot* edit an entry at the same time, lock the entry. It is *recommended* that you use incremental locks.

[Figure 20](#) is a simple example of using incremental locks to lock an entry before editing and to remove the lock after:

**Figure 20: ^DIE API—Sample Code Using Incremental Locks**

```
S DIE=^FILE(",DA=777,DR="[EDIT]"
L +^FILE(777):0 I $T D ^DIE L -^FILE(777) Q
W !?5,"Another user is editing this entry." Q
```



**NOTE:** The DIE call itself does *NO* locking.

#### 2.3.16.1.2 Edit Qualifiers

In the **DR** string, you can use edit qualifiers (described in the *VA FileMan Advanced User Manual*) in conjunction with the fields you specify. The possible qualifiers are:

- T
- DUP
- REQ
- Text literal strings in quotes



In interactive mode, users can combine qualifiers with fields by using semicolon (;) separators. But, in **DR**-strings, semicolons are already used to delimit individual fields, so you *must* use a different syntax for **DR**. Basically, leave out the semicolon and the unnecessary characters. Using Field #3 as an example, the syntax for edit qualifiers in **DR**-strings is:

**Table 17: ^DIE API—Edit qualifiers: Interactive Syntax**

Interactive Syntax	Syntax for DR-string	Explanation
<b>3;T</b>	<b>3T</b>	The <b>T</b> follows the field number immediately.
<b>3;"xxx"</b>	<b>3xxx</b>	The quotes are removed from the literal and it follows the field number immediately.
<b>3;DUP</b>	<b>3d</b>	The <b>D</b> becomes lowercase and the <b>UP</b> is dropped.
<b>3;REQ</b>	<b>3R</b>	The uppercase <b>R</b> follows immediately and the <b>EQ</b> is dropped.

You can combine specifiers as long as you separate them with tildes (~). For example, if you want to require a response to Field #3, and issue the title rather than the prompt, put **3R~T** in the **DR**-string.

### 2.3.16.1.3 Branching

You can include *branching logic* within **DR**. To do this, insert an executable **M** statement in one of the semicolon-pieces of **DR**. The **M** code is executed when this piece of **DR** is encountered by the **DIE** routine.

If the **M** code sets the variable **Y**, **DIE** jumps to the field whose number (or label) matches **Y**. (The field *must* be specified elsewhere within the **DR** variable.) **Y** can look like a placeholder (e.g., @1). If **Y** is set to zero or the null string, **DIE** exits if the editing is at the top-level; otherwise, it returns to the next higher level. If **Y** is **KILLED**, or never set, no branching occurs.

The **M** code can calculate **Y** based on **X**, which equals the internal value of the field previously asked for (as specified by the previous semicolon-piece of **DR**). In the example in [Figure 21](#) suppose that you do *not* want the user to be asked for Field #.01 if the answer to Field #4 was **YES**, you would write the following:

**Figure 21: ^DIE API—Sample Code to Calculate Y Based on X**

```
S DIE="^FILE(",DA=777
S DR="4;I X=""YES"" S Y=10;.01;10:15;101"
D ^DIE
```



**NOTE:** The ability to “jump” (by using the caret character; ^) to specific fields does *not* take into account previous branching logic. You *must* ensure that such movements are safe.

#### 2.3.16.1.4 Specific Fields in Multiples

When you include the field number of a Multiple in a **DR**-string, all the subfields of the Multiple are asked. However, suppose you want to edit only selected subfields in the Multiple. To do this, set **DR** in the usual manner and in addition set a subscripted value of **DR** equal to the subfields to edit. Subscript the additional **DR** node by file level and then by the Multiple's subfile number.

For example, if Field #15 is a Multiple and the subfile number for the Multiple is #16001.02 and you want the user to be prompted only for subfields #.01 and #7, do the following:

**Figure 22: ^DIE API—Prompting User for Specific Fields in Multiples**

```
S DR=".01;15;6;8"  
S DR(2,16001.02)=".01;7"
```

Where the first subscript, **2**, means the second level of the file and the second subscript is the subfile number of the Multiple (#15) field.

#### 2.3.16.1.5 Continuation DR-Strings

If there are more than **245** characters in a **DR**-string, you can set continuation strings by defining the **DR**-array at the third subscript level. These subscripts should be sequential integers starting at **1**. For example, the first continuation node of DR(2,16001.02) would be DR(2,16000.02,1); the second would be DR(2,16001.02,2), and so on.

#### 2.3.16.1.6 Detecting Exits

You can determine, upon return from DIE, whether the user exited the routine by typing a caret character (^; sometimes referred to in VistA legacy documentation as the "up-arrow"). If the user did so, the subscripted variable **Y** is defined; if all questions were asked and answered in normal sequence, **\$D(Y)** is zero.

#### 2.3.16.1.7 Editing a Subfile Directly

You can call ^DIE to directly edit an entry in a subfile (Multiple); you can descend into as many subfiles as you need to. Set the DIE input variable to the full global root leading to the subfile entry, including all intervening subscripts and the terminating comma up to, but not including, the IEN of the subfile entry to edit. Then set an array element for each file and subfile level in the **DA** input variable, where:

- **DA**—Entry number in the subfile to edit.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file's top-level.

For example, suppose that the data in Subfile #16000.02 is stored descendent from subscript 20 and you are going to edit entry number 777, subentry number 1; you would write the following:

**Figure 23: ^DIE API—Editing a Subfile Directly**

```
S DIE="^FILE(777,20," ; global root of subfile  
S DA(1)=777 ; entry number in file  
S DA=1 ; entry number in subfile  
S DR="3;7" ; fields in subfile to edit  
D ^DIE
```



**NOTE:** The internal number of the entry into the file appears in the variable **DIE** and appears as the value of **DA(1)**. When doing this, it is necessary that the subfile descriptor node be defined. In this example, it would be:

```
^FILE(777,20,0)="^16000.02^last number entered^number of entries"
```



**REF:** See also the discussion of “[Adding New Subentries to a Multiple](#)” in the “[^DIC: Lookup/Add](#)” section in the “[Classic VA FileMan API](#)” section.

### 2.3.16.1.8 Screening Variable Pointers

A variable pointer field can point to entries in more than one file. You can restrict the user’s ability to input entries to certain files by setting the **DIC(“V”)** variable in a **DR**-string or in an **INPUT** template. It screens files from the user. Set **DIC(“V”)** equal to a line of **M** code that returns a truth value when executed. The code is executed after someone enters data into a variable pointer field. If the code tests false, the user’s input is rejected; VA FileMan responds with **??** and an audible sound (“beep”).

The code setting the **DIC(“V”)** variable can be put into a **DR**-string or into an **INPUT** template. It is *not* a separate input variable for **^DIE** or **^DIC**. It should be set *immediately before* the variable pointer field is edited and it should be **KILLED** *immediately after* the field is edited.

When the user enters a value at a variable pointer field’s prompt, VA FileMan determines in which file that entry is found. The variable **Y(0)** is set equal to information for that file from the data dictionary definition of the variable pointer field. You can use **Y(0)** in the code set into the **DIC(“V”)** variable. **Y(0)** contains the following:

**Table 18: ^DIE API—Y(0) in the Code Set into the DIC(“V”) Variable**

^-Piece	Contents
Piece 1	File number of the pointed-to file.
Piece 2	Message defined for the pointed-to file.
Piece 3	Order defined for the pointed-to file.
Piece 4	Prefix defined for the pointed-to file.
Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.
Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed to file.

All of this information was defined when that file was entered as one of the possibilities for the variable pointer field.

For example, suppose Field #5 is a variable pointer pointing to (fictitious) Files #1000, #2000, and #3000. If you only want the user to be able to enter values from (fictitious) Files #1000 or #3000, you could set up your **INPUT** template like this:

**Figure 24: ^DIE API—Sample INPUT Template**

```
THEN EDIT FIELD: ^S DIC(“V”)="I +Y(0)=1000!(+Y(0)=3000)"
THEN EDIT FIELD: 5
THEN EDIT FIELD: ^K DIC(“V”)
```

### 2.3.16.1.9 Filing

DIE files data when any one of the following conditions is encountered:

- The field entered or edited is cross-referenced.
- A change of level occurs (i.e., either DIE *must* descend into a Multiple or ascend to the level above).
- Navigation to another file occurs.
- M code is encountered in one of the semicolon-pieces of the **DR**-string or in a template.
- **\$S** becomes less than **2000**.
- The user enters a caret (^) to a field.
- The end of the **DR**-string or INPUT template is reached.
- Templates are compiled and the execution is transferred from one routine to the next.

### 2.3.16.1.10 New-Style Compound Indexes and Keys

^DIE traditionally fires cross-references when the field on which the cross-reference is defined is edited. New-Style cross-references that have an execution of “**RECORD**” (hereafter referred to as record-level indexes) are fired once at the end of the ^DIE call, after all the semicolon pieces of the **DR** string have been processed.

When record-level uniqueness indexes are fired, the corresponding keys (hereafter called record-level keys) are checked to ensure that they are unique. If edits to a field in a key result in a duplicate key, then changes to that field are backed out and an error message is presented to the user.

You can set the **DIEFIRE** variable in any of the semicolon-pieces of **DR** to instruct VA FileMan to fire the record-level indexes at that point and validate the corresponding record-level keys. You can also control what VA FileMan does if any of the record-level keys is invalid.

**Table 19: ^DIE API—DIEFIRE Variable Settings**

DIEFIRE Contains	Action
<b>M</b>	Print error message to user.
<b>L</b>	Return the DIEBADK array (see <a href="#">Figure 25</a> ).
<b>R</b>	Restore invalid key fields to their pre-edited values.

If **DIEFIRE** contains an **L** and a key is invalid, the **DIEBADK** array is set as follows:

**Figure 25: ^DIE API—Sample Array when DIEFIRE Contains an L and a Key is Invalid**

DIEBADK(rFile#,key#,file#,IENS,field#,"O") = the original value of the field DIEBADK(rFile#,key#,file#,IENS,field#,"N") = the new (invalid) value of the field
---

Where:

- **rFile#**—The *root file* of the *uniqueness index* of the key. This is the file or subfile number of the fields that make up the key.
- **key#**—The internal entry number of the key in the KEY (#.31) file.
- **file#**—The *file* of the *uniqueness index* of the key. This is the file or subfile where the *uniqueness index* resides. For whole file indexes, this is a file or subfile at a higher level than *root file*.
- **IENS**—The IENS of the record that—with the edits—would have a *non-unique* key.
- **field#**—The field number of the field being edited.

If any of the keys is invalid, VA FileMan sets the variable **X** to the string “**BADKEY**”, which can be checked by M code in the subsequent semicolon-piece of the **DR** string. The variable **X** and the local array **DIEBADK** are available for use only in the semicolon piece immediately following the piece where the **DIEFIRE** was set.

For example:

**Figure 26: ^DIE API—Sample Code Setting the Variable X to the String “BADKEY”, if Any of the Keys is Invalid**

```
S DIE="^FILE(",DA=777
S DR="@1;.01;.02;S DIEFIRE="R";I X="BADKEY""
S Y="@1;1;2"
D ^DIE
```

In [Figure 26](#), the **.01** and **.02** field makes up a key to the file. After prompting the user for the value of the **.02** field, **DIEFIRE** is set to force VA FileMan to fire the record-level indexes and validate the key. If the key turns out to be invalid, VA FileMan sets **X** equal to “**BADKEY**” and, since **DIEFIRE** equals **R**, restores the fields to their pre-edited values. In the next semicolon-piece, you check if **X** equals “**BADKEY**” and, if so, branch the user back to the placeholder **@1**.

### 2.3.17 ^DIEZ: INPUT Template Compile—User Interactive

The ^DIEZ API interactively compiles or recompiles an INPUT template.

Compiling an INPUT template means telling VA FileMan to write a hard-coded M routine that will do just what a particular INPUT template tells the Enter or Edit File Entries option [DIEDIT] to do. This can enhance system performance by reducing the amount of data dictionary lookup that accompanies VA FileMan input. The routines created by DIEZ should run from 20% to 80% more efficiently than [DIE](#) does for the same input.

Call ^DIEZ and specify the maximum number of characters you want in your routines, the name of the INPUT template you are using, and the name of the M routine you want to create. If more code is compiled than fits into a single routine, overflow code is incorporated in routines with the same name, followed by 1, 2, etc. For example, routine DGT can call DGT1, DGT2, etc.

Once DIEZ has created a hard-coded routine for a particular INPUT template, VA FileMan *automatically* uses that routine in the Enter or Edit File Entries option [DIEDIT], whenever that template is specified for input. When definitions of fields used in the EDIT template are altered by the Modify File Attributes [DIMODIFY] or Utility Functions [DIUTILITY] options, the hard-code routines are recompiled immediately.

### 2.3.18 EN^DIEZ: INPUT Template Compile—No User Interaction

The EN^DIEZ API compiles or recompiles an INPUT template, *without* user intervention.



**REF:** For more information about compiled INPUT templates, see [^DIEZ](#).

#### Input Variables

- X: The name of the routine for the compiled INPUT template.
- Y: The internal entry number of the INPUT template to be compiled.
- DMAX: The maximum size the compiled routines should reach. Consider using the [\\$\\$ROUSIZE^DILF](#) function to set this variable.

### 2.3.19 ^DIK: Delete Entries

Call DIK at ^DIK to delete an entry from a file.



**CAUTION:** Use DIK to delete entries with *extreme caution*. It does *not* check Delete access for the file or any defined “DEL” nodes. Also, it does *not* update any pointers to the deleted entries. However, it does execute all cross-references and triggers.

Table 20: ^DIK—Reindexing Quick Reference

Entry Point	Reindexes Entries	Reindexes Cross-References	Executes Logic
<b>^DIK</b>	<b>All</b>	<b>All</b>	<b>KILL</b>
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

#### Input Variables

- DIK: The global root of the file from which you want to delete an entry.  
If you are deleting a subentry, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry to delete.
- DA: If you are deleting an entry at the top-level of a file, set **DA** to the internal entry number of the file entry to delete. For example, to delete ONE FMEMPLOYEE,

which is entry number 7, from the (fictitious) EMPLOYEE file that is stored in the (fictitious) global ^EMP, write the following:

```
S DIK="^EMP( " ,DA=7
>D ^DIK
```

If you are deleting an entry in a subfile (Multiple), set up **DA** as an array, where:

- **DA**—Entry number in the subfile to delete.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

For example, suppose employee THREE FMEMPLOYEE (record #1) has two skill entries (subrecords #1 and #2) in a SKILL Multiple. To delete the SKILL Multiple’s subrecord #2 you would write:

```
S DA(1)=1,DA=2,DIK="^EMP( "_DA(1)_" ,"SX" ","
>D ^DIK
```

Where:

- **DA**—Skill entry number in the subfile.
- **DA(1)**—Employee’s internal entry number in the (fictitious) EMPLOYEE file.
- **“SX”**—Node under which the subfile is located.

### 2.3.19.1 Looping to Delete Several Entries

^DIK leaves the **DA**-array and **DIK** defined; so you can loop through a file to delete several entries:

**Figure 27: ^DIK API—Sample Code Looping to Delete Several Entries**

```
>S DIK="^EMP( " F DA=2,9,11 D ^DIK
```

This deletes entries #2, #9 and #11 from the (fictitious) EMPLOYEE file.

### 2.3.19.2 Deleting Fields from a File

As discussed in the “[Reading the Attribute Dictionary—Example](#)” section, each attribute dictionary is also in the form of a file. You can therefore use the routine DIK to delete a *single-valued field* (i.e., *not* a Multiple) from a file.

To delete a *single-valued* field (i.e., *not* a Multiple) from a file, you would set the variables as follows:

- **DIK**—Set to the file’s data dictionary global node.
- **DA**—Set to the number of the field to be deleted.
- **DA(1)**—Set to the file number.

For example, to delete the SEX (#1) field from the (fictitious) EMPLOYEE (#3) file example, simply write:

**Figure 28: ^DIK API—Sample Code Deleting *Single-valued Fields* from a File**

```
>S DIK="^DD(3," ,DA=1,DA(1)=3
>D ^DIK
```

To delete a subfield from a Multiple from a file, you would set the variables as follows:

- **DIK**—Set to the subfile’s data dictionary global node.
- **DA**—Set to the number of the field to be deleted.
- **DA(1)**—Set to the subfile number.

For example, to delete the ZIP (#4) field of the ADDRESS (#3.02) Multiple field from the (fictitious) EMPLOYEE (#3) file example, simply write:

**Figure 29: ^DIK API—Sample Code Deleting a *Multiple Sub-field* from a File**

```
>S DIK="^DD(3.02," ,DA=4,DA(1)=3.02
>D ^DIK
```

When you use ^DIK to delete fields from a file, the data is *not* deleted.



**NOTE:** To delete a Multiple field from a file, use the [EN^DIU2](#) API.

**REF:** For more information, see the “[EN^DIU2: Delete Data Dictionary](#)” section.

## 2.3.20 EN^DIK: Reindex Field Cross-References for One File Entry—KILL and SET Logic

The EN^DIK API reindexes one or more cross-references of a field for one entry in a file. It executes the **KILL** logic first and then executes the **SET** logic of the cross-reference.



**CAUTION:** As of Patch DI\*22\*167, this API reindexes those cross-references marked with “DO NOT RE-INDEX,” because it operates on a single record.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 21: EN^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-References	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<b>EN^DIK</b>	1	<b>Some or all for 1 field</b>	<b>KILL then SET</b>
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET



Entry Point	Reindexes Entries	Reindexes Cross-References	Executes Logic
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before reindexing, you should be familiar with the effects of all relevant cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type

### Input Variables

**DIK:** If you are reindexing an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are reindexing a subentry, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry to reindex.

**DA:** If you are reindexing an entry at the *top-level* of a file, set **DA** to the internal entry number of the file entry to reindex.

If you are reindexing an entry in a *subfile*, set up **DA** as an array, where:

- **DA**—Entry number in the subfile to reindex.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

**DIK(1):** Use the field number to get *all* indexes, or the field number *and* specific indexes of the cross-reference.



**REF:** For examples, see the [ENALL^DIK](#) API description.

## 2.3.21 EN1^DIK: Reindex Field Cross-References for One File Entry—SET Logic

The EN1^DIK API reindexes one or more cross-references of a field for one entry in a file. It only executes the **SET** logic of the cross-reference.



**CAUTION:** As of Patch DI\*22\*167, this API reindexes those cross-references marked with “DO NOT RE-INDEX,” because it operates on a single record.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 22: EN1^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-References	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<b>EN1^DIK</b>	<b>1</b>	<b>Some or all for 1 field</b>	<b>SET</b>
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before reindexing, you should be familiar with the effects of all relevant cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type

### Input Variables

**DIK:** If you are reindexing an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are reindexing a subentry, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry to reindex.

**DA:** If you are reindexing an entry at the *top-level* of a file, set **DA** to the internal entry number of the file entry to reindex.

If you are reindexing an entry in a subfile, set up **DA** as an array, where:

- **DA**—Entry number in the subfile to reindex.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

DIK(1):

Use the field number to get *all* cross-references, or the field number *and* specific indexes of the cross-references you want.



**REF:** For examples, see the [ENALL^DIK](#) API description.

### 2.3.22 EN2^DIK: Executes KILL Logic for One or More Field Cross-References for One File Entry

EN2^DIK executes the **KILL** logic for one or more cross-references on a specific field for one entry in a file.



**CAUTION:** As of Patch DI\*22\*167, this API reindexes those cross-references marked with “DO NOT RE-INDEX,” because it operates on a single record.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 23: EN2^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<b>EN2^DIK</b>	<b>1</b>	<b>Some or all for 1 field</b>	<b>KILL</b>
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before calling this API, you should be familiar with the effects of executing the **KILL** logic for all cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type

### Input Variables

**DIK:** If you are executing the **KILL** logic for an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are executing the **KILL** logic for a *subentry*, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry.

**DA:** If you are executing the **KILL** logic for an entry at the *top-level* of a file, set **DA** to the internal entry number of that file entry.

If you are executing the **KILL** logic for an entry in a *subfile*, set up **DA** as an array, where:

- **DA**—Entry number in the subfile.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(*n*)**—Entry number at the file's top-level.

**DIK(1):** Use the field number to get *all* cross-references, or the field number *and* specific indexes of the cross-references you want.



**REF:** For examples, see the [ENALL^DIK](#) API description.

### 2.3.23 ENALL^DIK: Reindex All File Entries for Specific Field Cross-References—SET Logic

The ENALL^DIK API reindexes all entries in a file for the cross-references on a specific field. It can also be used to reindex all entries within a single subfile (i.e., a subfile corresponding to only one of the file’s entries). ENALL^DIK only executes the SET logic.



**CAUTION:** As of Patch DI\*22\*167, this API honors (does *not* reindex) those cross-references marked with “DO NOT RE-INDEX,” *unless the cross-reference is specifically named*.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 24: ENALL^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<b>ENALL^DIK</b>	<b>All</b>	<b>Some or all for 1 field</b>	<b>SET</b>
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before reindexing, you should be familiar with the effects of all relevant cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type



**NOTE:** The [IXALL^DIK](#), [IXALL2^DIK](#), ENALL^DIK, [ENALL2^DIK](#) APIs, and the Re-Index File option [DIRDEX] on the Utility Functions menu [DIUTILITY] do the following:

- Set the 3<sup>rd</sup> piece of the 0 node of the file’s global root (the file header) to the last internal entry number used in the file.
- Set the 4<sup>th</sup> piece to the total number of entries in the file.

## Input Variables

**DIK:** If you are reindexing an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are reindexing *subentries*, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IENs of the subfile entries to reindex.

**DA(1..n):** If you are reindexing entries in a subfile, set up **DA** as an array, where:

- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

Since ENALL^DIK reindexes *all* entries at a given file level, do *not* set the unsubscripted **DA** node.

**DIK(1):** Use the field number to get all indexes, or the field number *and* specific cross-references separated by carets (^) as shown below:

```
>S DIK(1)="FLD#" ;Just the field number to get all indexes.
```

Or:

```
;Field number followed by cross-reference name or number.
S DIK(1)="FLD#^INDEX"
;See the examples below:

S DIK(1)=".01^B"
S DIK(1)=".01^B^C"
S DIK(1)=".01^1^2"
D ENALL^DIK
```

### 2.3.24 ENALL2^DIK: Executes KILL Logic for One or More Field Cross-References for All File Entries

The ENALL2^DIK API executes the **KILL** logic for one or more cross-references on a specific field for all entries in a file.



**CAUTION:** As of Patch DI\*22\*167, this API honors (does *not* reindex) those cross-references marked with “DO NOT RE-INDEX,” *unless the cross-reference is specifically named*.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 25: ENALL2^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<b>ENALL2^DIK</b>	<b>All</b>	<b>Some or all for 1 field</b>	<b>KILL</b>
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before calling this API, you should be familiar with the effects of executing the **KILL** logic for all cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type



**NOTE:** The [IXALL^DIK](#), [IXALL2^DIK](#), [ENALL^DIK](#), ENALL2^DIK APIs, and the Re-Index File option [DIRDEX] on the Utility Functions menu [DIUTILITY] do the following:

- Set the 3<sup>rd</sup> piece of the **0** node of the file's global root (the file header) to the last internal entry number used in the file.
- Set the 4<sup>th</sup> piece to the total number of entries in the file.

### Input Variables

**DIK:** If you are executing the **KILL** logic for all entries at the *top-level* of a file, set **DIK** to the global root of the file.

**DA(1..n):** If you are executing the **KILL** logic for all entries in a subfile only, set **DIK** to the full global root of the subfile.

If you are executing the **KILL** logic for all entries at the *top-level* of a file, this variable need *not* be set.

If you are executing the **KILL** logic for all entries in a subfile, set up **DA** as an array, where:

- **DA(1)**—Entry number at the next higher file level.
- **DA(2)**—Entry number one level above that, etc.
- **DA(n)**—Entry number at the file's top-level.

Since ENALL2^DIK executes the **KILL** logic for all entries at a given file level, do *not* set the unsubscripted **DA** node.

**DIK(1):** Set **DIK(1)** to the field number to get *all* cross-references defined on that field. For example:

```
S DIK(1) = .01
```

Or:

Set **DIK(1)** to the field number and the names or numbers of specific cross-references on that field, all separated by carets (^). For example:

```
S DIK(1) = ".01^B"  
S DIK(1) = ".01^B^C"  
S DIK(1) = ".01^1^2"  
D ENALL2^DIK
```

### 2.3.25 IX^DIK: Reindex All File Cross-References for One File Entry—KILL and SET Logic

The IX^DIK API reindexes all cross-references of the file for only one entry in the file. It executes first the **KILL** logic and then the **SET** logic. Reindexing occurs at all file levels at or below the one specified in the **DIK** and **DA** input variables.



**CAUTION:** As of Patch DI\*22\*167, this API reindexes those cross-references marked with “DO NOT RE-INDEX,” because it operates on a single record.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 26: IX^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<b>IX^DIK</b>	<b>1</b>	<b>All</b>	<b>KILL then SET</b>
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL



Before reindexing, you should be familiar with the effects of all relevant cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type

### Input Variables

**DIK:** If you are reindexing an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are reindexing only a subentry, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry to reindex.

**DA:** If you are reindexing an entry at the *top-level* of a file, set **DA** to the internal entry number of the file entry to reindex.

If you are reindexing an entry in a subfile, set up **DA** as an array, where:

- **DA**—Entry number in the subfile to reindex.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

## 2.3.26 IX1^DIK: Reindex All File Cross-References for One File Entry—SET Logic

The IX1^DIK API reindexes all cross-references of the file for only one entry in the file. It only executes the **SET** logic of the cross-reference. Reindexing occurs at all file levels at or below the one specified in the **DIK** and **DA** input variables.



**CAUTION:** As of Patch DI\*22\*167, this API reindexes those cross-references marked with “DO NOT RE-INDEX,” because it operates on a single record.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 27: IX1^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<b>IX1^DIK</b>	<b>1</b>	<b>All</b>	<b>SET</b>
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before reindexing, you should be familiar with the effects of all relevant cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type

### Input Variables

**DIK:** If you are reindexing an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are reindexing a subentry, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry to reindex.

**DA:** If you are reindexing an entry at the *top-level* of a file, set **DA** to the internal entry number of the file entry to reindex.

If you are reindexing an entry in a subfile, set up **DA** as an array, where:

- **DA**—Entry number in the subfile to reindex.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

## 2.3.27 IX2^DIK: Executes KILL Logic of All Cross-References at File Level Specified

The IX2^DIK executes **KILL** logic of all cross-references for one entry at all file levels at and below the one specified in the **DIK** input variable.



**CAUTION:** As of Patch DI\*22\*167, this API reindexes those cross-references marked with “DO NOT RE-INDEX,” because it operates on a single record.



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 28: IX2^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<b>IX2^DIK</b>	<b>1</b>	<b>All</b>	<b>KILL</b>
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before calling this API, you should be familiar with the effects of executing the **KILL** logic for all cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type

### Input Variables

**DIK:** If you are executing the **KILL** logic for an entry at the *top-level* of a file, set **DIK** to the global root of the file.

If you are executing the **KILL** logic for a subentry, set **DIK** to the full global root leading to the subentry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry.

**DA:** If you are executing the **KILL** logic for an entry at the *top-level* of a file, set **DA** to the internal entry number of that file entry.

If you are executing the **KILL** logic for an entry in a subfile, set up **DA** as an array, where:

- **DA**—Entry number in the subfile.
- **DA(1)**—Entry number at the next higher file level, etc.
- **DA(n)**—Entry number at the file’s top-level.

### 2.3.28 IXALL^DIK: Reindexes All Cross-References for All File Entries—SET Logic

The IXALL^DIK API reindexes *all* cross-references for *all* entries in a file. It only executes the **SET** logic.



**CAUTION:** As of Patch DI\*22\*167, this API honor (does *not* reindex) those cross-references marked with “DO NOT RE-INDEX.”



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 29: IXALL^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<b>IXALL^DIK</b>	<b>All</b>	<b>All</b>	<b>SET</b>
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before reindexing, you should be familiar with the effects of all relevant cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type



**NOTE:** The IXALL^DIK, [IXALL2^DIK](#), [ENALL^DIK](#), [ENALL2^DIK](#) APIs, and the Re-Index File option [DIRDEX] on the Utility Functions menu [DIUTILITY] do the following:

- Set the 3<sup>rd</sup> piece of the 0 node of the file’s global root (the file header) to the last internal entry number used in the file.
- Set the 4<sup>th</sup> piece to the total number of entries in the file.

### Input Variable

DIK: The global root of the file to be indexed.

## 2.3.28.1 Examples

### 2.3.28.1.1 Example 1

A simple call to reindex the (fictitious) EMPLOYEE file would be:

**Figure 30: IXALL^DIK API—Example 1: Input**

```
>S DIK=""^EMP(" D IXALL^DIK
```

### 2.3.28.1.2 Example 2

The reindexing of data dictionary #3 would be:

**Figure 31: IXALL^DIK API—Example 2: Input**

```
>S DA(1)=3,DIK=""^DD(3," D IXALL^DIK
```

## 2.3.29 IXALL2^DIK: Executes KILL Logic for All File Entries

The IXALL2^DIK API executes the **KILL** logic for all entries in a file.



**CAUTION:** As of Patch DI\*22\*167, this API honors (does *not* reindex) those cross-references marked with “DO NOT RE-INDEX.”



**REF:** For more information about limiting reindexing of files, see the “Limits on Reindexing Files” section in the *VA FileMan Advanced User Manual*.

**Table 30: IXALL2^DIK API—Reindexing Quick Reference**

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">^DIK</a>	All	All	KILL
<a href="#">EN^DIK</a>	1	Some or all for 1 field	KILL then SET
<a href="#">EN1^DIK</a>	1	Some or all for 1 field	SET
<a href="#">EN2^DIK</a>	1	Some or all for 1 field	KILL
<a href="#">ENALL^DIK</a>	All	Some or all for 1 field	SET
<a href="#">ENALL2^DIK</a>	All	Some or all for 1 field	KILL

Entry Point	Reindexes Entries	Reindexes Cross-references	Executes Logic
<a href="#">IX^DIK</a>	1	All	KILL then SET
<a href="#">IX1^DIK</a>	1	All	SET
<a href="#">IX2^DIK</a>	1	All	KILL
<a href="#">IXALL^DIK</a>	All	All	SET
<a href="#">IXALL2^DIK</a>	All	All	KILL

Before calling this API, you should be familiar with the effects of executing the **KILL** logic for all cross-references that could be fired, including:

- Bulletins
- Triggers
- MUMPS-type



**NOTE:** The [IXALL^DIK](#), [IXALL2^DIK](#), [ENALL^DIK](#), [ENALL2^DIK](#) APIs, and the Re-Index File option [DIRDEX] on the Utility Functions menu [DIUTILITY] do the following:

- Set the 3<sup>rd</sup> piece of the **0** node of the file's global root (the file header) to the last internal entry number used in the file.
- Set the 4<sup>th</sup> piece to the total number of entries in the file.

### Input Variable

**DIK:** If you are executing the **KILL** logic for all entries at the *top-level* of a file, set **DIK** to the global root of the file.

If you are executing the **KILL** logic for all entries in a subfile, set **DIK** to the full global root of the subfile.

**DA:** If you are executing the **KILL** logic for all entries at the *top-level* of a file, this variable need *not* be set.

If you are executing the **KILL** logic for all entries in a subfile, set up **DA** as an array, where:

- **DA(1)**—Entry number of the next higher file level.
- **DA(2)**—Entry number one level above that, etc.
- **DA(n)**—Entry number at the file's top-level.

Since [IXALL2^DIK](#) executes the **KILL** logic for all entries at a given file level, do *not* set the unsubscripted **DA** node.

### 2.3.30 ^DIKZ: Compiles Cross-References into M Routines

Cross-references can be compiled into M routines by calling the ^DIKZ API. You are prompted to specify the maximum routine size and the name or number of the file. If you specify the routine name XXX and more code is generated than can fit into that one routine, overflow routines (XXX1, XXX2, etc.) are created. Routine XXX can call XXX1, XXX2, etc.

Once DIKZ has been used to create hard-coded cross-reference routines, those routines are used when calls to any entry point in DIK are made. However, if you restrict the cross-references to be reindexed by using the **DIK(1)** variable, the compiled routines are *not* used. As soon as data dictionary cross-references are added or deleted, the routines are recompiled. The purpose of this DIKZ code generation is simply to improve overall system throughput.



**REF:** For instructions on permanently stopping the use of compiled cross-references, uncompiling cross-references, see the “Edit File” section in the *VA FileMan Advanced User Manual*.

### 2.3.31 EN^DIKZ: Recompiles a File’s Cross-References—No User Intervention

The EN^DIKZ API recompiles a file’s cross-references by setting the input variables *without* user intervention.

#### Input Variables

- X: The routine name.
- Y: The file number of the file for which you want the cross-references recompiled.
- DMAX: The maximum size the compiled routines should reach. Consider using the [\\$\\$ROUSIZE^DILF](#) function to set this variable.

### 2.3.32 \$\$ROUSIZE^DILF: Returns Maximum Routine Size

\$\$ROUSIZE^DILF is an *argumentless* intrinsic function that returns the maximum routine size that should be used when compiling cross-references, PRINT templates, or INPUT templates.

#### Format

\$\$ROUSIZE^DILF

#### Input Parameters

None.

#### Output

This function returns the maximum routine size defined in the MUMPS OPERATING SYSTEM (#.7) file.

#### 2.3.32.1 Example

Figure 32: \$\$ROUSIZE^DILF API—Example: Input and Output

```
>W $$ROUSIZE^DILF
4000
```

### 2.3.33 ^DIM: Validates M Code

Call the ^DIM API to validate any line of M code. ^DIM checks that code conforms to the 1995 ANSI Standard. Code is also checked against aspects of VA's Programming Standards and Conventions (SAC).



**NOTE:** ^DIM does *not* allow KILLing an unsubscripted global.

#### Input Variable

X: (Required) Invoke ^DIM with the line to be validated in the local variable X.

#### Output Variable

X: ^DIM either KILLS X or leaves it unchanged. If \$D(X) is zero on return from ^DIM, the line of code is invalid. However, the converse is *not* always true; in other words, ^DIM is *not* as smart as a real M interpreter and sometimes validates strings when it should *not*.

### 2.3.34 DT^DIO2: Writes External Date from Internal

The DT^DIO2 API takes a VA FileMan internal date in the variable Y and *writes out* its external form.

#### Input Variable

Y: (Required) This contains the VA FileMan internal date to be converted. Y is required and it is *not* changed.



**REF:** In addition, see the [X ^DD\("DD"\): Converts Internal to External Date Format](#) and [DD^%DT: Converts Internal to External Date Format](#) APIs, which also convert a date from VA FileMan internal *YYMMDD* format to external format.

#### Example

Figure 33: DT^DIO2 API—Example: Input and Output

```
>S Y=2690720.163 D DT^DIO2
JUL 20,1969 1630
```

This results in Y being equal to **JUL 20,1969 16:30**. (No space before the 4-digit year; 2 spaces before the hours:minutes [**16:30**].)

### 2.3.35 ^DIOZ: SORT Template Compile

The ^DIOZ API marks a SORT template compiled or uncompiled. The ^DIOZ API asks for the name of the SORT template to be used and whether the user wishes to do either of the following:

- Mark it compiled.
- Uncompile it if it is already marked compiled.

Actual compilation occurs at the time the template is used in the sort/print. There are no input or output variables.

SORT templates can be compiled into M routines to increase efficiency of the sort and improve system performance. Good candidates for compilation are sorts with many sort fields or those that sort on fields reached with relational syntax.



The process of sort compilation is different from other VA FileMan compiling activities:

- SORT templates can be “marked” for compilation, and then each time the SORT template is used in a VA FileMan sort/print, a new compiled routine is created.
- When the print job finishes, the routine is deleted.
- The routine is named DISZnnnn; where “nnnn” is a four-digit number.
- The routine names are reused. Thus, a routine name is *not* tied to a particular SORT template.
- Routine numbers are taken from the COMPILED ROUTINE (#.83) file.



**REF:** For more information on the routine numbers, see the “COMPILED ROUTINE File Cleanup: ENRLS^DIOZ()” section in the *VA FileMan Advanced User Manual*.

### 2.3.36 EN1^DIP: Print Data

Use the EN1^DIP AI to print a range of entries, in columnar format.

#### 2.3.36.1 Input Variables

**L:** (Required) String that evaluates to zero. A required variable that should be set to zero or some string whose numeric evaluation is zero (e.g., “LIST DRUGS”). If set to a text string, the string is used to replace the word “SORT” in the “SORT BY:” prompts, when VA FileMan asks the user for sort values:

```
LIST DRUGS BY: NAME//
```

**DIC:** (Required) The open global root of the file in the usual format [e.g., “^DIZ(16540,)”] or the file number.

**FLDS:** (Optional) The various fields to be printed. If this parameter is *not* sent, the user is prompted for fields to print. **FLDS** can contain the following:

- Numbers or names of the fields to be printed, separated by commas. These fields are printed in the order that they are listed.
- Print qualifiers, which determine column width, caption contents, and many other features of the output, can be included exactly as they are when answering the “PRINT FIELD:” prompt.



**REF:** For details on print qualifiers, see the “Print” section in the *VA FileMan User Manual*.

For example:

```
FLDS=".01,.03,1;C20"
```

If there are more fields than can fit on one string, **FLDS** can be subscripted [**FLDS(1)**, **FLDS(2)**, and so forth], but **FLDS** as a single-valued variable *must* exist.

The name of a PRINT template preceded by an open bracket (I) and followed by a close bracket (J). For example:

```
FLDS=" [ DEMO ] "
```

BY:

(Optional) The fields by which the data is to be sorted. If **BY** is undefined, the user is prompted for the sort conditions. You can sort by up to seven (7) fields (i.e., you can have up to a 7-level sort).

You can set **BY** to:

- The numbers or names of the fields separated by commas. Sort qualifiers, which determine aspects of the sort and of the printout, can be included exactly as they are when answering the “SORT FIELD:” prompt. For example:

```
BY=" .01 ; C1 , 1 "
```

If one of the comma pieces of the **BY** variable is the at-sign character (@), the user is asked for that SORT BY response. So, if you want to sort by DIAGNOSIS but allow the user to order the sort within DIAGNOSIS, set BY=“DIAGNOSIS,@”.

- The name of a SORT template preceded by an open bracket (I) and followed by a close bracket (J). For example:

```
BY=" [ DEMOSORT ] "
```



**NOTE:** You *cannot* use the name of a SORT template in the **BY** variable if the **BY(0)** input variable has been set. If you want to create such complex sorts, you can include the **BY(0)** information within the SORT template.



**REF:** For more information, see the “[Storing BY\(0\) Specifications in SORT Templates](#)” section.

- The name of a SEARCH template, preceded by an open bracket (I) and followed by a close bracket (J). The SEARCH template *must* have results stored in it. Only those records in the SEARCH template print, and they print in IEN order. For example:

```
BY=" [ DEMOSEARCH ] "
```



**NOTE:** If more than one field is included in the **BY** variable, separate the fields with commas. The same comma-pieces identify the field in the **FR** and **TO** variables. If, for example, you wanted a sorted report of entries with DOBs in 1960 and

with ZIP CODEs in the 90000s, you could define the variables by writing:

```
BY="DOB, ZIP CODE"  
FR="01/01/60,90000"  
TO="12/31/60,99999"
```

Since the delimiter of **BY** is a comma, the value placed in the variable should *not* contain a comma. Therefore, if your field name contains a comma, use the field number in the **BY** variable instead of its name. For the same reason, if sort from or to values contain commas, the alternate **FR**(*n*) and **TO**(*n*) input arrays described below should be used instead of the **FR** and **TO** input variables.

**FR:** (Optional) The “START WITH:” values of the SORT BY fields. If **FR** is undefined, the user is asked the “START WITH:” question for each SORT BY field. If **FR** is defined, it consists of one or more comma pieces, where the piece position corresponds to the order of the sort field in the **BY** variable. Each comma piece can be:

- Value from which the selection of entries begins.
- **Null**—If a comma piece of **FR** is null, then the sort starts from the very beginning of the file for that field.
- **?**—The question mark as one of the comma pieces causes the “START WITH:” prompt to be presented to the user for the corresponding SORT BY field.
- **@**—The at-sign indicates that the sort should begin with null values (i.e., with entries that have no data on file). If the corresponding piece of the **TO** variable or array also is set to @, then only entries with null values for this sort field are selected during the sort. If **TO** does *not* contain @, then after the null values, the sort starts at the first *non*-null value and goes to the value indicated by **TO**.



**NOTE:** If **BY** contains the name of a SORT template and if the developer answered **NO** to the question SHOULD TEMPLATE USER BE ASKED ‘FROM’-‘TO’ RANGE... for a field at the time the template was defined, then the information in the **FR** and **TO** variables is ignored for that field. Instead, the from/to ranges stored in the sort template are used.

If you customize sorts using **BY(0)**, see special note on **FR** in that section at the end of this call.

**FR**(*n*): (Optional) An alternate way to provide the “START WITH:” values of the SORT BY fields. If **FR** is defined, it overrides this array. The subscript “*n*” corresponds to the comma piece in the **BY** variable (i.e., the sort by field number). This alternate way of inputting the from and to values allows the use of values containing commas, such as PATIENT NAMES. Each *n*th entry in the array corresponds to, and can have the same value as, the *n*th comma piece in the **FR** variable. The only difference is that any *n*th entry, **FR**(*n*), can be undefined, causing the “START WITH:” question to be asked for the *n*th SORT FIELD.

For example, if you were using the unsubscripted **TO** and **FR** variables to do a sort on two fields, you might do as follows:

```
S FR="A,01/01/95",TO="Zz,01/31/95"
```

To set up the same sort using the subscripted forms of **TO** and **FR**, you would set them up as follows:

```
S FR(1)="A",FR(2)="01/01/95"  
S TO(1)="Zz",TO(2)="01/31/95"
```



**NOTE:** If you customize sorts using **BY(0)**, see special note on **FR** in that section at the end of this call.

TO:

(Optional) The “GO TO:” values of the SORT BY fields. Its characteristics correspond to the **FR** variable. If undefined, the user is asked the “GO TO:” questions for each SORT BY field. If **TO** is defined, it consists of one or more comma pieces. Each comma piece can be:

- Value at which the selection of entries ends.
- **Null**—If **TO** is null, then the sort goes from **FR** to the end of the file.
- **?**—The question mark as one of the comma pieces causes the “GO TO:” prompt to be presented to the user for the corresponding SORT BY field.
- **@**—The at-sign indicates that the sort should include null values (i.e., entries that have no data on file). If the corresponding piece of the **FR** variable or array also is set to **@**, then only entries with null values for this sort field are selected during the sort. If **FR** does *not* contain **@**, then after the null values, the sort starts at the **FR** value and includes all other *non-null* values to the end of the file.



**NOTE:** If **BY** contains the name of a SORT template and if the developer answered **NO** to the question “SHOULD TEMPLATE USER BE ASKED ‘FROM’-‘TO’ RANGE...” for a field at the time the template was defined, then the information in the **FR** and **TO** variables is ignored for that field. Instead, the from/to ranges stored in the SORT template are used.

TO(*n*):

(Optional) An alternate way to provide the “GO TO:” values of the SORT BY fields. If **TO** is defined, it overrides this array. The subscript “*n*” corresponds to the comma piece in the **BY** variable. This alternate way of inputting the from and to values allows the use of values containing commas, such as PATIENT NAMES. Each *n*th entry in the array corresponds to, and can have the same value as, the *n*th comma piece in the **TO** variable. The only difference is that any *n*th entry, TO(*n*), can be undefined, causing the “GO TO:” question to be asked for the *n*th SORT BY field.

If you customize sorts using **BY(0)**, see special note on TO(*n*) in that section at the end of this call.

- DHD: (Optional) The header desired for the output. **DHD** can be one of the following:
- @—If header is *not* desired.
  - @@—If header *and* form feed are *not* desired.
  - A literal that is printed, as is, in the upper left hand corner of the printout. The date, page, and field headings are in their normal places.
  - A line of M code that *must* begin with a write statement. For example:

```
DHD="W ?0 D ^ZZHDR"
```

- A PRINT template name preceded by an open bracket (I) and followed by a close bracket (J). In this case, the template replaces all parts of the header that VA FileMan normally generates.
- Two PRINT templates separated by a minus sign. The first is used as the header and the second is used as the trailer. For example:

```
DHD=" [ HEADER ] - [ TRAILER ] "
```

- DIASKHD: (Optional) Set to null (“”) to prompt user for a header:
- **Defined**—If this variable is defined, the user is prompted to enter a header.
  - **Undefined**—If this variable is undefined, the user does *not* have the opportunity to change the header on the print.

DIPCRIT: (Optional) If this variable is set to **1**, the SORT criteria prints in the header of the first page of the report.


PG: (Optional) Starting page number. If variable is undefined, page **1** is assumed.

DHIT: (Optional) A string of M code that is executed for every entry *after* all the fields specified in the **FLDS** variable have been printed.

DIOEND: (Optional) A string of M code that is executed *after* the printout has finished but *before* returning to the calling program.

DIOBEG: (Optional) A string of M code that is executed *before* the printout starts.

DCOPIES: (Optional) Number of copies to print (for SDP-type devices). If Kernel’s %ZIS chooses an SDP device and if multiple copies are desired, you can call for them by setting **DCOPIES** equal to the number (greater than one) of copies desired.

 **REF:** For more information about SDP devices, see the *Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide*.

IOP: (Optional) Name of device to which to send output. EN1^DIP calls the Kernel ^%ZIS API to determine to which device the output should go. This requires user interaction unless you pre-answer the DEVICE prompt. You can do this by setting **IOP** equal to the name of the device (as it is stored in the DEVICE [#3.5] file) to which the output should be directed. You can also set **IOP** in any of the additional formats recognized by Kernel’s ^%ZIS API to specify the output device.



**REF:** For more information on ^%ZIS and **IOP**, see the Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide.

If you need to call Kernel's ^%ZIS API beforehand to obtain the name of the device in question from the user, call it with the %ZIS N flag set so that ^%ZIS does *not* actually open the device. The name of the device is then returned in the **ION** output variable. EN1^DIP opens and closes the device you specify in **IOP** on its own; do *not* open it yourself beforehand.

In addition to setting **IOP** equal to a device for printing, you can use this variable (in conjunction with the **DQTIME** variable described immediately below) to queue the printing of a report. This functionality is only available if Kernel is present. Also, you *must* set up all of the input variables for EN1^DIP so that the user is *not* asked any questions. For example, the **BY**, **FR**, and **TO** variables *must* be defined. To establish queuing, **IOP** should equal **Q;output device**. For example:

```
>S IOP="Q;MY PRINTER - NLQ"
```

**DQTIME:** (Optional) Time to print, for queued printing. If output is queued, this variable contains the time for printing. You can set it equal to any value that %DT recognizes. For example:

```
S DQTIME="NOW"
```

Or:

```
S DQTIME="T@11PM"
```

**DIS(0):** (Optional) M code to screen out entries. You can screen out certain entries so that they do *not* appear on the output by setting the optional array **DIS**. The first subscript in this array can be 0 (zero). This variable (as well as all the others) contains an executable line of M code that includes an **IF**-statement. If the execution of the **IF** sets **\$T** to **1**, then the entry prints. The internal number of the entry being processed is in **D0**.

**DIS(n):** (Optional) Additional screens, "OR"-ed with each other, "AND"-ed with the **DIS(0)** screen. You can set other elements in the **DIS** array: **DIS(1)**, **DIS(2)**, **DIS(3)**, etc. The subscripts *must* be consecutive integers starting at **1**. Again, they *must* contain M code that sets **\$T**. If many elements are defined, then **DIS(0)** (if it exists) *must* be **true** and any one of the other elements in the array *must* be **true** for the entry to print.

**DISUPNO:** (Optional) Set to **1** to suppress output when no records are found. If this variable is set to **1** and if no records are found within the sort ranges specified for the print, the report header and the "No Records to Print" message is *not* printed.

**DISTOP:** (Optional) Set to **0** to prevent users from stopping prints. If Kernel is present, by default, prints queued through the EN1^DIP call can be stopped by the user with a TaskMan option. However, if this variable is set to **0**, users are *not* able to stop their queued prints.

**DISTOP** can also be set equal to M code that is executed once near the start of a queued print. If the code sets **\$T** to:

- **True**—User is able to stop the job.
- **False**—User is *not* able to stop the job.

For example:

```
S DISTOP="I DUZ(0) = "@""
```

This would mean that only those with programmer access could stop the print.

**DISTOP("C"):** (Optional) M code to execute if a user stops the print. If the user stops a queued print job by using TaskMan's option, code in this optional variable is executed before the output device is closed. It might, for example, do clean up necessary because the job did *not* run to completion.

### 2.3.36.1.1 Optional: Controlling Sorts with BY(0)

**BY(0):** For more information and a description of these variables, see the "[EN1^DIP: Controlling Sorts with BY\(0\) \(In Detail\)](#)" section.

**L(0):**

**FR(0,n):**

**TO(0,n):**

**DISPAR(0,n):**

**DISPAR(0,n, "OUT"):**

### 2.3.36.2 Output Variables

None.



**NOTE:** Unlike most calls, EN1^DIP **KILLS** all the input variables before it quits. You do *not* have to **KILL** them.

### 2.3.36.3 Details and Features

#### 2.3.36.3.1 Input Variables to Control Sorts

You can use a special set of input variables to:

- Preselect a set of records for printing.
- Preselect the order in which these records should be printed.

The set of variables for controlling sorts is:

- **BY(0)**
- **L(0)**
- **FR(0,n)**
- **TO(0,n)**
- **DISPAR(0,n)**
- **DISPAR(0,n, "OUT")**



**REF:** For more information and a description of these variables, see the [“EN1^DIP: Controlling Sorts with BY\(0\) \(In Detail\)”](#) section.

### 2.3.36.3.2 Setting up BY, FR, and TO Variables to Sort within a Multiple

If you have a file like:

```
.01 PARENT NAME
1 SPOUSE (mult.)
  .01 SPOUSE NAME
  1 SPOUSE DOB
  2 CHILDREN (mult.)
    .01 CHILDS NAME
    1 CHILDS DOB
    2 CHILDS SEX
    3 CHILDS NICKNAME
2 PARENT NICKNAME
```

And you wish to sort on the NICKNAME field for CHILDREN, from “A” to “Z”, then by the PARENT NICKNAME field from “B” to “E”. You set:

```
BY = "1,2,3,2"
FR = "A,B"
TO = "Z,E"
```

You *must* put in all field numbers to get down to the Multiple in the BY (1,2,3), but then it pops you out of the Multiple so that the following number “2” in the **BY** gets you Field #2 at the top-level (PARENT NICKNAME), rather than Field #2 within the lowest Multiple (SEX).

But note the **FR** and **TO**: here you just put the starting and ending values for the two fields on which you wish to sort.



**NOTE:** This same logic does *not* work on the **FLDS** Multiple. It is suggested that in order to print fields within a Multiple, the print logic should be set up in a PRINT template.



### 2.3.36.3 Using EN1^DIP to Print Audit Trails

The Audit files are structured differently than other VA FileMan files. To print audit trails for a file's data or Data Dictionary, the **DIC** variable *must* contain the global location of the requested audit file and the file number of the file that was audited as the open root:

- **Data Audit Trail**—To print a data audit trail for (fictitious) File #662001, set DIC="^DIA(662001,".
- **DD Audit Trail**—To print the DD audit trail, set DIC="^DDA(662001,".

The other input variables are set as for a normal print. Remember that the fields being printed and sorted come from the audit files, *not* from the file for which the audit trail was recorded.

### 2.3.36.4 EN1^DIP: Controlling Sorts with BY(0) (In Detail)

Ordinarily, you control the way EN1^DIP sorts output using the **BY**, **FR**, and **TO** input variables. This lets you sort based on field values, a previous sort stored in a SORT template, or on the records stored in a SEARCH template.

The **BY(0)** feature allows you to control the sort. With **BY(0)**, you can force VA FileMan to sort using an existing compound index (i.e., one that indexes more than a single data field) for efficiency. Also, use of **BY(0)** allows you to pre-sort a list of record numbers in a global and pass this pre-sorted list to EN1^DIP. This lets you pre-sort reports in any way that you can use subscripts to sort a global. The only limitation is that the total number of subscripts in the global that you sort by *must* be seven or less.

The two main ways in which the **BY(0)** feature should be used are as follows:

- Set **BY(0)** to the global location of an *existing* VA FileMan index. In particular, this lets you sort based on a MUMPS cross-reference or a compound cross-reference defined on the INDEX (#.11) file; *not* possible otherwise). Since the sorting is already done in advance, any such prints are very fast.
- Set **BY(0)** to the global location of a list of records you create “on-the-fly.” This lets you sort the records in any order you want, and also lets you easily limit the number of records by pre-selecting them.

### 2.3.36.5 Input Variables for Sorting with BY(0)

**BY(0):** (Optional; Required for **BY(0)** sorts) Set this variable to an open global root. The open global root should be the static part of a global; a list of record numbers *must* be stored at a descendent subscript level.

```
^DIZ(662001,"E","FM-ALBERT",1009)
^DIZ(662001,"E","FM-ANDREA",339)
^DIZ(662001,"E","FM-ANDREW",552)
-----
<-static part-> <-dynamic part->
```

In this example, you would set **BY(0)** to '^DIZ(662001,"E",,'.

There can be intervening subscript levels between the static, fixed global root and the subscript level where the list of records numbers is stored. Any intervening subscript levels define a sort order. Use the **L(0)** input variable to tell VA FileMan the number of dynamic subscript levels it needs to sort through [see **L(0)** description below].

Alternatively, you can set **BY(0)** to the name of a SEARCH template, in [brackets]. This tells VA FileMan to sort on the list of record numbers contained in the corresponding SEARCH template entry in the ^DIBT global.

**BY(0)** affects your sorts as follows:

- It restricts the possible records for printing to those in the specified list.
- When you set **BY(0)** to a static global reference, each intervening subscript level (between the static part of the global reference and the subscript level containing record numbers) defines a sort level, starting from the highest intervening subscript level.

### **BY(0) for a VA FileMan Index**

If you set **BY(0)** to sort based on an existing VA FileMan-maintained cross-reference, make sure the subscript you set **L(0)** to point to is in fact the location where VA FileMan stores its list of records [when sorting on a regular single-field index, **L(0)** should be 2].

### **BY(0) for a List of Records “On-the-Fly”**

If you build your own list of sorted records on-the-fly in a temporary global (as opposed to setting **BY(0)** to a VA FileMan-maintained cross-reference), it is best *not* to let the final subscript of your static global reference be “**B**”.



**REF:** For more information, see the discussion in the [“Details and Features”](#) section.



**NOTE:** If you are using both the **BY** and **BY(0)** input variables, do *not* set **BY** to the name of a template; an error message will print or hard errors could result.

**L(0):**

(Optional; Required if **BY(0)** is set to an open global root.)

Use **L(0)** to specify the number of dynamic subscript levels that exist beyond the static global root, including the subscript level containing the list of record numbers. The minimum value of **L(0)** is 1.

EN1^DIP lets you sort by up to seven (7) subscripts; therefore, the maximum value of **L(0)** is 8.

For example, if **BY(0)** refers to a regular “**E**” index on a file [e.g., '^DIZ(662001,“E”,’ ] you should set **L(0)=2** [i.e., one for the subscript containing the (dynamic) value of the field being cross-referenced, plus one for the record number].

**FR(0,*n*):**

(Optional) To select only a subset of records at a given subscript level “*n*”, you can use **FR(0,*n*)** and **TO(0,*n*)**. For “*n*” equal to any of the “*n*” dynamic sorting subscript levels in the global specified by **BY(0)**, you can set **FR(0,*n*)** to the sort-from value for that subscript level.

This restricts the printed records to those whose subscript values at subscript level *n* sort the same or greater than the value you set into **FR(0,*n*)**. If **FR(0,*n*)** is undefined for any subscript *n*, the sort on that subscript level begins with the first value for that subscript.



**NOTE:** These values *must* be in VA FileMan internal format, as they are stored in the subscript of the index or global defined by **BY(0)**.

TO(0,*n*):

(Optional) This variable contains the ending value (the sort-to value) for any of the “*n*” dynamic sorting subscripts in the global specified by **BY(0)**. If **TO(0,*n*)** is undefined for any subscript “*n*”, the sort on that subscript level ends with the last value for that subscript.



**NOTE:** These values *must* be in VA FileMan internal format, as they are stored in the subscript of the index or global defined by **BY(0)**.

DISPAR(0,*n*)

(Optional) Like the **FR(0,*n*)** and **TO(0,*n*)** variables, this variable array can be set for any of the “*n*” dynamic sorting subscripts in the global specified by **BY(0)**. This array allows you to create subheaders for the sorting subscripts in the global. In order to create a sub-header, you *must* define a title for the subscript, as VA FileMan has no knowledge of the subscripts. Each entry in the array can have information in two ^-pieces:

1. The first piece contains the sort qualifiers that are normally entered interactively before a sort field.



**REF:** For more information, see the *VA FileMan User Manual*.

Two of the sort qualifiers can be used here:

- !—Number the entries by sort value.
- #—Page break when the sort values changes.

2. The second piece contains the sort qualifiers that are normally entered interactively after the sort field. In order to print a subheader, you *must* enter literal subheader “caption” (e.g., “Station/PO Number: ”). To have no subheader text other than the subheader value, use a null caption (e.g., “”).

You can also use the any of the following *sort qualifiers*:

- ;Cn
- ;Ln
- ;Sn



**REF:** For more information, see the *VA FileMan User Manual*.

The subheaders defined in **DISPAR(0,*n*)** *cannot* be suppressed.

DISPAR(0,*n*,”OUT”):

(Optional) If a literal title is input to **DISPAR(0,*n*)** above, then you can also enter M code to transform the value of the subscript from the global before it is printed as a subheader. It acts like an OUTPUT transform. At the time of execution, the untransformed value is in **Y**. The code should put the transformed value back into **Y**. Any other variables used in the code should be NEWed.

## 2.3.36.6 Examples

### 2.3.36.6.1 Example 1

Suppose you have a simple MUMPS cross-reference that inverts dates so that the values in the cross-reference are 99999999-date. The cross-reference might look something like:

**Figure 34: EN1^DIP API—Example 1: Cross-Reference**

```
^DIZ(662001,"AC",97069889,2)=""  
^DIZ(662001,"AC",97969898,3)=""  
^DIZ(662001,"AC",97969798,1)=""  
...etc.
```

If you wanted to sort all entries by this inverse date and to convert the date values into a readable format for the subheader, you would set up the variables for the EN^DIP call like this:

**Figure 35: EN1^DIP API—Example 1: Setting Up Variables**

```
S DIC="^DIZ(662001,"L=0,FLDS="your field list"  
S BY(0)="^DIZ(662001,"AC","  
S L(0)=2  
S DISPAR(0,1)="^;"DATE""  
S DISPAR(0,1,"OUT")="S:Y Y=99999999-Y S Y=$$FMTE^XLFD(Y)"
```

### 2.3.36.6.2 Example 2

Suppose you have a list of record numbers in a global that looked like this:

**Figure 36: EN1^DIP API—Example 2: Sample Record Numbers**

```
^TMP($J,1)=""  
^TMP($J,3)=""  
^TMP($J,35)=""  
^TMP($J,39)=""  
...etc.
```

If you wanted to print those records sorted by the .01 field of the file, you would:

**Figure 37: EN1^DIP API—Example 2: Input to Sort and Print Records**

```
S DIC="^DIZ(662001,"L=0,BY=.01,(FR,TO)="",FLDS="your field list"  
S BY(0)="^TMP($J,"  
S L(0)=1
```

### 2.3.36.6.3 Example 3

Suppose you have a MUMPS multi-field-style cross-reference, with subscripts based on the values of two fields. The first field in the subscript is free-text, and the second is a number. The cross-reference might look like:

**Figure 38: EN1^DIP API—Example 3: Cross-Reference**

```
^DIZ(662001,"AD","ANY",4.99,5)=""  
^DIZ(662001,"AD","ANYTHING",1.3,2)=""  
^DIZ(662001,"AD","ANYTHING",1.45,1)=""  
^DIZ(662001,"AD","SOMETHING",.4,10)=""  
...etc.
```

You want to sort from value “A” to “AZ” on the free-text field and from 1 to 2 on the numeric field. Also, you want to print a subheader for the numeric field. You could set your variables like this:

**Figure 39: EN1^DIP API—Example 3: Input Setting Variables to Sort and Print**

```
S DIC="^DIZ(662001," ,L=0,FLDS="your field list"
S BY(0)="^DIZ(662001,""AD"" ,
S L(0)=3
S FR(0,1)="A",TO(0,1)="AZ"
S FR(0,2)=1,TO(0,2)=2
S DISPAR(0,2)="^;" "NUMBER""
S DISPAR(0,2,"OUT")="S Y=$J(Y,2)"
```

## 2.3.36.7 Details and Features

### 2.3.36.7.1 Sorting on MUMPS Cross-References

The **BY(0)** feature is designed to let you pre-sort your VA FileMan reports using MUMPS cross-references. As long as the MUMPS cross-reference has 0 to 7 dynamic (sorting) subscripts, followed by the record numbers stored in a final subscript level, you can order your reports based on that cross-reference using **BY(0)**.

While you can have used MUMPS cross-references in the past only for sorting hard-coded reports, you can consider using them with VA FileMan-based reports as well.

### 2.3.36.7.2 Sorting a Compound Cross-reference Defined in the INDEX (#.11) File

The **BY(0)** feature allows you to sort using a compound cross-reference on the INDEX (#.11) file



**NOTE:** A compound cross-reference is one that indexes more than one data field.

This feature lets you use any index that has no more than seven (7) data valued subscripts.

### 2.3.36.7.3 Sorting Using One or More Subscript Levels

Each intervening subscript level between the static part of the open global root in **BY(0)** and the record number subscript level serves as one sort level, starting with the highest subscript level.

In [Example 3](#), the records would sort by the value of the free-text field stored in the first dynamic subscript, and within that by the value of the numeric field stored in the second dynamic subscript.

### 2.3.36.7.4 Additional Sorting with BY, FR, and TO

When using **BY(0)**, you can still sort in the usual way (setting **BY**, **FR**, and **TO**) to *further* sort and limit the range within the list provided by **BY(0)**.



**NOTE:** If you set **BY(0)**, **BY** cannot contain the name of a SORT template.



**REF:** If your sort is complicated, see the [“Storing BY\(0\) Specifications in SORT Templates”](#) section.

VA FileMan selects only the list of records specified by **BY(0)** and its associated variables. VA FileMan accepts as-is the sort sequence created by any dynamic subscripts in the global specified in **BY(0)**. Then within that sort sequence, it further sorts the records by the information provided in the **BY**, **FR**, and **TO** variables.

You can only sort by up to seven (7) sort levels in EN1^DIP, so the number of subscripts you sort by using **BY(0)** combined with the number of fields you sort by using **BY** *must not* total more than 7.

If **BY(0)** has been defined without the **BY**, **FR**, and **TO** variables, the user is *not* prompted for the SORT BY or FROM/TO ranges.

### 2.3.36.7.5 Storing **BY(0)** Specifications in SORT Templates

You can store the **BY(0)** information in a SORT template, in order to design more complicated sorts. This allows you to sort using the global described in the **BY(0)** variable, and within those subscripts, to sort by additional fields and to save the entire sort description into a template. You need programmer access to do this.

In VA FileMan's sort dialogue (with programmer access), at the "SORT BY:" prompt, you can enter the characters **BY(0)** as shown in [Figure 40](#). When you enter **BY(0)**, you are then prompted for the **BY(0)**, **L(0)**, and all related values; exactly the same as if they were entered as input variables to the EN1^DIP call.

**Figure 40: EN1^DIP API—Sort **BY(0)** Example**

```
Select OPTION: 2 <Enter> PRINT FILE ENTRIES

OUTPUT FROM WHAT FILE: ZZTAMI TEST// <Enter>
SORT BY: NAME// BY(0)

BY(0): // ^DIZ(662001,"H",
L(0): // 2

Edit ranges or subheaders? NO// YES

SUBSCRIPT LEVEL: 1// 1
FR(0,n): // 2690101
TO(0,n): // 2701231
DISPAR(0,n) PIECE ONE: // <Enter>
DISPAR(0,n) PIECE TWO: // ;"Date of Birth: "
DISPAR(0,n,OUT): // S Y=$$FMTE^XLFD(Y,1)

Edit ranges or subheaders? NO// <Enter>

BY(0)=^DIZ(662001,"H",      L(0)=2

SUB: 1 FR(0,1): 2690101
      TO(0,1): 2701231
      DISPAR(0,1) PIECE ONE:
      DISPAR(0,1) PIECE TWO: ;"Date of Birth: "
      DISPAR(0,1,OUT): S Y=$$FMTE^XLFD(Y,1)

OK? YES// <Enter>
Enter additional sort fields? NO// YES

WITHIN BY(0), SORT BY: NAME
START WITH NAME: FIRST// <Enter>
      WITHIN NAME, SORT BY: <Enter>

STORE IN 'SORT' TEMPLATE: ZZTAMIBY0
```

When you enter **BY(0)**, you are prompted for **BY(0)** and **L(0)**. In addition, you are asked if you want to edit ranges or subheaders. This lets you enter the **FR(0,n)**, **TO(0,n)**, **DISPAR(0,n)**, and **DISPAR(0,n,"OUT")** values for various subscript levels. This lets you specify all the aspects of sorting using **BY(0)**. You can store these criteria in a SORT template. If you answer **YES** to "Enter additional sort fields?", you are allowed to enter additional sort fields; exactly the same as you would when creating a SORT template without the **BY(0)** features.

The functionality of **BY(0)** interactively or in a SORT template is identical to its functionality in the EN1^DIP API.

An error results if, in a call to EN1^DIP, you sort by a SORT template that contains **BY(0)** sort criteria, and also use **BY(0)** as an input variable.



**NOTE:** The sort ranges associated with subscripts in the **BY(0)** global or index can be set dynamically by setting the **FR(0,n)** and **TO(0,n)** input variables. These input variables override any sort ranges set in the template.

The “SUBSCRIPT LEVEL” prompt refers to the position of the data value in the global or index. Thus, entering a value for **FR(0,n)** when the SUBSCRIPT LEVEL is **1**, sets the “from” value for the first data valued subscript.

Use the documentation for the **BY(0)** and related input variables for additional help. Also, be sure to use online **?** and **??** help.

[Figure 41](#) is an example of how to call EN1^DIP when the **BY(0)** information is contained in a template:

**Figure 41: Example of How to Call EN1^DIP when the BY(0) Information is Contained in a Template**

```
S DIC="^DIZ(16600," ,L=0,BY="[ZZTEST]" ,FR(0,1)=70001,FLDS=.01
D EN1^DIP
```

#### 2.3.36.7.6 **BY(0)** “Don’ts”

You should *not* use **BY(0)** if you are merely setting it to the global location of an existing regular cross-reference. You do *not* gain any speed, because VA FileMan’s built-in sort optimizer already knows to sort on regular cross-references.

Also, do *not* specify a field’s regular cross-reference as the global reference in **BY(0)** to sort on, and then sort on the same field using the **BY**, **FR**, and **TO** variables. This actually increases the amount of work VA FileMan needs to do!

#### 2.3.36.7.7 “On-the-Fly” Globals Whose Static Global Reference Ends with “B”

If you build your own list of sorted records on-the-fly in a temporary global [as opposed to setting **BY(0)** to a VA FileMan-maintained cross-reference], it is best *not* to let the final subscript of your static global reference be “**B**”.

This avoids problems that might be caused by VA FileMan’s special handling of the “**B**” index for mnemonic cross-references.

### 2.3.37 ^DIPT: PRINT Template Display

The PRINT TEMPLATE (#.4) file contains a computed field labeled PRINT FIELDS that displays a PRINT template exactly as it was entered. Use the ^DIPT API to make this display immediately available to a user.

#### Input Variable

D0: (Required) Set **D0** equal to the internal number of the template in the PRINT TEMPLATE (#.4) file. For example, to display the PRINT template whose record number is 70:

```
S D0=70 D ^DIPT
```



**NOTE:** Use the number **0** (zero) *not* the letter **O** in this variable name.

### 2.3.38 DIBT^DIPT: SORT Template Display

The SORT TEMPLATE (#.401) file contains a computed field labeled SORT FIELDS that displays a SORT template exactly as it was entered. Use the v API to make this display immediately available to a user.

#### Input Variable

D0: (Required) Set **D0** equal to the internal number of the template in the SORT TEMPLATE (#.401) file. For example, to display the SORT template whose record number is 70:

```
S D0=70 D DIBT^DIPT
```



**NOTE:** Use the number **0** (zero) *not* the letter **O** in this variable.

### 2.3.39 ^DIPZ: PRINT Template Compile for Code Generation—User Interactive

PRINT templates can be compiled into M routines just as INPUT templates can be. The purpose of the DIPZ code generation is simply to improve overall system throughput.

Only regular PRINT templates can be compiled. You *cannot* compile the following, which are also stored in the PRINT TEMPLATE (#.4) file:

- FILEGRAM
- EXTRACT
- Selected Fields for Export
- EXPORT templates



Call the user interactive ^DIPZ API and specify the following:

- Maximum routine size
- Name of the PRINT template to be used
- Name of the M routine to be created
- Margin width to be used for output (typically 80 or 132)

If you specify the routine name XXX and if more code is generated than can fit into that one routine, overflow routines (XXX1, XXX2, etc.) is created. Routine XXX can call XXX1, XXX2, etc.

Once DIPZ has been used to create a hard-coded output routine, that routine is usually invoked automatically by VA FileMan within the Print File Entries [DIPRINT] and Search File Entries [DISEARCH] options and when called at [EN1^DIP](#) whenever the corresponding PRINT template is used. The compiled routines are *not* used if a user-specified output margin width is less than the compiled margin. Also, if the template is used with ranked sorting (i.e., the ! sort qualifier is used), the compiled version is *not* used.

As with compiled INPUT templates, as soon as data dictionary definitions of fields used in the PRINT template are changed, the hard-core routines are compiled immediately.

### 2.3.39.1 Invoking Compiled PRINT Templates

A DIPZ-compiled M routine can be called by any program that passes to it the following variables:

- **DT**
- **DUZ**
- **IOSL** (screen length)
- **U (^)**
- **D0** (the entry number to be displayed)

Additionally, the variable **DXS** *must* be KILLED *before* calling the routine and *after* returning from it. The compiled routine writes out its report for that single entry. However, routines compiled from templates that include statistical totals *cannot* be called in this way.

### 2.3.40 EN^DIPZ: PRINT Template Compile—No User Interaction

PRINT templates can be compiled into M routines just as INPUT templates can be. The purpose of this DIPZ code generation is simply to improve overall system throughput.

Only regular PRINT templates can be compiled. You *cannot* compile the following, which are also stored in the PRINT TEMPLATE (#.4) file:

- FILEGRAM
- EXTRACT
- Selected Fields for Export
- EXPORT templates

The EN<sup>^</sup>DIPZ API recompiles a PRINT template *without* user intervention by setting the following input variables:

### Input Variables

- X: The routine name.
- Y: The internal number of the template to be compiled.
- DMAX: The maximum size the compiled routines should reach. Consider using the [\\$\\$ROUSIZE<sup>^</sup>DILF](#) function to set this variable.

## 2.3.41 D<sup>^</sup>DIQ: Converts Internal Date to External Form

The D<sup>^</sup>DIQ API takes an internal date in the Y variable and converts it to its external form. This API is very similar to [DD<sup>^</sup>%DT](#).

### Input Variable

- Y: (Required) Contains the internal date to be converted. If this has five or six decimal places, seconds are automatically returned.

### Output Variable

- Y: External form of the date or date/time value (e.g., JAN 01, 1998).

## 2.3.42 DT<sup>^</sup>DIQ: Converts Internal Date to External Form and Writes Date

The DT<sup>^</sup>DIQ API converts the date in the Y variable exactly like [D<sup>^</sup>DIQ](#). Unlike [D<sup>^</sup>DIQ](#), however, it also writes the date after it has been converted.

### Input Variable

- Y: (Required) Contains the internal date to be converted. If this has five or six decimal places, seconds are automatically returned.

### Output Variable

- Y: External form of the date or date/time value (e.g., JAN 01, 1998).

### 2.3.43 EN^DIQ: Displays Captioned Range of Data

The EN^DIQ API displays a range of data elements in captioned format, to the current device. The output from this API is very similar to that of the Inquiry to File Entries option [DIINQUIRE].



**REF:** For more information on the Inquiry to File Entries option [DIINQUIRE], see the “Inquire Option” section in the *VA FileMan User Manual*.

#### Input Variables

- DIC:** (Required) The global root of the file in either of the following forms:
- ^GLOBAL(
  - ^GLOBAL(#,
- If you are displaying an entry in a subfile, set **DIC** to the full global root leading to the subfile entry, including all intervening subscripts and the terminating comma, up to, but *not* including, the IEN of the subfile entry to display.
- DA:** (Required) If you are displaying an entry at the *top-level* of a file, set **DA** to the internal entry number of the file entry to display.
- If you are editing an entry in a subfile, set up **DA** as an array, where:
- **DA**—Entry number in the subfile to display.
  - **DA(1)**—Entry number at the next higher file level, etc.
  - **DA(n)**—Entry number at the file’s top-level.
- DR:** (Optional) Names the global subscript or subscripts that are to be displayed by DIQ. If **DR** contains a colon (:), the range of subscripts is understood to be specified by what precedes and follows the colon. Otherwise, **DR** is understood to be the literal name of the subscript. All data fields stored within, and descendent from, the subscripts are displayed, even those that normally have Read access security protection.
- If **DR** is *not* defined, all fields are displayed.
- DIQ(0):** (Optional) You can include the following flags in this variable to change the display of the entry:
- **A**—To display **A**udit records for the entry.
  - **C**—To display **C**omputed fields.
  - **R**—To display the entry’s **R**ecord number (IEN).

### 2.3.44 Y^DIQ: Converts Internal Data to External Form

The Y^DIQ API converts the internal form of any data element to its external form. It does the following:

- Works for all VA FileMan data types.
- Uses output transforms.
- Follows pointer trails to their final resolution.

The equivalent Database Server call is [\\$\\$EXTERNAL^DILFD](#).

## Input Variables

Naked Global Reference:

The naked global reference *must* be at the zero node of the data dictionary definition that describes the data [i.e., it *must* be at `^DD(File#,Field#,0)`].



**REF:** For an example of setting the naked reference, see the description of the **C** input variable below.

**C:** Set **C** to the second piece of the zero node of the data dictionary that defines that element. Typically, the developer would:

```
S C=$P(^DD(file#,field#,0),U,2)
```

And then:

```
D Y^DIQ
```

This correctly sets the **Naked Global Reference** as described above.

**Y:** Set **Y** to the internal form of the value being converted. This is the data that you want to convert to external form.

## Output Variable

**Y:** The external form of the value. Basically, **Y** is changed from internal to external.

### 2.3.45 EN^DIQ1: Data Retrieval

The EN^DIQ1 API retrieves data from a file for a particular entry.



**NOTE:** The equivalent Database Server calls are [GETS^DIQ](#) and [\\$\\$GET1^DIQ](#).

It is your responsibility to **KILL** the output array, `^UTILITY("DIQ1",$J)`, before and after using this call.

## Input Variables

**DIC:** (Required) The file number or global root.

**DR:** (Required) A string specifying the data fields to retrieve for the given entry. The **DR**-string can contain:

- A single number corresponding to the internal number of a field in the file.
- A range of field numbers, in the form **M:N**; where:
  - **M**—First number of the inclusive range.
  - **N**—Last number of the inclusive range.All fields whose numbers lie within this range are retrieved.
- A combination of the above, separated by semicolons. For example if field numbers **.01, 1, 2, 4, 10, 11, 12, 13, 14, 15**, and **101** exist for a file, and you want to retrieve the data in these fields, simply write:

```
S DR=".01;1;4;10:15;101"
```

**DR(subfile\_number):** (Optional) If you want to retrieve values from fields from a subentry in a Multiple field, include the top-level field number for the Multiple in **DR**. Then, include the Multiple's subfield numbers whose values you want to retrieve in a node in **DR**, subscripted by the subfile number.



**REF:** To specify which subfile entry to retrieve, see also the [DA\(subfile number\)](#) variable.

For example, if you want to retrieve data from subfields **.01** and **7** for subentry **1** from Field #4 that defines the (fictitious) Multiple #16000.02, then you write:

```
S DIC=16000,DR="4",DA=777
S DR(16000.02)=".01:7",DA(16000.02)=1
D EN^DIQ1
```

**DA:** (Required) The internal number of the entry from which data is to be extracted.

**DA(subfile\_number):** (Optional) If you want to retrieve values from fields from a subentry in a Multiple, set **DA** to the top-level entry number. Then, include the subentry number in a node in **DA**, subscripted by the subfile number.



**REF:** For how to specify which fields in the subfile entry to retrieve, see the [DR\(subfile number\)](#) variable.

You can descend one or more subfile levels; however, you can only retrieve values for one subentry at any given subfile level. The full path from the top-level of the file to the lowest-level subfile entry *must* be fully specified in nodes in the **DR** and **DA** variables.

**DIQ:** (Optional) The local array name into which the field values are placed. **^UTILITY("DIQ", \$J)**, is used if **DIQ** is *not* present. This array name should *not* begin with **DI**.

**DIQ(0):** (Optional) This variable is used to control which is returned:

- Internal values
- External values
- Both internal and nexternal values

**DIQ(0)** also indicates when null values are *not* returned. The **DIQ(0)** string can contain the values that follow:

- **I**—Return **I**nternal values.
- **E**—Return **E**xternal values.
- **N**—Do *not* return **N**ull values.

## Output

The format and location of the output from **EN^DIQ1** depends on the status of input variables **DIQ** and **DIQ(0)** and on whether or not a **WORD-PROCESSING** field is involved.

### 2.3.45.1 DIQ and DIQ(0) Undefined

Output into:

**Figure 42: EN^DIQ1 API—Data Retrieval: DIQ and DIQ(0) Undefined**

```
^UTILITY("DIQ1", $J, file#, DA, field#)=external value
```

This is for backward compatibility. Each field requested is defined in the utility global but the value can be null. The only exception to this would be when **DA** held the number of an entry that does *not* exist. In that case, nothing is returned. The values returned are the external values. Printable values (e.g., pointers, sets of codes, etc.) are resolved; dates are in external format.

### 2.3.45.2 DIQ(0) Defined, DIQ Undefined

Output into:

**Figure 43: EN^DIQ1 API—Data Retrieval: DIQ(0) Defined, DIQ Undefined**

```
^UTILITY("DIQ1", $J, file#, DA, field#, "E")=external value
^UTILITY("DIQ1", $J, file#, DA, field#, "I")=internal value
```

If **DIQ(0)** contains:

- **E**—The external value is returned with a final global subscript of “**E**”.
- **I**—The internally stored value is returned with a final global subscript of “**I**”. The internal value is the value stored in the file, for example, the record number of the entry in the pointed-to file, *not* the resolved value of the pointer. Since computed fields store no data, no nodes are returned for computed fields.
- **N**—No nodes are set for either internal or external values if the field is null.
- **Both I and E**—Generally two nodes are returned for each field: one with the internal value, one with the external value. However, no nodes are produced for the internal value if the field is computed and no nodes are produced at all for null-valued fields if **DIC(0)** contains **N**. Nodes are subscripted as described above.

### 2.3.45.3 DIQ Defined

The output is similar except that the data is stored in the specified local array. So if **DIQ(0)** is *not* defined, then the output is:

**Figure 44: EN^DIQ1 API—Data Retrieval: DIQ Defined**

```
@(DIQ(file#, DA, field#))=external value
```

If **DIQ(0)** is defined, then the output is:

**Figure 45: EN^DIQ1 API—Data Retrieval: DIQ Defined: Output**

```
@DIQ(file#, DA, field#, "E")=external value
@DIQ(file#, DA, field#, "I")=internal value
```

### 2.3.45.4 Word-Processing Field

Output from a WORD-PROCESSING field is only an external value. The status of **DIQ(0)** has no effect. If **DIQ** is *not* defined, it goes into the global nodes that follow:

**Figure 46: EN^DIQ1 API—Data Retrieval: Word-Processing Field**

```
^UTILITY("DIQ1", $J, file#, DA, field#, 1)
^UTILITY("DIQ1", $J, file#, DA, field#, 2)
.
.
.
```

If **DIQ** is defined, it goes into:

**Figure 47: EN^DIQ1 API—Data Retrieval: Word-Processing Field: DIQ is Defined**

```
@DIQ(file#, DA, field#, 1)=External Value 1
@DIQ(file#, DA, field#, 2)=External Value 2
@DIQ(file#, DA, field#, 3)=External Value 3
@DIQ(file#, DA, field#, 4)=External Value 4
.
.
.
```

### 2.3.46 ^DIR: Response Reader

DIR is a general purpose response reader that can be used to:

1. Issue a prompt.
2. Read input interactively.
3. Perform syntax checking on the input.
4. Issue error messages or help text.
5. Return input in a processed form.

Its use is recommended to standardize user dialogue and to eliminate repetitive coding.

If DIR fails the syntax checking, it will automatically uppercase the input and retry the syntax checking.

DIR is reentrant; A DIR call can be made from within a DIR call. To reenter DIR, use the **NEW** command to save the DIR array (**NEW DIR**) before setting input variables and making the second call.

- [Input and Output Variables \(Summary\)](#)
- [Required Input Variables \(Full Listing\)](#)
- [Optional Input Variables \(Full Listing\)](#)
- [Output Variables \(Full Listing\)](#)
- [Examples](#)



**CAUTION:** KILL the DIR variable *after* the ^DIR call, so that other VA FileMan APIs that also use the ^DIR reader are *not* affected.



**NOTE:** DIR exits after **50** consecutive failed read attempts (to prevent infinite loops).



**NOTE:** If DIR fails the syntax checking, it will automatically uppercase the input and retry the syntax checking.

### 2.3.46.1 Input and Output Variables (Summary)

Make sure to perform the following steps before calling this API:

- NEW all variables.
- Set all input variables.
- Call the API.

#### Input Variables-Required (Summary)

DIR(0): (Required) First character of Piece-1 (first 3 characters for DD-type)

- (Optional) Subsequent characters of Piece-1—Read type: Input modifiers
- (Optional) Piece-2—Read type: Input parameters
- (Optional) Piece-3—Read type: INPUT transform

#### Input Variables-Optional (Summary)

DA: For DD-type reads, can specify entry from which to retrieve default value.

DIR("A"): Developer-supplied prompt to override default.

DIR("A",#): Optional array of additional lines to display when **DIR("A")** is specified.

DIR("B"): Default response.

DIR("L"): For set-of-code fields: developer-specified format to display codes.

DIR("L",#): Optional array of additional lines to display when **DIR("L")** is specified.

DIR("S"): Screen for pointer, set-of-code, and list/range reads.

DIR("T"): Time specification to be used instead of **DTIME**.

DIR("?"): Help displayed when the user enters a single question mark (?).

DIR("?",#): Optional array of additional lines to display when **DIR("??")** is specified.

DIR("??"): Help displayed when the user enters a double question mark (??).

#### Output Variables-Always Returned

X: Unprocessed user response.

Y: Processed user response.

#### Output Variables-Conditionally Returned

Y(0): External form of response for set, pointer, list, and date.

DTOUT: Defined if the user times out.

DUOUT: Defined if the user entered a caret (^).



DIRUT: Defined if the user entered a caret (^), pressed **Enter**, or timed out.

DIROUT: Defined if the user enters two carets (^ ^).

### 2.3.46.2 Required Input Variables (Full Listing)

DIR(0): **DIR(0)** is the only required input variable. It is a three-piece variable. The first character of the first piece *must* be defined (or first 3 characters for DD-type). Additional characters of the first piece and the second two pieces are all optional.

The first character of the first caret (^) piece indicates the type of the input to be read. The second piece describes parameters, delimited by colons (:), to be applied to the input. Examples are maximum length for free text data or decimal digits for numeric data. The third piece is executable M code that acts on the input in the same manner as an INPUT transform. The acceptable types are shown in [Table 31](#):

**Table 31: DIR(0)—Summary of Acceptable Types**

DIR(0) Read Type	Piece-1: First Character (Required)	Subsequent Characters (Optional)	Piece-2: Format	Piece-3: Executable M code (Optional)
Date	D	A,O	Minimum date:- Maximum date:%DT	code
End-of-Page	E	A	--	--
Free-text	F	A,O,U,r	Minimum length: Maximum length	code
List or range	L	A,O,C	Minimum:Maximum:M aximum decimals	code
Numeric	N	A,O	Minimum:Maximum:M aximum decimals	code
Pointer	P	A,O,r	Global Root or #:DIC(0)	cod
Set of Codes	S	A,O,X,B	Code: Stands for;Code: stands for;	code
Yes/No	Y	A,O	--	code
DD	#, #	A,O,r	--	code

## DIR(0) (Detailed Explanation):

### Piece-1 of DIR(0) (Subsequent Characters are Optional):

The first caret (^) piece of **DIR(0)** can contain other parameters that help to specify the nature of the input or modify the behavior of the reader. These characters *must* appear after the character indicating type (or after the field number if it is a DD type). They are described below and examples are provided later in this section):

- **A**—Indicates that nothing should be Appended to the developer-supplied prompt **DIR("A")**, which is described below. If there is no **DIR("A")**, then no prompt is issued.
- **B**—Only applies to a set of codes; indicates that the possible choices are to be listed horizontally after the prompt.
- **C**—Only applies to list reads. The values returned in **Y** and the **Y()** array are Compressed. They are *not* expanded to include each individual number; rather, ranges of values are returned using the hyphen syntax. This is similar to the format in which the user can enter a range of numbers.

This flag is particularly useful when a user can select many numbers (e.g., when decimals are involved). The call is much faster and the possibility of the local symbol table filling up with nodes in the **Y()** array is eliminated.

- **O**—Indicates that a response is Optional. If this is *not* included, then a null response is *not* allowed. For DD type reads, the **O** is automatically included if the field in question is *not* a required field.
- **r**—If user does *not* choose to accept the default, they *must* type in their entire response. They do *not* get the “Replace-With” prompt, regardless of how long the default response is.
- **U**—Only applies to free text reads. It allows the user response to contain a caret (^; aka Up-Arrow). A leading caret aborts the READ and SET's **DUOUT** and **DIRUT** whether or not **U** is in **DIR(0)**. However, **U** allows ^s to be embedded in the user response.
- **X**—Only applies to set of codes. Indicates a request for an eXact match. No lowercase to uppercase conversion is to be done.

### Piece-2 of DIR(0) (Optional):

Qualifying limits on user response are as described in summary [Table 31](#).

### Piece-3 of DIR(0) (Optional):

The third piece of **DIR(0)** is executable M code that acts like the INPUT transform of a field in a data dictionary. The value that was entered by the user is contained in the variable **X**. The code can examine **X** and, if it is *not* appropriate, should **KILL X**.

If **X** is undefined after the execution of the third piece of **DIR(0)**, the reader knows that:

1. The input was unacceptable.
2. Issues a help message.
3. Re-asks for input.

It is unnecessary to put checks for minimum and maximum or length in the third piece. These should be specified in the second piece of **DIR(0)**. An example of **DIR(0)** with all three pieces is:

```
S DIR(0) = "F^3:30^K:X'? .U X"
```

This means that if the input is *not* all uppercase, then the data is unacceptable. The check for a length from 3 to 30 characters takes place automatically because of the second piece. The third piece is *not* executed if the specifications in the second piece are *not* met. If the user combines the DD data type with a third piece in **DIR(0)**, for example:

```
S DIR(0)="19,.01^^K:X'?1" "DI" " X"
```

Then, the third piece of **DIR(0)** is *not* executed until after the INPUT transform has been executed and **X** was *not* **KILLED** by the transform.

For pointer-type reads, the third piece of **DIR(0)** is executed after an entry is selected from the file.



**CAUTION:** KILL the DIR variable *after* the ^DIR call, so that other VA FileMan APIs that also use the ^DIR reader are *not* affected.

### 2.3.46.3 Optional Input Variables (Full Listing)

**DA:** (Optional) For DD-type reads only, if **DIR("B")** is *not* set, you can retrieve a value from the database to display as a default. Identify the entry from which the value should come by setting the **DA** variable to its record number. If a subfile is involved, set up a **DA()** array where:

- **DA**—Equals the record number for the lowest level subfile.
- **DA(1)**—Equals the record number for the next higher, and so on.



**NOTE:** Although you can retrieve defaults from the database by using **DA**, the values in the database are *not* changed by ^DIR calls.

**DIR("A"):** (Optional) The reader provides a generic default prompt for each type (e.g., enter a number or enter a response). To issue a more meaningful prompt, **DIR("A")** can be set to a character string that more clearly indicates the nature of the data being requested. For example, setting the following:

```
S DIR("A")="PRICE PER DISPENSE UNIT: "
S DIR(0)="NA^0:5:2"
```

Causes the prompt to appear as:

```
PRICE PER DISPENSE UNIT:
```

**DIR("A",#):** (Optional) If you want to issue a longer message before actually reading the input, you can set the **DIR("A",#)** array in addition to **DIR("A")**. The #'s *must* be numeric. After the array has been displayed, **DIR("A")** is issued as the prompt for the read. It is necessary for **DIR("A")** to be set if the developer is to use this array. For example, setting the following:

```
S DIR("A")="PRICE PER DISPENSE UNIT:"
S DIR("A",1)="Enter price data with two decimal points."
S DIR("A",2)="Cost calculations require this precision."
```

Causes the following dialogue to appear to the user:

```
Enter price data with two decimal points.
Cost calculations require this precision.
PRICE PER DISPENSE UNIT:
```

**DIR("B"):** (Optional) Set this variable to the default response for the prompt issued. It appears after the prompt and before the // (double slashes). If the user simply presses **Enter**, the default response is accepted by the reader.

**DIR("L") DIR("L",#):** (Optional) Only applies to set-of-codes fields. It allows you to replace the standard vertical listing of codes that the Reader displays with your own listing. It is up to you to ensure that the contents of the **DIR("L")** array match the codes in the second ^-piece of **DIR(0)**.

The format of the **DIR("L")** array is similar to **DIR("A")** and **DIR("?")**. The #'s *must* be numeric starting from 1. The numeric subscripted array nodes are written first and the **DIR("L")** node is written last. For example, if you code:

```
S DIR(0)="SO^1:ONE;2:TWO;3:THREE;4:FOUR;5:FIVE"
S DIR("L",1)="Select one of the following:"
S DIR("L",2)=""
S DIR("L",3)=" 1 ONE          4 FOUR"
S DIR("L",4)=" 2 TWO          5 FIVE"
S DIR("L")=" 3 THREE"
D ^DIR
```

The user sees the following:

```
Select one of the following:

1 ONE          4 FOUR
2 TWO          5 FIVE
3 THREE

Enter response:
```

**DIR("PRE"):** (Optional) This variable contains M code that acts as a pre-validation transform. It can either change **X**, in which case the reader proceeds as though the user had entered the new value in **X**, or **KILL X**, in which case the reader behaves as though the user entered an illegal value. **DIR("PRE")** is executed almost immediately after the READ takes place, just after **DTOUT** is set if the READ timed out, and before any other checking is done. The only inputs and outputs are **X** and **DTOUT**.

In order for ^DIR to respond properly when the user does the following:

- Times out.
- Inputs ^.
- Inputs ?.

The M code should:

- Check for **DTOUT** being defined.
- **X** containing ^.
- **X** containing ?.

In each of these cases return **X** unchanged.

DIR("S"):

(Optional) Use the **DIR("S")** variable to screen the allowable responses for pointer, set of codes, and list/range reads. This variable works as the **DIC("S")** variable does for ^DIC calls. Set **DIR("S")** equal to M code containing an **IF** statement. After execution, if **\$T** is set to:

- **1**—User response is accepted.
- **0**—User response is *not* accepted.

For pointer reads, when **DIR("S")** is executed:

- The M **Naked Indicator** is equal to the **0** node of the entry being screened.
- The variable **Y** equals its record number.

For set of codes reads, when the **DIR("S")** is executed, **Y** equals the internal code.

For list/range reads, if you also use the **C** flag in piece **1** of **DIR(0)**, your output is still compressed. Internally during the call, however, the range *must* be uncompressed, so that each number in the range can be screened. So, using **DIR("S")** with the **C** flag during list/range reads loses the **C** flag's advantages in speed (but the **C** flag's advantage in avoiding storage overflows remains).

DIR("T"):

(Optional) Time-out value to be used in place of **DTIME**. Value is represented in seconds.

DIR("?")

(Optional) This variable contains a simple help prompt, which is displayed to the user when one question mark is entered. It usually takes the place of the reader's default prompt. For example, if you code:

```
S DIR(0)="F^3:10"  
S DIR("?")="Enter from three to ten characters"  
S DIR("A")="NICKNAME"  
D ^DIR
```

The user sees the following:

```
NICKNAME: ?  
Enter from three to ten characters.
```



**NOTE:** When displayed, a period (.) is added to the **DIR("?")** string; however, periods are *not* appended when displaying the **DIR("?",#)** array.

When one question mark is entered in DD reads, the data dictionary's help prompt is shown before **DIR("??")**. For pointer reads, a list of choices from the pointed-to file is shown in addition to **DIR("??")**.

As an alternative, you can set **DIR("??")** to a caret (^) followed by M code, which is executed when the user enters one question mark. An example might be:

```
S DIR(" ? ") = "^D HELP^%DTC"
```

Execution of this M code overrides the reader's default prompt. If **DIR("??")** is defined in this way (a *non-null* second piece), the **DIR("??",#)** array is *not* displayed.

**DIR("??",#)**

(Optional) This array allows the user to display more than one line of help when the user types a single question mark:

- The first caret (^) piece of **DIR("??")** *must* be set for the array to be used.
- The second caret piece of **DIR("??")** *must* be null; otherwise, the **DIR("??",#)** array is ignored.
- The #'s *must* be numeric starting from 1.
- The numbered lines are written first [i.e., first **DIR("??",1)**, and then **DIR("??",2)**, etc.].
- The last help line written is **DIR("??")**.

These lines are the only ones written, which means that the reader's default prompt is *not* issued.

**DIR("???"):**

(Optional) This variable, if defined, is a two-part variable:

- The first caret (^) piece can contain the name of a help frame. The help processor displays this help frame if the user enters two question marks (??).
- The second part of this variable (after the first caret piece) can contain M code that is executed after the help frame is displayed.

For example:

```
S DIR(" ??? ") = "DIHELPXX^D EN^XXX"
```



**NOTE:** In order to use this variable, you *must* have Kernel's help processor on your system.

### 2.3.46.4 Output Variables (Full Listing)

**X:** This is the unprocessed response entered by the user. It is always returned. If the user accepts the default in **DIR("B")**, it is the default. If the user enters a caret (^) or just presses **Enter** on an optional input, **X** is the caret or null.

**Y:** **Y** is always defined as the processed output. The values returned are listed in [Table 32](#):

**Table 32: ^DIR: Reader Output Variables (Full Listing)—Y Processed Output**

Type	Y Returned As
<b>Date</b>	The date/time in VA FileMan internal format.
<b>End-of-page</b>	<ul style="list-style-type: none"> <li>• <b>Y=1</b> for continue (user pressed <b>Enter</b>).</li> <li>• <b>Y=0</b> for exit (the user entered a caret [^]).</li> <li>• <b>Y=""</b> for time out (the user timed out).</li> </ul>
<b>Free-text</b>	The data typed in by the user. In this case, it is the same as <b>X</b> .
<b>List or Range</b>	<p>The list of numeric values, delimited by commas and ending with a comma.</p> <p>If the <b>C</b> flag was <i>not</i> included in the first piece of <b>DIR(0)</b>, an expanded list of numbers, including each individual number in a range, is returned. If the <b>C</b> flag was included, a compressed list that uses the hyphen syntax to indicate a range of numbers is returned.</p> <p>Any leading zeroes or trailing zeroes following the decimal point are removed (i.e., only canonic numbers are returned). If the list of returned numbers has more than <b>245</b> characters, integer-subscripted elements of <b>Y</b> [Y(1), Y(2), etc.] contain the additional numbers. <b>Y(0)</b> is <i>always</i> returned equal to <b>Y</b>.</p>
<b>Numeric</b>	The canonic value of the number entered by the user (i.e., leading zeroes are deleted and trailing zeroes after the decimal are deleted).
<b>Pointer</b>	The normal value of <b>Y</b> from a DIC lookup (i.e., Internal Entry Number^Entry Name). If the lookup was unsuccessful, <b>Y=-1</b> .
<b>Set of Codes</b>	The internal value of the response.
<b>Yes/No</b>	<ul style="list-style-type: none"> <li>• <b>Y=1</b> for yes.</li> <li>• <b>Y=0</b> for no.</li> </ul>
<b>DD (#,#)</b>	The first ^-piece of <b>Y</b> contains the result of the variable <b>X</b> after it has been passed through the INPUT transform of the field specified. Depending on the data type involved, subsequent ^-pieces can contain additional information.

[Table 33](#) summarizes the values of **Y** upon timeout, entering a caret (^), or pressing the **Enter** key for all READs. Exceptions are noted.

**Table 33: ^DIR: Reader Output Variables (Full Listing)—Y Values upon Timeout**

Condition	Value of Y	Comments
Timeout	Y=""	--
Caret (^)	Y=^	In all cases except end-of-page reads.
Y=0	Upon end-of-page reads.	--
Double Caret ("^^")	Y=^^	In all cases except end-of-page reads.
Return	Y=""	For optional reads (reads allowing a null response).
	Y=-1	For pointer reads.
	Y=0	For YES/NO type when <b>NO</b> is the default.
	Y=1	For YES/NO type when <b>YES</b> is the default.
	Y=1	For end-of-page reads.
	Y=default	When a default is provided other than for YES/NO type questions.

Y(0):

This is defined for the set of codes, list, pointer, date, and Yes/No reads. It is also returned for DD reads when the DATA TYPE field value is a:

- SET OF CODES
- POINTER
- VARIABLE POINTER
- DATE/TIME

It holds the external value of the response for set of codes or Yes/No, the zero node of the entry selected for a POINTER, and the external date for a DATE/TIME and VARIABLE POINTER. To have **Y(0)** returned for pointer-types, the **DIC(0)** string in the second piece of **DIR(0)** *must* contain a **Z**. For example:

DIR(0) = "P^19:EMZ"
---------------------

For list reads, it contains the same values as the **Y** variable. There can be additional nodes in the **Y()** array depending on the size of the list selected by the user.

DTOUT:

**DTOUT** is defined if the read has timed-out.



DUOUT: **DUOUT** is defined if the user entered a leading caret (^).

DIRUT: **DIRUT** is defined if the user:

- Enters a leading caret (^).
- Times out.
- Enters a null response. A null response results from pressing **Enter** at a prompt with no default or entering the at-sign (@), signifying deletion.

If, however, the user presses **Enter** in response to an end of page read, **DIRUT** is *not* defined.

If **DIRUT** is defined, the user can enter the following common check to quit after a reader call:

```
Q: $D(DIRUT)
```

DIROUT: If the user entered two carets (^ ^), **DIROUT** is defined.



**CAUTION:** KILL the DIR variable *after* the ^DIR call, so that other VA FileMan APIs that also use the ^DIR reader are *not* affected.

### 2.3.46.5 Examples

1. [Date Example](#)
2. [End-of-Page Example](#)
3. [Free-Text Example](#)
4. [List or Range Example](#)
5. [Numeric Example](#)
6. [Pointer Example](#)
7. [Set Example](#)
8. [Yes/No Example](#)
9. [DD Example](#)

#### 2.3.46.5.1 Date Example

Figure 48: ^DIR API—Date Example

```
S DIR(0) = "D^2880101:2880331:EX"
```

This tells the reader that the input *must* be an acceptable date. To determine that, ^%DT is invoked with the %DT variable equal to **EX**. If the date is a legitimate date, then it is checked to see if the date falls between January 1, 1988 and March 31, 1988. In general, both minimum and maximum are optional. If they are there, they *must* be in VA FileMan internal format. The only exceptions are that **NOW** and **DT** can be used to reference the current date/time. Remember that **NOW** contains a time stamp. If it is used as a minimum or maximum value, an **R** or **T** should be put into the %DT variable. If **DIR(0)** is set up to expect a time in the response, you can help the user by including that requirement in the prompt. Otherwise, a response without a time stamp (e.g., **TODAY**) might unexpectedly fail.

### 2.3.46.5.2 End-of-Page Example

Figure 49: ^DIR API—End-of-Page Example: Input

```
S DIR(0)="E"
```

There are no parameters. The **Enter** and caret (^) keys are the only acceptable responses. This **DIR(0)** setting causes the following prompt to be issued:

Figure 50: ^DIR API—End-of-Page Example: Prompt Displayed

```
Press the return key to continue or '^' to exit:
```

### 2.3.46.5.3 Free-Text Example

Figure 51: ^DIR API—Free-Text Example: Input

```
S DIR(0)="F^3:30"
```

This tells the reader that the input *must* be alphanumeric or punctuation, (control characters are *not* allowed), and that the length of input *must* be no fewer than 3 and no more than 30 characters. The maximum acceptable length for a free-text field is **245** characters.



**NOTE:** A leading caret (^) always aborts the READ and SETs **DIRUT** or **DUOUT**.

#### 2.3.46.5.3.1 With DIR(0) Containing U

Figure 52: ^DIR API—With DIR(0) Containing U Example: Input

```
S DIR(0)="FU^3:30"
```

The user can enter any response that is from 3 to 30 characters long. The response can contain embedded carets (^). Without **U**, an embedded caret causes the user to receive an error message.

#### 2.3.46.5.3.2 With DIR(0) Containing A

Figure 53: ^DIR API—With DIR(0) Containing A Example: Input

```
S DIR(0)="FA^2:5",DIR("A")="INITIAL"
```

The prompt is set only to the word **INITIAL**. If the **A** were *not* included, a colon and space would be appended to the prompt and it would look like this:

Figure 54: ^DIR API—With DIR(0) Containing A Example: Prompt Displayed

```
INITIAL:
```

### 2.3.46.5.4 List or Range Example

Figure 55: ^DIR API—List or Range Example: Input

```
S DIR(0)="L^1:25"
```

This tells the reader that the input can be any set of numbers between 1 and 25. The numbers can be separated by commas, dashes, or a combination of both. Two acceptable responses to the example in [Figure 55](#) are shown in [Figure 56](#):

**Figure 56: ^DIR API—List or Range Example: Acceptable Responses**

```
1, 2, 20
4-8, 16, 22-25
```

Remember that this is a numeric range or list. It can only contain *positive* integers and zero (no negative numbers).

#### 2.3.46.5.4.1 With DIR(0) Containing C

**Figure 57: ^DIR API—With DIR(0) Containing C Example: Input and Output**

```
>S DIR(0)="LC^1:100:2" D ^DIR
Enter a list or range of numbers (1-100): 5,8.01,9-40,
7.03,45.9,80-100
>ZW Y
Y=5,7.03,8.01,9-40,45.9,80-100,
Y(0)=5,7.03,8.01,9-40,45.9,80-100,
```

In [Figure 57](#) the user can enter numbers from 1 to 100 with up to two decimal places. The **C** flag tells the reader *not* to return each individual number in **Y**. Instead, inclusive ranges of numbers are returned. In this case, without the **C** flag, 137 subscripted nodes of the **Y()** array would be returned; the call would be very slow and might cause an error if the size of the **Y()** array exceeded local storage.

#### 2.3.46.5.5 Numeric Example

**Figure 58: ^DIR API—Numeric Example: Input**

```
>S DIR(0)="N^20:30:3"
```

This tells the reader that the input *must* be a number between 20 and 30 with no more than three decimal digits.



**NOTE:** If no maximum is specified in the second ^-piece, the default maximum is 99999999999.

#### 2.3.46.5.5.1 With DIR(0) Containing O

**Figure 59: ^DIR API—With DIR(0) Containing O Example: Input**

```
S DIR(0)="NO^0:120",DIR("A")="AGE"
```

This allows the user to press **Enter** *without* entering any response and leave the reader. Without the **O**, the following messages appear:

**Figure 60: ^DIR: Reader—With DIR(0) Containing O Example: Prompt Displayed**

```
This is a required response. Enter ^^ to exit.
```

### 2.3.46.5.6 Pointer Example

Figure 61: ^DIR API—Pointer Example: Input

```
S DIR(0)="P^19:EMZ"
```

This tells the reader to do a lookup on File #19, setting **DIC(0)**="EMZ" before making the call.

If the user enters a response that causes the lookup to fail, the user is prompted again for a lookup value.

A pointer read can be used to look up in a subfile. In that case, the global root *must* be used in place of the file number. For example, to look up in the menu subfile (stored descendent from subscript 10) for entry #2 in File #19:

Figure 62: ^DIR API—Pointer Example: Subfile Lookup

```
S DIR(0)="P^DIC(19,2,10,:QEM"
```

Remember to set any necessary variables [e.g., **DA(1)**].

### 2.3.46.5.7 Set Example

Figure 63: ^DIR API—Set Example: Input

```
S DIR(0)="S^1:MARRIED;2:SINGLE"
```

This tells the reader to only accept one of the two members of the set. The response can be 1, 2, MARRIED, or SINGLE. When **DIR("A")** is included without the **A** modifier on the first piece, the prompting is done as follows:

Figure 64: ^DIR API—Set Example: Input and Prompt Displayed

```
>S DIR(0)="S^M:MALE;F:FEMALE"
>S DIR("A")="SEX" D ^DIR

Select one of the following:
      M      MALE
      F      FEMALE
SEX:
```

#### 2.3.46.5.7.1 With DIR(0) Containing A

Figure 65: ^DIR API—With DIR(0) Containing A Example: Input

```
S DIR(0)="SA^M:MALE;F:FEMALE"
S DIR("A")="SEX: " D ^DIR
```

Whereas, with the **A**, it would appear as follows:

Figure 66: ^DIR API—With DIR(0) Containing A Example: Prompt Displayed

```
SEX:
```

### 2.3.46.5.7.2 With DIR(0) Containing B

Figure 67: ^DIR API—With DIR(0) Containing B Example: Input

```
S DIR(0)="SB^M:MALE;F:FEMALE"  
S DIR("A")="SEX" D ^DIR
```

When this is executed, instead of getting the vertical listing as shown in [Figure 64](#), the prompt would appear as shown in [Figure 68](#):

Figure 68: ^DIR API—With DIR(0) Containing B Example: Prompt Displayed

```
SEX: (M/F):
```

### 2.3.46.5.7.3 With DIR(0) Containing X

Figure 69: ^DIR API—With DIR(0) Containing X Example: Input

```
S DIR(0)="SX^M:MALE;F:FEMALE"  
S DIR("A")="SEX"
```

This would cause a lowercase **M** or **F** to be rejected. The prompting is done as follows:

Figure 70: ^DIR API—With DIR(0) Containing X Example: Prompt Displayed

```
Select one of the following:  
M Male  
F Female  
SEX: F <Enter>  
Enter a code from the list.
```

### 2.3.46.5.8 Yes/No Example

Figure 71: ^DIR API—Yes/No Example: Input

```
S DIR(0)="Y",DIR("B")="YES"
```

This tells the reader that the response can only be **Yes** or **No**. When using **DIR("B")** to provide a default response, spell out the entire word; so that when the user presses **Enter** to accept the default, echoing functions properly.

### 2.3.46.5.9 DD Example

Figure 72: ^DIR API—DD Example: Input Format 1

```
S DIR(0)="19,1"
```

This format is different from the others in that the:

- First number is a file number.
- Second number is a field number in that file.

The reader uses the data dictionary for Field #1 in File #19 and issues the label of that field as the prompt. The input is passed through the INPUT transform in the dictionary. Help messages are also the ones contained in the dictionary for this field.

Normally, DD reads based on a free text field do *not* allow embedded carets (^). However, if the field specified is positioned on the data node using the **Em,n** format (instead of the ^-piece format), carets embedded in the user’s response are accepted.



**REF:** For an explanation of locating fields on the data node, see the “[Field Global Storage](#)” section in the “[Advanced File Definition](#)” section.

Initial carets abort the READ and SET the **DIRUT** and **DUOUT** variables.

It is *not* possible to use this format if the field defines a subfile (i.e., the second piece of the zero node of the field definition contains a subfile number). To use the reader for a field in a subfile, do the following:

**Figure 73: ^DIR API—DD Example: Input Format 2**

```
S DIR(0)="Subfile#,field#"
```

It is the developer’s responsibility to set any variables necessary for the INPUT transform to execute correctly.

Always **NEW** or **KILL DA** before doing a DD-type DIR call, unless you wish to use the default feature. The default feature allows you to retrieve default values from the database for DD reads by setting **DA** (or the **DA** array for subfiles) equal to the record number containing the desired default value.

### 2.3.47 EN^DIS: Searches File Entries

You can call the Search File Entries option [DISEARCH] of VA FileMan for a given file when you want the user to be able to specify the search criteria. This is done by invoking the EN^DIS API. In addition to **DT** and **DUZ**, the API needs the **DIC** input variable.

#### Input Variable

**DIC:** (Required) The global root of the file in any of the following forms:

- ^GLOBAL(
- ^GLOBAL(#
- Number of the file

If the search is allowed to run to completion, and if the search criteria have been stored in a template, then a list of the record numbers that meet the search criteria is stored in that same template.



**NOTE:** The same global array is used to store a list of record numbers saved in VA FileMan Inquire mode.

**Figure 74: EN^DIS API—Sort Template**

```
^DIBT(SORT_TEMPLATE#,1,IEN)=""
```

The **1** node indicates that the IEN list was created one of two ways:

- **INQUIRE**—User was in VA FileMan INQUIRE mode, selected a number of records, and saved the list in a template.
- **SEARCH**—User ran the VA FileMan SEARCH, either through the interactive VA FileMan menu or through the EN^DIS API. In this case, the IEN list is the group of record numbers that met the search criteria.

IEN is the internal entry number of a record in the file indicated by the fourth piece of the zero node of the template:

```
^DIBT(SORT_TEMPLATE#,0)
```

The list of record numbers stored in the template can be used as input to the print routine, [EN1^DIP](#), to create further reports.

## 2.3.48 EN^DIU2: Delete Data Dictionary

Use the EN^DIU2 API to delete a file's data dictionary and its entry in [^DIC](#) in order to properly update a running system.

You usually have the option of deleting the data when you delete the data dictionary [see the [DIU\(0\)](#) variable]. However, data is always deleted if your file is in [^DIC\(File#](#),



**CAUTION:** Be careful using this utility when your data is in the ^DIC global.

In all cases, both **DIU** and **DIU(0)** are returned from the call. You find that **DIU** is returned as the global root regardless of whether it was defined as the file number or as the global root when making the call.



**NOTE:** If the root of a file's data is an unsubscribed global [e.g., **DIU**=`^MYDATA(`), you *must* make sure that the systems on which you want to perform the deletion do *not* restrict the KILLing of the affected unsubscribed globals.



**CAUTION:** It is your responsibility to clean up (KILL) DIU, the input variable, after any call to this routine!

### Input Variables

**DIU:** (Required) The file number or global root [e.g., `^DIZ(16000.1,)`]. This *must* be a subfile number when deleting a subfile's data dictionary.

**DIU(0):** Input parameter string that can contain the following:

- **D**—Delete the data as well as the data dictionary.
- **E**—Echo back information during deletion.
- **S**—Subfile data dictionary is to be deleted.
- **T**—Templates are to be deleted.

### 2.3.48.1 Example

Figure 75: EN^DIU2 API—Example: Input

```
S DIU=^^DIZ(16000.1,"",DIU(0)=" D EN^DIU2
```

Only the data dictionary is deleted. The data and templates remain. By including either the **D** or **T**, you can also delete the data or the templates. If the **E** is included, then the user is asked whether or *not* the global should be deleted.

### 2.3.48.1.1 Subfile Deletion

If you want to delete the dictionary for a subfile, you *must* include the **S** in **DIU(0)**. The **DIU** variable, in this case, *must* be a subfile data dictionary number. It *cannot* be a global root. When deleting a subfile's dictionary, all dictionaries subordinate to that dictionary are also deleted. Data can also be deleted when deleting a subfile; this process could take some time depending on the number of entries in the whole file.

### 2.3.48.1.2 Example

Figure 76: EN^DIU2 API—Example: Input for Subfile Deletion

```
S DIU=16000.01,DIU(0)="S" D EN^DIU2
```

## 2.3.49 EN^DIWE: Text Editing

Use the EN^DIWE API to edit word-processing text using VA FileMan's editors. If the user has established a Preferred Editor through Kernel, that editor is presented for use. VA FileMan's editors expect the text to contain only printable ASCII characters.

### Input Variables

**DDWAUTO:** (Optional) This variable can be set to an interval in minutes that the Screen Editor should automatically save the text for the user. It can be an integer between **1** and **120**. If set to **0**, no autosave occurs. The setting takes effect for only the current invocation of the Screen Editor and can be changed by the user via the <PF1><PF1>**S** key sequence.

The default value of **DDWAUTO** is **0**.

This variable is **KILLED** by VA FileMan.

**DDWTAB:** (Optional) This variable indicates to the Screen Editor the initial tab stop positions. The setting takes effect for only the current invocation of the Screen Editor and can subsequently be changed by the user via the <PF1><PF1><Tab> key sequence.

To set individual tab stops, set **DDWTAB** to a series of numbers separated by commas. For example:

```
DDWTAB = "4,7,15,20"
```

Sets tab stops at columns 4, 7, 15, and 20. To set tab stops at repeated intervals after the last stop, or after column **1**, type the interval as **+n**. For example:

```
DDWTAB = "10,20,+5"
```

Sets tab stops at columns 10, 20, 25, 30, 35, etc.

If *not* passed, the Screen Editor assumes **DDWTAB** = **" +8"** (i.e., it initially sets tab stops at columns **1, 9, 17, 25**, etc.).

This variable is **KILLED** by VA FileMan.

**DIC:** (Required) The global root of where the text is located.





**NOTE:** VA FileMan uses ^UTILITY(\$J,"W") when EN^DIWE is called. Thus, **DIC** should *not* be set equal to that global location.

**DWLW:** (Optional) This variable indicates the maximum number of characters that are stored on a word-processing global node. When the user enters text, the input line is *not* broken to **DWLW**-characters until after the **Enter** key is pressed. Thus, if **DWLW**=40 and the user types 90 characters before pressing the **Enter** key, the text would be stored in three lines in the global.

If this variable is *not* set, the default value is **245**.

This variable is always KILLED by VA FileMan.

**DWPK:** (Optional) This variable determines how lines that are shorter than the maximum line length (set by **DWLW**) are treated by VA FileMan. It can be set to **1** or **2**.

This variable is always KILLED by VA FileMan.

Possible values for DWPK:

- **DWPK=1**—If the user enters lines shorter than the maximum line length in variable **DWLW**, the lines are stored as is; they are *not* joined. If lines longer than **DWLW** are entered, the lines are broken at word boundaries.
- **DWPK=2**—If the user types lines shorter than the maximum line length in variable **DWLW**, the lines are joined until they get to the maximum length; the lines are “filled” to **DWLW** in length. If the lines are longer than **DWLW**, they are broken at word boundaries. This is the default used if **DWPK** is *not* set prior to the EN^DIWE call.



**NOTE:** **DWLW** and **DWPK** only have an effect if text is entered using the Line Editor. They do *not* affect how text is stored if the Screen Editor or some other alternate editor is used.

**DWDISABL:** (Optional) This variable can be used to disable specific Line Editor commands. For example, if **DWDISABL** contains **P**, then the Print command in the Line Editor is disabled.

This variable is KILLED by VA FileMan.

**DIWEPSE:** (Optional) If this variable is defined before entering the Preferred Editor (if the Preferred Editor is *not* the Line Editor), the user receives the following prompt:

```
Press RETURN to continue or '^' to exit:
```

Set this variable if you want to allow the user to read information on the screen before the display is cleared by a screen-oriented editor.

This variable is always KILLED by VA FileMan.

**DIWESUB:** (Optional) The first **30** characters of this variable are displayed within angle brackets (< and >) on the top border of the Screen Editor screen.

This variable is KILLED by VA FileMan.

- DIWETXT:** (Optional) **DIWETXT** is a string and the characters from position **1** through the **RIGHT MARGIN (IOM, usually 80 or 132)** are displayed in high intensity on the first line of the Screen Editor screen.
- This variable is **KILLED** by VA FileMan.
- DDWLMAR:** (Optional) This variable indicates the initial column position of the left margin when the Screen Editor is invoked. The user can subsequently change the location of the left margin.
- This variable is **KILLED** by VA FileMan.
- DDWRMAR:** (Optional) This variable indicates the initial column position of the right margin when the Screen Editor is invoked. The user can subsequently change the location of the right margin.
- This variable is **KILLED** by VA FileMan.
- DDWRW:** (Optional) This variable indicates to the Screen Editor the line in the document on which the cursor should initially rest. This variable has effect only if the user's preferred editor is the Screen Editor and applies only when the Screen Editor is first invoked. If the user switches from the Screen Editor to another editor and then back to the Screen Editor, the cursor always rests initially on line **1**.
- If this variable is set to **B**, the cursor initially rests at the bottom of the document and the value of **DDWC** described immediately below is ignored.
- The default value of **DDWRW** is **1**.
- This variable is **KILLED** by VA FileMan.
- DDWC:** (Optional) This variable indicates to the Screen Editor the initial column position of the cursor. The same restrictions described above for **DDWRW** apply to **DDWC**.
- If this variable is set to **E**, the cursor initially rests at the end of the line defined by **DDWRW**.
- The default value of **DDWC** is **1**.
- This variable is **KILLED** by VA FileMan.
- DDWFLAGS:** (Optional) Flags to control the behavior of the Screen Editor. The possible values are:
- **M**—Indicates that the Screen Editor should initially be in **NO WRAP Mode** when invoked.
  - **Q**—Indicates that if the user attempts to **Quit** the editor with **<PF1>Q**, the confirmation message "Do you want to save changes?" is *not* asked.
  - **R**—Indicates that the Screen Editor should initially be in **REPLACE** mode when invoked.
- This variable is **KILLED** by VA FileMan.

## 2.3.50 ^DIWF: Form Document Print

### 2.3.50.1 Form Document Print Introduction (^DIWF)

The entry points in ^DIWF are designed to use the contents of a WORD-PROCESSING field as a target document into which data can be inserted at print time. The data can come from another VA FileMan file (i.e., “source” file) or be provided by the user interactively at the time the document is printed. A file containing a WORD-PROCESSING type field (i.e., “document” or “target” file) is first selected and then an entry from that file. The word-processing text in that entry is then used as a form with which to print output from any other file.

The word-processing text used typically includes windows into which data from the source file automatically gets inserted by DIWF. Word-processing windows are expressions framed by vertical bars (|). Thus, if a word-processing document contains [NAME] somewhere within it, DIWF tries to pick the NAME field (if there is one) out of the source file. Any *non*-Multiple field label or computed expression can be used within a |-window, if both of the following are true:

- An expression within the |-window *cannot* be evaluated.
- The output of DIWF is being sent to a different terminal than the one used to call up the output.

Then, the user is asked to type in a value for the window, for each data entry printed. Thus, the word-processing text used as a target document might include the window |SALUTATION|, where SALUTATION is *not* a valid field name in the source file. When DIWF encounters this window, and failing to find a SALUTATION field in the source file, it asks the user to enter SALUTATION text, which then immediately gets incorporated into the output in place of that window.



**NOTE:** If there is a possibility that the output is to be queued, you *must* ensure that *all* windows can be evaluated, since in a queued or tasked job, there can be no user interaction.

Invoking DIWF at the top (i.e., **D ^DIWF**) results in an interactive dialogue with the user.

#### 2.3.50.1.1 Example

Suppose you had a (fictitious) FORM LETTER (#16001) file, and data is stored in the ^DIZ(16001, global. This (fictitious) file has a WORD-PROCESSING type field where the text of a form letter is stored. In this file, as shown in [Figure 77](#), there are several form letter entries, one of which is the (fictitious) APPOINTMENT REMINDER field:

**Figure 77: ^DIWF API—Example: Word-Processing Type Field**

```
Select Document File: FORM LETTER
Select DOCUMENT: APPOINTMENT REMINDER
Print from what FILE: EMPLOYEE
WANT EACH ENTRY ON A SEPARATE PAGE? YES// <Enter>
SORT BY: NAME// FOLLOWUP DATE=MAY 1, 1999
DEVICE:
```

In this example ([Figure 77](#)), the word-processing text found in the (fictitious) APPOINTMENT REMINDER field entry of the (fictitious) FORM LETTER file is used to print a sheet of output for each (fictitious) EMPLOYEE file entry where the (fictitious) FOLLOWUP DATE field equals May 1, 1999.

If the document file contains a pointer field pointing to File #1, and if the document entry selected has a value for that pointer, then the file pointed to is automatically used to print from and the user is *not* asked “Print from what FILE:”.



**NOTE:** The Read access is checked by DIWF for both files selected.



**NOTE:** If there is a possibility that the output is to be queued, you *must* ensure that *all* windows can be evaluated, since in a queued or tasked job, there can be no user interaction.

## 2.3.51 EN1^DIWF: Form Document Print with Known Document

### 2.3.51.1 Form Document Print Introduction (^DIWF)



**REF:** For a complete description, see the “[Form Document Print Introduction \(^DIWF\)](#)” section.

The EN1^DIWF API is used when the calling program knows which file (document file) contains the desired word-processing text to be used as a target document.

#### Input Variable

**DIC:** A file number or a global root. The file identified *must* contain a WORD-PROCESSING field.

#### Output Variable

**Y:** This is **-1** only if the file sent to DIWF in the variable **DIC** does *not* contain a WORD-PROCESSING field.

#### 2.3.51.1.1 Example

**Figure 78: EN1^DIWF API—Example: Input**

```
>S DIC=16001 D EN1^DIWF
```

The user is then branched to the “Select DOCUMENT:” prompt in the dialogue described in [^DIWF](#) to select a particular entry in the (fictitious) FORM LETTER file.

## 2.3.52 EN2^DIWF: Form Document Print with Known Document and Entry

### 2.3.52.1 Form Document Print Introduction (^DIWF)



**REF:** For a complete description, see the “[Form Document Print Introduction \(^DIWF\)](#)” section.

The EN2^DIWF API is used when the calling program knows both the document file and the entry within that file, which contains the desired word-processing text to be used as a target document.

#### Input Variables

**DIWF:** The global root at which the desired text is stored. Thus, in the example, if (fictitious) APPOINTMENT REMINDER is the third document in the (fictitious) FORM LETTER file (stored in ^DIZ(16001,) and the WORD-PROCESSING field is stored in subscript 1, you can:

```
>S DIWF="^DIZ(16001,3,1,"
```

DIWF then *automatically* uses this entry and the user is *not* asked to select the document file and which document in that file.

**DIWF(1):** If the calling program wants to specify which file should be used as a source for generating output, the number of that file should appear in the **DIWF(1)** variable. Otherwise, the user is asked the “Print from what FILE:” question.

After this point, [EN1^DIP](#) is invoked. You can have the calling program set the usual **BY**, **FR**, and **TO** variables if you want to control the SORT sequence of the data file.

#### Output Variable

**Y:** **Y** is -1 if:

- There is no data beneath the root passed in **DIWF**.
- The file passed in **DIWF(1)** could *not* be found.

## 2.3.53 ^DIWP: Formats and Outputs Text Lines

Call the ^DIWP API to format and (optionally) output any group of text lines.

Before calling ^DIWP, **KILL** the ^UTILITY(\$J,“W”) global.

^DIWP works in **two modes** (based on whether the **DIWF** input variable contains **W** or not):

- **Accumulate Mode**—In ^DIWP’s “**accumulate**” mode, repeated calls to ^DIWP accumulate and format text in ^UTILITY(\$J,“W”). After you have finished accumulating text, call the [^DIWW](#) API to write the text to the current device using the margins specified in the calls to ^DIWP. It then removes the text from ^UTILITY.
- **Write Mode**—In ^DIWP’s “**write**” mode, if the text added to ^UTILITY(\$J,“W”) by ^DIWP causes one or more (i.e., *n*) line breaks, *n* lines are written to the current device (and the remaining partial line is stored in ^UTILITY). This leaves one line of text in ^UTILITY once all calls to ^DIWP are completed. To write the remaining line of text to the current device and remove it from ^UTILITY, call the [^DIWW](#) API.

## Input Variables

**X:** (Required) The string of text to be added as input to the formatter.

The **X** input string can contain |-windows (e.g., |SETTAB(9,23,44)|).



**REF:** For more information on |-windows, see the “Formatting Text with Word-processing Windows” section in the “Advanced Edit Techniques” section in the *VA FileMan Advanced User Manual*.

The expressions within the windows are processed as long as they are *not* context-dependent (i.e., as long as they do *not* refer symbolically to database field names). Thus, |**TODAY**| causes today’s date to be inserted into the formatted text, but |**SSN**| is printed out as it stands, because it *cannot* be interpreted in context.

**DIWL:** (Required) The (integer-valued) left margin for the text. Set this to a positive number, **1** or greater. Do *not* change the value of **DIWL** if you are making repeated calls to ^DIWP to format text.

**DIWR:** (Required) The (integer-valued) right margin for the text.

**DIWF:** (Required) A string of format control parameters. If contained in **DIWF**, the parameters have the following effects:

- **W**—If the **DIWF** variable contains **W**, ^DIWP operates in “**write**” mode. If the **DIWF** variable does *not* contain **W**, ^DIWP operates in “**accumulate**” mode. See above for the discussion of these [two modes](#).

When making repeated calls to ^DIWP, do *not* mix modes. Use “**write**” or “**accumulate**” mode, but do *not* switch between them.

- **Cn**—The text is formatted in a Column width of **n**; thus, overriding the value of **DIWR**.
- **D**—The text is in **Double-spaced** format.
- **In**—The text is **Indented n** columns in from the left margin (**DIWL**).
- **N**—Each line is printed as it appears in the text (**No-wrap**). If **DIWF** contains **N**, the value of **DIWR** is ignored.



**REF:** For details about word wrapping, see the “Advanced Edit Techniques” section in the *VA FileMan Advanced User Manual*.

- **R**—The text is in **Right-justified** format.
- **X**—Word-processing text that contains the vertical bar character “|” is displayed exactly as they are stored, (i.e., no window processing takes place).

Patch DI\*22\*152 added the | character to the list of optional characters to use in the **DIWF** input variable. The | character means that any | in the text should be printed as-is, but word-wrap should still function, and margins respected.

## Output

`^UTILITY($J,“W”)` Formatted output text.

### 2.3.54 `^DIWW`: Output Remaining Text in `^UTILITY($J,“W”)` by `^DIWP`

Use the `^DIWW` API to output to the current device the remaining text left in `^UTILITY($J,“W”)` by [^DIWP](#).

The `^DIWW` API is designed to be used in conjunction with the [^DIWP](#) API. Using [^DIWP](#), you can accumulate and format text in `^UTILITY($J,“W”)`, in one of **two modes**:

- **Accumulate Mode**—In [^DIWP](#)'s “**accumulate**” mode, repeated calls to [^DIWP](#) accumulate and format text in `^UTILITY($J,“W”)`. After you have finished accumulating text, call the `^DIWW` API to write the text to the current device using the margins specified in the calls to [^DIWP](#). It then removes the text from `^UTILITY`.
- **Write Mode**—In [^DIWP](#)'s “**write**” mode, if the text added to `^UTILITY($J,“W”)` by [^DIWP](#) causes one or more (i.e., *n*) line breaks, *n* lines are written to the current device (and the remaining partial line is stored in `^UTILITY`. This leaves one line of text in `^UTILITY` once all calls to [^DIWP](#) are completed. To write the remaining line of text to the current device and remove it from `^UTILITY`, call the `^DIWW` API.

### 2.3.55 `^%DT`: Validates Date/Time Input and Converts to Internal Format




**REF:** For an introduction to Date/Time formats, see the “[Introduction to Date/Time Formats: %DT](#)” section.

The `^%DT` API accepts input and validates the input as being a correct date and time.


#### Input Variables

`%DT`: (Required) A string of alphabetic characters that alter how `%DT` responds. Briefly stated, the acceptable characters are:

- **A**—Ask for date input.
- **E**—Echo the answer.
- **F**—Future dates are assumed.
- **I**—For **I**nternationalization, assume day number precedes month number in input.
- **M**—Only **M**onth and year input is allowed.
- **N**—Pure **N**umeric input is *not* allowed.
- **P**—**P**ast dates are assumed.
- **R**—**R**equires time input.
- **S**—**S**econds should be returned.
- **T**—**T**ime input is allowed but *not* required.
- **X**—**E**Xact input is required.


 **REF:** For an explanation of each character, see the “[%DT Input Variables in Detail](#)” section.

X: (Optional) If **%DT** does *not* contain an **A**, then the variable **X** *must* be defined as equal to the value to be processed.

 **REF:** For acceptable values for **X** and for the interpretation of those values, see “Date Fields” in the “Editing Specific Field Types” section in the *VA FileMan User Manual*.


**%DT(“A”):** (Optional) A prompt that is displayed prior to the reading of the input. Without this variable, the prompt “DATE:” is issued.

**%DT(“B”):** (Optional) The default answer to the “DATE:” prompt. It is your responsibility to ensure that **%DT(“B”)** contains a valid date/time.

 **REF:** Allowable date input formats are explained in the “Editing Specific Field Types” section in the *VA FileMan User Manual*.

**%DT(0):** (Optional) Prevents the input date value from being accepted if it is chronologically before or after a particular date:

- Set **%DT(0)** equal to a VA FileMan-format date [e.g., **%DT(0)=2690720**] to allow input only of dates greater than or equal to that date.
- Set it negative [e.g., **%DT(0)=-2831109.15**] to allow only dates less than or equal to that date/time.
- Set it to **NOW** to allow dates from the current (input) time forward.
- Set it to **-NOW** to allow dates up to the current time.

 **NOTE:** Be sure to **KILL** this variable after returning from [%DT](#).

## Output Variables

Y: [%DT](#) always returns the **Y** variable, which can be one of two values:

- **Y=-1**—The date/time was invalid.
- **Y=YYMMDD.HHMMSS**—The value determined by [%DT](#).

X: **X** is always returned. It contains either what was passed to [%DT](#) (in the case where **%DT** did *not* contain an **A**) or what the user entered.

DTOUT: This is only defined if [%DT](#) has timed-out waiting for input from the user.

### 2.3.55.1 %DT Input Variables in Detail

A: [%DT](#) Asks for input from the terminal. It continues to ask until it receives:

- Correct input.
- A null.



- A caret (^).

If **%DT** does *not* contain the character **A**, the input to **%DT** is assumed to be in the variable **X**.

**E:** The **External** format of the input is echoed back to the user after it has been entered. If the input was erroneous, two question marks and an audible sound (“beep”) are issued.

**F:** If a year is *not* entered ([Example 1](#)), or if a two-digit year is entered ([Example 2](#)), a date in the **Future** is assumed.

**EXCEPTION:** If a two-digit year is entered and those two digits equal the current year, the current year is assumed even if the date is in the past ([Example 3](#)).

Example	Current Date	User Input	Date Returned	Returned Without F
1	July 1, 2000	5/1	May 1, 2001	May 1, 2000
2	July 1, 2000	5/1/90	May 1, 2090	May 1, 1990
3	July 1, 2000	5/1/00	May 1, 2000	May 1, 2000



**REF:** For the behavior of **%DT** when neither the **F** nor **P** flag is used, see “[Y2K Changes](#).”

**I:** For **Internalization**, this flag makes **%DT** assume that in the input, the day number precedes the month number (i.e., **DD/MM/YYYY**). For example, input of 05/11/2000 is assumed to be November 5, 2000 (instead of May 11, 2000). Also, with this flag, the month *must* be input as a number. For example, November *must* be input as 11, *not* NOV. The output provides **DD MON YYYY**. For example:

```
>S %DT="AEIX" D ^%DT W Y
DATE: 10052015<Enter> (10 MAY 2015)3150510
```

**M:** Only **Month** and year input is allowed. Input with a specific day or time is rejected ([Example 1](#)). If only a month and two digits are entered, the two digits are interpreted as a year instead of a day ([Example 2](#)).

If the **M** flag is used with the **X** flag, a month *must* be specified; otherwise, the input can be just a year ([Example 3](#)).

**M Flag:**

Example	Date Input	Date Returned	Returned Without M
1	7-05-2005	invalid	July 5, 2005
2	7-05	July 2005	July 5, 2000*

\*Assuming the current year is 2000 and the **F** and **P** flags are *not* used.

**M Flag (with X Flag):**

Example	Date Input	Date Returned	Returned Without X
3	05 or 2005	invalid	2005

N: Ordinarily, a user can enter a date in a purely **N**umeric form (i.e., **MMDDYY**). However, if **%DT** contains an **N**, then this type of input is *not* allowed.

P: If a year is *not* entered ([Example 1](#)), or if a two-digit year is entered ([Example 2](#)), a date in the **P**ast is assumed.

**EXCEPTION:** If a two-digit year is entered and those two digits equal the current year, the current year is assumed even if the date is in the future ([Example 3](#)).

Example	Current Date	User Input	Date Returned	Returned Without P
1	March 1, 1995	6/1	June 1, 1994	June 1, 1995
2	March 1, 1995	6/1/98	June 1, 1898	June 1, 1998
3	March 1, 1995	6/1/95	June 1, 1995	June 1, 1995



**REF:** For the behavior of **%DT** when neither the **F** nor **P** flag is used, see [“Y2K Changes.”](#)

R: Time is **R**equired. It *must* be input.

S: Seconds are to be returned.

T: Time is allowed in the input, but it is *not* necessary.



**REF:** For details of how user-input times are interpreted, see the “Date Fields” in the “Editing Specific Field Types” section in the *VA FileMan User Manual*.

X: **EX**act input is required. If **X** is used *without M*, date input *must* include a day and month. Without **X**, the input can be just month-year or only a year.

If **X** is used with **M**, date input *must* include a month. If **M** is used *without X*, then the input can be just a year.

### 2.3.55.2 Y2K Changes : Behavior of %DT when neither the F nor P Flag is Used

If no year is entered, the current year is assumed (Example 1).

If a two-digit year is entered, a year less than 20 years in the future and no more than 80 years in the past is assumed. For example, in the year 2000, two-digit years are assumed to be between 1920 through 2019.



**NOTE:** Only the year, *not* the current month and day, is taken into account in this calculation (Examples [2](#) through [5](#)).

**Table 34: ^%DT: Internal to External Date—Y2K Changes**

Example	Current Date	User Input	Date Returned
1	Sep 15, 2000	3/15	Mar 15, 2000
2	Sep 15, 2000	1/1/20	Jan 01, 1920
3	Sep 15, 2000	12/31/20	Dec 31, 1920
4	Sep 15, 2000	1/1/19	Jan 01, 2019
5	Sep 15, 2000	12/31/19	Dec 31, 2019

### 2.3.56 DD^%DT: Converts Internal to External Date Format



**REF:** For an introduction to Date/Time formats, see the [“Introduction to Date/Time Formats: %DT”](#) section.

#### 2.3.56.1 DD^%DT: Converts Internal to External Date Format

There are two ways to convert a date from internal to external format:

- DD^%DT (this call)
- X ^DD(“DD”)

This is the reverse of what [%DT](#) does. The DD^%DT API takes a VA FileMan internal date in the **Y** variable and converts it to its external representation.

#### Input Variables

**Y:** (Required) This contains the internal date to be converted. If this has five or six decimal places, seconds are automatically returned.

**%DT:** (Optional) This forces seconds to be returned even if **Y** does *not* have that resolution. **%DT** *must* contain **S** for this to happen.

#### Output Variable

**Y:** **Y** is returned as the external form of the date.



**REF:** See also the [DT^DIO2: Writes External Date from Internal](#) API, which takes an internal date in the **Y** variable and *writes out* its external form.

### 2.3.56.1.1 Example

Figure 79: DD^%DT API—Example: Input and Output

```
>S Y=2690720.163 D DD^%DT W Y
JUL 20, 1969@1630
```

This results in **Y** being equal to JUL 20, 1969@16:30. (Single space before the 4-digit year.)

### 2.3.57 ^%DTC: Returns Number of Days between Two Dates

The ^%DTC API returns the number of days between two dates.

#### Input Variables

- X1: (Required) One date in VA FileMan internal format. This is *not* returned.  
X2: (Required) The other date in VA FileMan internal format. This is *not* returned.

#### Output Variables

- X: The number of days between the two dates. **X2** is subtracted from **X1**.  
%Y: Returns: If %Y is equal to:
- **1**—The dates have both month and day values.
  - **0**—The dates were imprecise, and therefore, *not* workable.

### 2.3.58 C^%DTC: Adds/Subtracts Days and Returns VA FileMan Date and \$H Format

The C^%DTC API takes a date and adds or subtracts a number of days, returning a VA FileMan date and a **\$H** format date. If time is included with the input, it is also included with the output.

#### Input Variables

- X1: (Required) The date in VA FileMan internal format to which days are going to be added or from which days are going to be subtracted. This is *not* returned.  
X2: (Required) If positive, the number of days to add. If negative, the number of days to subtract. This is *not* returned.

#### Output Variables

- X: The resulting date, in VA FileMan internal format, after the operation has been performed.  
%H: The **\$H** form of the date.

## 2.3.59 COMMA^%DTC: Formats Number to String with Commas

The COMMA^%DTC API formats a number to a string that separates billions, millions, and thousands with commas.

### Input Variables

- X: (Required) The number you want to format. **X** can be positive or negative.
- X2: (Optional) The number of decimal digits you want the output to have. If **X2** is *not* defined, two decimal digits are returned. If **X2** is a number followed by the dollar sign (e.g., 3\$) then a dollar sign is prefixed to **X** before it is output.
- X3: (Optional) The length of the desired output. If **X3** is less than the formatted **X**, **X3** is ignored. If **X3** is *not* defined, then a length of twelve is used.

### Output Variable

- X: The initial value of **X**, formatted with commas, rounded to the number of decimal digits specified in **X2**.
- If **X2** contained a dollar sign, then the dollar sign is next to the leftmost digit.
  - If **X** was negative, then the returned value of **X** is in parentheses.
  - If **X** was positive, a trailing space is appended.
  - If necessary, **X** is padded with leading spaces so that the length of **X** equals the value of the **X3** input variable.

### 2.3.59.1 Examples

#### 2.3.59.1.1 Example 1

Figure 80: COMMA^%DTC API—Example 1: Input

```
>S X=12345.678 D COMMA^%DTC
```

The result is shown in [Figure 81](#):

Figure 81: COMMA^%DTC API—Example 1: Output

```
X=" 12,345.68 "
```

#### 2.3.59.1.2 Example 2

Figure 82: COMMA^%DTC API—Example 2: Input

```
>S X=9876.54,X2="0$" D COMMA^%DTC
```

The result is shown in [Figure 83](#):

Figure 83: COMMA^%DTC API—Example 2: Output

```
X=" $9,877 "
```

### 2.3.59.1.3 Example 3

Figure 84: COMMA^%DTC API—Example 3: Input

```
>S X=-3,X2="$2$" D COMMA^%DTC
```

The result is shown in [Figure 85](#):

Figure 85: COMMA^%DTC API—Example 3: Output

```
X=" ($3.00)"
```

### 2.3.59.1.4 Example 4

Figure 86: COMMA^%DTC API—Example 4: Input

```
>S X=12345.678,X3=10 D COMMA^%DTC
```

The result is shown in [Figure 87](#):

Figure 87: COMMA^%DTC API—Example 4: Output

```
X="12,345.68 "
```

## 2.3.60 DW^%DTC: Converts VA FileMan Date to \$H Format and Outputs Name of the Day

The DW^%DTC API produces results similar to [H^%DTC](#). The difference is that **X** is reset to the name of the day of the week (i.e., Sunday, Monday, and so on). If the date is imprecise, then **X** is returned equal to null.

## 2.3.61 H^%DTC: Converts VA FileMan Date to \$H Format

The H^%DTC API converts a VA FileMan internal date/time to a **\$H** format date/time.

### Input Variable

**X:** (Required) The date/time in VA FileMan internal format. This is *not* returned.

### Output Variables

**%H:** The same date in **\$H** format. If the date is imprecise, then the first of the month or year is returned.

**%T:** The time in **\$H** format (i.e., the number of seconds since midnight). If there is no time, then **%T** equals zero.

**%Y:** The day-of-week as a numeric from **0** to **6**; where:

- **0**—Sunday
- **1**—Monday
- **2**—Tuesday
- **3**—Wednesday
- **4**—Thursday

- **5**—Friday
- **6**—Saturday

If the date is imprecise, then **%Y** is equal to **-1**.

### 2.3.62 **HELP^%DTC: Display Help Prompt Based on Date**

The **HELP^%DTC** API displays a help prompt based on the **%DT** and **%DT(0)** input variables.

#### **Input Variables**

**%DT:** The format of **%DT** is described in the “[%DT](#)” section. The help prompt displays different messages depending on the parameters in the variable.

**%DT(0):** (Optional) The format of **%DT(0)** is described in the “[%DT](#)” section. This input variable causes **HELP** to display the upper or lower bound that is acceptable for this particular call.

### 2.3.63 **NOW^%DTC: Returns Current Date/Time in VA FileMan and \$H Formats**

The **NOW^%DTC** API returns the current date/time in VA FileMan internal and **\$H** formats.

#### **Input Variables**

None.

#### **Output Variables**

**%:** VA FileMan internal date/time down to the second.

**%H:** **\$H** date/time.

**%I(1):** The numeric value of the month.

**%I(2):** The numeric value of the day.

**%I(3):** The numeric value of the year.

**X:** VA FileMan internal date only.

### 2.3.64 **S^%DTC: Converts Time into Decimal Part of VA FileMan Internal Date**

The **S^%DTC** API takes the number of seconds from midnight and turns it into hours, minutes, and seconds as a decimal part of a VA FileMan internal date.

#### **Input Variable**

**%:** (Required) A number indicating the number of seconds from midnight [e.g., **\$P(\$H,“,”,2)**].

#### **Output Variable**

**%:** The decimal part of a VA FileMan internal date.

### 2.3.64.1 Example

Figure 88: S^%DTC API—Example: Input and Output

```
>SET %=44504 D S^%DTC W %  
.122144
```

### 2.3.65 YMD^%DTC: Converts \$H to VA FileMan Format

The YMD^%DTC API converts a **\$H** format date to a VA FileMan internal date.

#### Input Variable

%H: (Required) A **\$H** format date/time. This is *not* returned.

#### Output Variables

%. Time down to the second in VA FileMan internal format (i.e., as a decimal).  
If %H does *not* have time, then % equals zero.

X: The date in VA FileMan internal format.

### 2.3.66 YX^%DTC: Returns Printable and VA FileMan Internal Formats from \$H

The YX^%DTC API takes a **\$H** date and returns a:

- Printable date and time
- VA FileMan internal form of the date and time

#### Input Variable

%H: (Required) This contains the date and time in **\$H** format that is to be converted to VA FileMan internal date format. Time is optional. This is *not* returned.

#### Output Variables

Y: The date and time (if time has been sent) in external format. Seconds are included if the input contained seconds.

X: The date in VA FileMan internal format.

%. The time as a decimal value in VA FileMan internal format. If time was *not* sent, then % is returned as zero.



## 2.3.67 %XY^%RCR: Moves Arrays between Locations

The %XY^%RCR API can be used to move arrays from one location to another. The location can be local or global.

After the call has completed, both arrays are defined. They are identically subscripted if the %Y array did *not* previously exist. If the array identified in %Y had existing elements, those elements still exist after the call to %XY^%RCR. However, their values may have to be examined, because an identically subscripted element in the %X array replaces the one in the %Y array, but an element that existed in the %Y array (but *not* in the %X array) remains as it was.

### Input Variables

%X: The global or array root of an existing array. The descendants of %X is moved.  
%Y: The global or array root of the target array. It is best if this array does *not* exist before the call.

### 2.3.67.1 Example

To move the local array X( to ^TMP(\$J, you would write:

**Figure 89: %XY^%RCR API—Example: Input**

```
>S %X="X(" S %Y="^TMP($J," D %XY^%RCR
```

## 3 Database Server (DBS) API

### 3.1 Introduction

The VA FileMan Database Server (DBS) is an Application Programming Interface (API) for accessing data attributes and data in VA FileMan files. The principal function of these APIs is to separate database access from user presentation. In Classic VA FileMan's roll and scroll mode, the interaction with the end user was closely tied to the code that actually changed the database. Whenever VA FileMan needed information from the user, a READ was done; whenever VA FileMan needed to present information to the user, a WRITE was done.

However, with VA FileMan's DBS calls, no WRITES to the current device are done. Interaction with the user is managed by the client application. Package developers can manage user interaction from within their own code and can call VA FileMan whenever interaction with the database is needed. The DBS calls are used to update the database in a *non*-interactive mode. Information needed by the VA FileMan routines is passed through parameters rather than through interactive dialogue with the user. Any information that needs to be displayed to the end-user is passed by VA FileMan back to the calling routine in arrays.

This separation of data access from user input/output (I/O) makes possible the construction of alternative front-ends to the VA FileMan database (e.g., a windowed Graphical User Interface [GUI]). In addition, this API can be the basis for data access by applications running outside M.

This section is structured as follows:

- [How to Use Database Server \(DBS\) Calls](#)—Describes the conventions used in the DBS API.
- [How the Database Server \(DBS\) Communicates](#)—Offers a detailed description of the way DBS calls return information to the client application in arrays.
- Individual calls are described, including input parameters, output, and examples of their use.

### 3.2 How to Use Database Server (DBS) Calls

- [Format and Conventions of the Calls](#)
- [IENS: Identify Entries and Subentries](#)
- [FDA: Format of Data Passed to and from VA FileMan](#)
- [Documentation Conventions](#)

#### 3.2.1 Format and Conventions of the Calls

All of the DBS calls use parameter passing instead of relying on variables set prior to the call that are passed through the symbol table. However, VA FileMan's key variables (e.g., **DUZ** and **DT**) are *not* passed in the parameter list. When needed, VA FileMan continues to expect them to be defined in the local symbol table.

Except where noted, the order of the parameters in the argument list follows a consistent pattern as follows:

**Figure 90: Database Server (DBS) API—Format and Conventions of the Calls: Order of the Parameters in the Argument List**

```
TAG^ROUTINE(file,iens,field,flags,other_required_params,other_optional_params)
```

If a particular call does *not* use one or more of the first four parameters, that parameter is omitted from the list of arguments. Generally, when a file is needed, the file number (*not* global root) *must* be passed. This allows for consistency when referring either to a top-level file or to a subfile. Similarly, a field is identified by its field number.

When it is necessary to pass the root of a local or global array, the complete closed reference of the array for use with subscript indirection is needed, *not* the traditional open VA FileMan root. Examples are illustrated in [Table 35](#):

**Table 35: Database Server (DBS) API—Format and Conventions of the Calls—Acceptable vs. Unacceptable Roots**

Acceptable Roots	Unacceptable Roots
^TMP("NMSP", \$J)	^TMP("NMSP", \$J,
LOCALVAR	LOCALVAR(

Since the array identified by this root is accessed by indirection, the contents of the array can be changed by the VA FileMan call. The description of the individual calls indicates whether you can rely on the arrays *not* being changed. In addition, to assure that an input array is *not* inadvertently changed during the DBS call, namespace the array.

### 3.2.2 IENS: Identify Entries and Subentries

The way to represent internal entry numbers for entries in the database is by a structure called an Internal Entry Number String (IENS). It is VA FileMan’s way of representing the internal entry numbers for an entry in all of the DBS calls.

An IENS is a comma-delimited list of internal entry numbers beginning with the lowest level subentry and ending with the top-level entry number. Regardless of how many levels exist, a comma (,) is appended to the end. For example, to specify subentry 2 in a Multiple for entry 250, IENS would equal “2,250,”. The corresponding values for the DA() array would be DA=2 and DA(1)=250 (or D0=250 and D1=2). If you were referencing the top-level of the file, the IENS would be “250,”; DA=250 or D0=250. There are calls that can be used to construct an IENS from a DA() array and a DA() array from an IENS.



**REF:** For more information, see descriptions of [DA^DILF](#) and [\\$\\$IENS^DILE](#).

In the simplest case, each comma-piece of the IENS is a number that directly and uniquely identifies an entry in a file or subfile. However, sometimes the client application does *not* know the entry number. For example, often the entry number is unknown when a call to the [Updater](#) is being made. In other situations, the client application wants the DBS to find a record and then file data in it; the entry number is unimportant to the client. In order to accommodate these circumstances, certain placeholders can be used in the IENS if the particular DBS call supports their use. The extended IENSs (those including a placeholder) are *not* accepted for all DBS calls. The calls that accept the extended IENSs are identified in the call’s documentation.

The placeholder consists of a one- or two-character code identifying how you want the entry number derived, followed by a positive integer. The codes are listed in [Table 36](#). The integer uniquely identifies the record involved in different nodes of the VA FileMan Data Array (FDA), as described in Section 3.2.3, “[FDA: Format of Data Passed to and from VA FileMan](#).”

**Table 36: IENS: Identify Entries and Subentries—Placeholder Codes**

Placeholder Code	Description
+	Add a new entry or subentry.
?	Find an entry or subentry and use it for filing.
?+	Find an entry or subentry; if one does not exist, add it (LAYGO).

Thus, if you wanted to find an entry and then to add a new subentry into that entry, your IENS might look like: “+2,?1”. Every time you referenced that top-level entry in your **FDA**, you would use “?1”; every time you referenced that particular subentry, you would use “+2”. A second new subentry might be “+3”, and so on.



**REF:** For more information about using the entry number placeholders, see the descriptions of the [Updater](#) and [Finder](#) calls.

### 3.2.3 FDA: Format of Data Passed to and from VA FileMan

Data is passed to and from the DBS as values in the VA FileMan Data Array (FDA). The **FDA** contains the file, internal entry numbers, and field information in its subscripting scheme.

#### Format

```
FDA_ROOT(file#,"iens",field#)="value"
```

#### Input Parameters

- file#: (Required) The number of the file or subfile to which the data belongs.
- iens: (Required) As explained in Section 3.2.2, “[IENS: Identify Entries and Subentries](#),” a comma-delimited string of entry and subentry numbers. The **iens** *always* ends with a comma.
- field#: (Required) The number of the field being accessed.
- value: (Required) The internal (and verified) or external (and unverified) value of the field. The specific call that you are making along with the way certain flags are set determines if the internal or external value is appropriate.

The values for WORD-PROCESSING fields are stored in the **FDA** differently. Instead of setting the node equal to the actual value, set it equal to the root of an array (local or global) that holds the data. The word-processing data *must* be stored at nodes with positive numbers in the designated array or at the **0**-node descendent from those nodes. The subscripts need *not* be integers.

For example, if the value of an **FDA** node were “**^TMP(\$J,“WP”)**”, the location of the word-processing data could be:

```
^TMP($J, "WP", 1, 0)=Line 1
^TMP($J, "WP", 2, 0)=Line 2
...etc.
```

Or:

```
^TMP($J, "WP", 1)=Line 1
^TMP($J, "WP", 2)=Line 2
...etc.
```

For word-processing data, the file and field numbers should reflect the file (or subfile) and field of the **WORD-PROCESSING** field, *not* the subfile number of the pseudo-Multiple where the word-processing data is actually stored.

Nodes in the **FDA** can be set in several ways. The Validator call ([VAL^DIE](#)) optionally creates nodes in an **FDA** for valid user input. If the Validator is *not* being used, developers can use the [FDA^DILF](#) call that creates an element in the **FDA**. Finally, the application developer can set the nodes manually in the client application’s code.

### 3.2.4 Documentation Conventions

If a parameter *must* be passed by reference, that parameter is preceded by a period (.) when the format for the call is shown. In [Figure 91](#), the **argument** array *must* be passed by reference.

**Figure 91: Database Server (DBS) API—Documentation Conventions: Passing by Reference Only**

```
CALL^DIFM(. argument)
```

If a parameter can be passed either by reference *or* by value, it is preceded by a period enclosed in brackets ([.]). In [Figure 92](#), the **argument** parameter can be passed either by reference or by value.

**Figure 92: Database Server (DBS) API—Documentation Conventions: Passing by Reference or by Value**

```
CALL^DIFM([.] argument)
```



**CAUTION:** It is very important that arrays be passed as specified in the descriptions of the calls (i.e., by value or reference as indicated).

## 3.3 How the Database Server (DBS) Communicates

- [Overview](#)
- [How Information Is Returned](#)
- [Contents of Arrays](#)
- [Obtaining Formatted Text from the Arrays](#)

- [Cleaning Up the Output Arrays](#)
- [Example of Call to VA FileMan DBS](#)

### 3.3.1 Overview

A distinguishing feature of the Database Server (DBS) calls is that they do *not* “talk,” nothing is written to a device. The DBS communicates with the client application by passing data in arrays instead of communicating directly with the user by writing to the screen. It is the client application’s responsibility to determine if, when, and how to inform the user of the information originating from the DBS.

The way that the DBS passes *primary* information, such as the value of a field when doing a Data Retriever call or a record’s internal entry number when doing a Finder call, is documented for each call.

*Secondary* information consists of:

- Error messages.
- Help text.
- Information currently written from nodes in the Data Dictionary by Classic VA FileMan calls.

The way secondary information is passed to the client application is described in the following sections:

- [How Information Is Returned](#)
- [Contents of Arrays](#)
- [Obtaining Formatted Text from the Arrays](#)
- [Cleaning Up the Output Arrays](#)
- [Example of Call to VA FileMan DBS](#)

### 3.3.2 How Information Is Returned

Information is passed back to the client application in arrays. By default the arrays are:

**Figure 93: Database Server (DBS) API—How Information Is Returned: Arrays**

<code>^TMP("DIHELP", \$J)</code>	for help
<code>^TMP("DIMSG", \$J)</code>	for other user messages
<code>^TMP("DIERR", \$J)</code>	for error messages



**NOTE:** In traditional VA FileMan Classic calls, the first two of these types of messages are written directly to the screen; the last one did *not* exist or consisted solely of “<BEEP>?”.

In addition, there is an output variable associated with each of these arrays. DIHELP and DIMSG equal the number of nodes of text associated with their respective arrays. DIERR has the following two pieces:

```
number_of_errors^number_of_nodes_of_text
```

If the client application wants the data returned in another array (local or global), the array’s closed root should be passed as a parameter in the DBS call. The major DBS calls have a parameter to accept this root as the last parameter. Thus, if the call looks like [Figure 94](#):

**Figure 94: Database Server (DBS) API—How Information Is Returned: Passing Parameters: Input**

<code>&gt;D CALL^FM("other_parameters", "mymsgs")</code>
--

Information is returned in ([Figure 95](#)):

**Figure 95: Database Server (DBS) API—How Information Is Returned: Passing Parameters: Output**

```
MYMSGS ( "DIHELP" )  
MYMSGS ( "DIMSG" )  
MYMSGS ( "DIERR" )
```

Also, the values stored in the corresponding local variables are put into the top-level nodes of these arrays. When the application specifies an array for output, nothing is returned in the **^TMP** arrays.

### 3.3.3 Contents of Arrays

The following arrays are discussed in this section:

- [DIHELP Array](#)
- [DIMSG Array](#)
- [DIERR Array](#)

#### 3.3.3.1 DIHELP Array

Text in the **DIHELP** array has several sources:

- Some help text is stored in the DIALOG (#.84) file; an example of this sort of help is the text returned by **%DT** when you enter a **?** at a prompt requiring a date.
- Other help comes directly from text in the data dictionary (DD).
- Executable help relies on calls to the Loader (see [EN^DDIOL](#)) embedded in the executable code. The Loader call takes the place of WRITES.



**NOTE:** In other contexts, the Loader puts text under the **DIMSG** subscript. However, when executing Executable Help, the Loader puts the text under the **DIHELP** subscript instead.

The DBS call in [Figure 96](#) returns help for a particular field:

**Figure 96: Database Server (DBS) API—DIHELP Array: Input to Return Help for a Particular Field**

```
>D HELP^DIE(file,iens,field,type_of_help,msg_root)
```

**type\_of\_help** is a set of flags that allows the client application to specify which help text (e.g., help prompt, description, list of set of codes, executable help, etc.) to return. Alternatively, a single or double question mark returns the same information that is currently returned in scrolling mode.



**REF:** For details, see the documentation for the [Helper](#) call.

If **msg\_root** is *not* specified as a target, the help is returned in **^TMP("DIHELP", \$J)** as described in Section [3.3.2](#), "[How Information Is Returned](#)." The local variable **DIHELP** equals the total number of nodes returned.

Text in the array that contains help is subscripted with integers. If more than one kind of help is being returned, a null node is put between them.

If a flag is set by the client application when the [CHK^DIE](#) or [VAL^DIE](#) calls are made, help is returned when a value is found to be invalid. The help is returned in the standard way described in Section [3.3.2](#), "[How Information Is Returned](#)."

### 3.3.3.2 DIMSG Array

A main source of the **DIMSG** array is output from the Loader: [EN^DDIOL](#). Writes that are currently embedded in the database *must* be changed to calls to [EN^DDIOL](#) if the DBS is to be used. When running applications in scrolling mode, the Loader simply WRITES the text to the screen. However, if the node containing the [EN^DDIOL](#) call is executed from within one of the DBS calls, the DBS returns text in an array, usually subscripted by **DIMSG**.



**REF:** For more detailed information about [EN^DDIOL\(\): Message Loader](#), see its description in the “Classic VA FileMan API” section.

When the user is *not* in scrolling mode, the Loader most frequently places the text into the **DIMSG** array with the local variable **DIMSG** set equal to the total number of lines in the array. There are certain situations, however, where the output is put into another array. As mentioned in the [DIHELP Array](#), when the DBS [HELP^DIE](#) call is used to get help, the output of an [EN^DDIOL](#) call embedded in executable help is placed into the **DIHELP** array.

Like **DIHELP**, the **DIMSG** array is simply a list of lines of text.

Suppose an INPUT transform currently contains:

**Figure 97: Database Server (DBS) API—DIMSG Array: Sample Input Transform**

```
N Y S Y=$L(X) K:Y>30!(Y<3) X I '$D(X) W !,"Your input was "_Y_
" characters long.",!, "This is the wrong length."
```

It can be changed to:

**Figure 98: Database Server (DBS) API—DIMSG Array: Changing Input Transform: Executed in Scrolling Mode**

```
N Y S Y=$L(X) K:Y>30!(Y<3) X I '$D(X) S Y(1)="Your input was "_Y_
" characters long.",Y(2)="This is the wrong length." D EN^DDIOL(.Y)
```

This change would have no effect if the user were in scrolling mode; the same message is written to the screen. However, if the second INPUT transform were executed from a silent call, nothing is written and the “**DIMSG**” array returned to the client application might look like [Figure 99](#):

**Figure 99: Database Server (DBS) API—DIMSG Array: Changing Input Transform: Executed from a Silent Call**

```
^TMP("DIMSG",$J,1)="Your input was 2 characters long."
^TMP("DIMSG",$J,2)="This is the wrong length."
```

### 3.3.3.3 DIERR Array

When an error condition is encountered during a DBS call, an error message and other information is placed in the **DIERR** array. In addition, the **DIERR** variable is returned with the following two pieces of information:

- Number of errors generated during the call in the first piece.
- Total number of lines of the error messages in the second.



Thus, a **\$D** check on the variable **DIERR** after the completion of the call allows the client application to determine if an error occurred. Both of the following errors are returned:

- Syntactical (e.g., the root of an array is *not* in the proper format for subscript indirection)
- Substantive (e.g., a specified field does *not* exist in the specified file).

The information contained in the **DIERR** array is designed to give the client application-specific information about the kind of error that occurred to allow for intelligent error handling and to provide readable error messages. [Figure 100](#) is an example of error reporting following a [Filer](#) call:

**Figure 100: Database Server (DBS) API—DIERR Array: Sample Input and Output**

```
>W $G(DIERR)
2^2
>D ^%G

Global ^TMP("DIERR",$J
      TMP("DIERR",$J
^TMP("DIERR",731990208,1) = 305
^TMP("DIERR",731990208,1,"PARAM",0) = 1
^TMP("DIERR",731990208,1,"PARAM",1) = ^TMP("MYWPDATA",$J)
^TMP("DIERR",731990208,1,"TEXT",1) = The array with a root of
'^TMP("MYWPDATA",$J)' has no data associated with it.
^TMP("DIERR",731990208,2) = 501
^TMP("DIERR",731990208,2,"PARAM",0) = 3
^TMP("DIERR",731990208,2,"PARAM",1) = 89
^TMP("DIERR",731990208,2,"PARAM","FIELD") = 89
^TMP("DIERR",731990208,2,"PARAM","FILE") = 16200
^TMP("DIERR",731990208,2,"TEXT",1) = File #16200 does not contain a field 89.
^TMP("DIERR",731990208,"E",305,1) =
^TMP("DIERR",731990208,"E",501,2) =
```

The **DIERR** variable acts like a flag. In [Figure 100](#), it reports that two errors occurred and that they have a total of two lines of text.

The **^TMP("DIERR",\$J)** global contains information about the errors.

```
^TMP("DIERR",$J,sequence#) = error number
```

In this case, two errors were returned: errors #305 and #501. Each error number corresponds to an entry in the DIALOG (#.84) file. The actual text of each error is stored in nodes descendent from **"TEXT"**:

```
^TMP("DIERR",$J,sequence#,"TEXT",line#) = line of text
```

The **^TMP("DIERR",\$J,sequence#,"PARAM")** subtree contains specific parameters that can be returned with each error:

```
^TMP("DIERR",$J,sequence#,"PARAM",0) = number of parameters returned with the
error
^TMP("DIERR",$J,sequence#,"PARAM","param_name") = parameter value
```

The VA FileMan error messages and their associated parameters are documented in “[Appendix A—VA FileMan Error Codes](#).” For example, Appendix A indicates that three parameters are returned with error #501:

- “1”—Field name or number
- “FILE”—File number
- “FIELD”—Field number

So, in [Figure 100](#), for error #501, the “PARAM” nodes indicate that the error corresponds to (fictitious) File #16200, Field #89.

Finally, the “E” cross-reference in the ^TMP(“DIERR”,\$J) global allows you to determine quickly whether a particular error occurred. For example, if you wanted to do some special error processing if a DBS call generated error #305, you could check:

```
$D(^TMP("DIERR", $J, "E", 305))
```

The **DIERR** array is more complicated than the other arrays discussed, thereby making more information available to the client application for error handling.

### 3.3.4 Obtaining Formatted Text from the Arrays

If you want the text from any of the three arrays, the call in [Figure 101](#) extracts it from the structures described in Section 3.3.3, “[Contents of Arrays](#).”

**Figure 101: Database Server (DBS) API—Obtaining Formatted Text from the Arrays: Input**

```
>D MSG^DIALOG(flags, .output_array, text_width, left_margin, input_root)
```

It does either of the following:

- Writes it to the screen.
- Puts it into a local array for further use:

The flags for the MSG^DIALOG call:

- Control whether the text is written to the current device or moved into the **output\_array** specified in the second parameter.
- Direct whether the source arrays are saved or deleted, and which kinds of dialogue (e.g., errors, help, or other messages) are processed.
- Supports some formatting of text.



**REF:** For details of its use, see the description of the [MSG^DIALOG\(\): Output Generator](#) API.

### 3.3.5 Cleaning Up the Output Arrays

When you make a DBS call and use the default arrays in the **^TMP** global for output of help, user, and error messages, the DBS call KILLS off these arrays and their related variables at the start of the call. Therefore, you know that any data that exists after the call was generated by that call.

If you do *not* use the default arrays for output, however, and instead specify your own arrays in which this information is returned, your arrays are *not* automatically KILLED at the start of a DBS call. So, if there is any chance that these arrays might already exist, you should KILL them yourself *before* making the DBS call.

After making a DBS call, if you used the default arrays in **^TMP** for output of help, user, and error messages, you should delete these arrays *before* your application Quits. To do this, use the following call:

**Figure 102: Database Server (DBS) API—Cleaning Up the Output Arrays: Input**

```
>D CLEAN^DILF
```



**REF:** For details of its use, see the description of the “[CLEAN^DILF: Array and Variable Clean-up](#)” API.

If you are using your own arrays for output, however, you need to clean up your arrays yourself. You should still call [CLEAN^DILF](#) to KILL off the variables related to these arrays.

### 3.3.6 Example of Call to VA FileMan DBS

One of the DBS calls validates data. If the data is valid, the internal representation of that data is returned. If the data is invalid, a caret (^) is returned along with various messages, optionally including the relevant help text. The validator call looks like this:

```
VAL^DIE(file,iens,field,flags,value,.result,fda_root,msg_root)
```



**REF:** For details, see the “[Validator](#)” documentation.

Your call might look like [Figure 103](#):

**Figure 103: Database Server (DBS) API—Example of Call to VA FileMan DBS: Input**

```
>D VAL^DIE(999000,"223","4","H","AB",.MYANSWER,"","MYMSGS("WIN3"))
```

If MYANSWER equaled ^ after the call, your MYMSGs("WIN3") array might look like [Figure 104](#):

**Figure 104: Database Server (DBS) API—Example of Call to VA FileMan DBS: Sample Array Output**

```
MYMSGS("WIN3","DIERR")=1^1
MYMSGS("WIN3","DIERR",1)=701
MYMSGS("WIN3","DIERR",1,"PARAM",0)=4
MYMSGS("WIN3","DIERR",1,"PARAM",3)="AB"
MYMSGS("WIN3","DIERR",1,"PARAM","FIELD")=4
MYMSGS("WIN3","DIERR",1,"PARAM","FILE")=999000
MYMSGS("WIN3","DIERR",1,"PARAM","IENS")="223"
MYMSGS("WIN3","DIERR",1,"TEXT",1)="The value 'AB' for field ALPHA DATA in file
TEST1 is not valid."
MYMSGS("WIN3","DIERR","E",701,1)=""
MYMSGS("WIN3","DIHELP")=1
MYMSGS("WIN3","DIHELP",1)="Answer must be 3-30 characters in length."
MYMSGS("WIN3","DIMSG")=1
MYMSGS("WIN3","DIMSG",1)="Your input was 2 characters long."
MYMSGS("WIN3","DIMSG",2)="This is the wrong length."
```

- The **DIERR** portion of this array indicates that error number 701 is being reported. Documentation makes clear that this means that an input value was invalid.
- The **PARAM** nodes (also documented) give the client application the relevant file#, field#, IENS, and value. This information might be used by the application in its error handling.
- The **TEXT** node contains the error message.



**NOTE:** It is customized to include specifics of the current error.

- The **DIHELP** node contains single-question-mark help for the field.
- The **DIMSG** nodes contain a message generated by the INPUT transform via an [EN^DDIOL](#) call.

(The sample INPUT transform discussed in the “[DIMSG Array](#)” section produced this message.)

Now, the client application decides what (if anything) to show the user. In a GUI environment, you might decide to put the error message along with any text from the INPUT transform into a document gadget. A **HELP** button that could be used by the user to display the help information might be added to the box. VA FileMan’s DBS has provided text; the client application is in complete control regarding the use of this text.

### 3.4 Database Server Calls Cross-Referenced by Category

Table 37: Database Server (DBS) API—Database Server (DNS) Calls Cross-referenced by Category

Category	Database Server Call (DBS)
Data Dictionary	<ul style="list-style-type: none"> <li>• <a href="#">FIELD^DID</a></li> <li>• <a href="#">FIELDLST^DID</a></li> <li>• <a href="#">FILE^DID</a></li> <li>• <a href="#">FILELST^DID</a></li> <li>• <a href="#">\$\$GET1^DID</a></li> <li>• <a href="#">\$\$FLDNUM^DILFD</a></li> <li>• <a href="#">PRD^DILFD</a></li> <li>• <a href="#">\$\$ROOT^DILFD</a></li> <li>• <a href="#">\$\$VFIELD^DILFD</a></li> <li>• <a href="#">\$\$VFILE^DILFD</a></li> </ul>
Data Dictionary Modification	<ul style="list-style-type: none"> <li>• <a href="#">CREIXN^DDMOD</a></li> <li>• <a href="#">DELIX^DDMOD</a></li> <li>• <a href="#">DELIXN^DDMOD</a></li> <li>• <a href="#">FILESEC^DDMOD</a></li> </ul>
Data Editing	<ul style="list-style-type: none"> <li>• <a href="#">CHK^DIE</a></li> <li>• <a href="#">FILE^DIE</a></li> <li>• <a href="#">HELP^DIE</a></li> <li>• <a href="#">\$\$KEYVAL^DIE</a></li> <li>• <a href="#">UPDATE^DIE</a></li> <li>• <a href="#">VAL^DIE</a></li> <li>• <a href="#">VALS^DIE</a></li> <li>• <a href="#">WP^DIE</a></li> <li>• <a href="#">RECALL^DILFD</a></li> </ul>
Data Retrieval	<ul style="list-style-type: none"> <li>• <a href="#">\$\$GET1^DIQ</a></li> <li>• <a href="#">GETS^DIQ</a></li> </ul>
Lookup	<ul style="list-style-type: none"> <li>• <a href="#">FIND^DIC</a></li> <li>• <a href="#">\$\$FIND1^DIC</a></li> <li>• <a href="#">LIST^DIC</a></li> </ul>
User Dialogue	<ul style="list-style-type: none"> <li>• <a href="#">BLD^DIALOG</a></li> <li>• <a href="#">\$\$EZBLD^DIALOG</a></li> <li>• <a href="#">MSG^DIALOG</a></li> </ul>

Category	Database Server Call (DBS)
Utilities	<ul style="list-style-type: none"> <li>• <a href="#">CLEAN^DILF</a></li> <li>• <a href="#">\$\$CREF^DILF</a></li> <li>• <a href="#">DA^DILF</a></li> <li>• <a href="#">DT^DILF</a></li> <li>• <a href="#">FDA^DILF</a></li> <li>• <a href="#">\$\$HTML^DILF</a></li> <li>• <a href="#">\$\$IENS^DILF</a></li> <li>• <a href="#">LOCK^DILF</a></li> <li>• <a href="#">\$\$OREF^DILF</a></li> <li>• <a href="#">\$\$VALUE1^DILF</a></li> <li>• <a href="#">VALUES^DILF</a></li> <li>• <a href="#">\$\$EXTERNAL^DILFD</a></li> </ul>

## 3.5 Database Server (DBS) Calls Presented in Alphabetical Order

This section lists and describes the VA FileMan Database Server (DBS) calls in alphabetical order. However, the table above cross-references the DBS calls by category:

### 3.5.1 CREIXN^DDMOD(): New-Style Cross-Reference Creator

The CREIXN^DDMO API creates a New-Style cross-reference definition in the INDEX (#.11) file. Optionally, it builds the data in the index (for Regular cross-references) or executes the **SET** logic (for MUMPS cross-references) for all entries in the file. Compiled input templates that contain one or more of the fields defined in the cross-reference are recompiled. If cross-references on the file are compiled, they are recompiled.

One use of CREIXN^DDMOD is in the pre-install or post-install routine of a Kernel Installation and Distribution System (KIDS) build to create a New-Style cross-reference at the installing site.



**REF:** For information on the call to delete a New-Style cross-reference definition, see the [DELIX^DDMOD\(\): Traditional Cross-reference Delete](#) API.

For information on a programmer mode utility that can be used to help create a routine that calls the CREIXN^DDMOD API, see the ^DIKCBLD API in the “[^DIKCBLD: Build an M Routine that Makes a Call to CREIXN^DDMOD](#)” API.

#### Format

```
CREIXN^DDMOD( .xref[, flags][, .result][, output_root][, msg_root])
```

#### Input Parameters

- .xref: (Required) This input array contains information about the New-Style cross-reference to be created. The elements in this array are as follows:
- (Required) **XREF(“FILE”)**—The number of the file or subfile on which the index physically resides. For whole-file indexes, this should be the file number of the upper-level file, *not* the subfile that contains the fields in the index. For MUMPS cross-references that do *not* set an index, XREF(“FILE”) should be the file that contains the fields in the cross-reference.
  - (Required) **XREF(“TYPE”)**:
    - **R** or **REGULAR**—For regular indexes
    - **MU** or **MUMPS**—For MUMPS-type cross-references.
  - (Required if **XREF(“USE”)** is *not* passed) **XREF(“NAME”)**—The name of the cross-reference.

If **XREF(“NAME”)** is *not* passed, CREIXN^DDMOD gets the next available name based on the **XREF(“FILE”)** and **XREF(“USE”)**. In most cases, however, you should explicitly give your new cross-reference a name.
  - (Required for whole-file indexes) **XREF(“ROOT FILE”)**—For whole-file indexes, the number of the file or subfile that contains the fields in

the cross-reference. This is the subfile number, *not* the upper-level file number where the index physically resides. **XREF("ROOT FILE")** should only be set for whole-file indexes.

- (Required) **XREF("SHORT DESCR")**—Short description of the cross-reference.
- (Optional) **XREF("DESCR",1)**—Line 1 of the cross-reference description.
- (Optional) **XREF("DESCR",n)**—Line *n* of the cross-reference description.
- (Required if **XREF("NAME")** is *not* passed) **XREF("USE")**:
  - **LS** or **LOOKUP & SORTING**—For indexes used for both lookup and sorting. The cross-reference sets an index and the index name *must* start with **B** or a letter that alphabetically follows **B**. Calls to Classic VA FileMan lookup ([^DIC](#)) or the Finder ([FIND^DIC](#) or [\\$\\$FIND1^DIC](#)) where the index is *not* specified include this index in the search. The index is available for use by the VA FileMan Sort and Print ([EN1^DIP](#)).
  - **S** or **SORTING ONLY**—For indexes used for sorting only. The cross-reference sets an index, and the index name *must* start with **A**. Calls to Classic VA FileMan lookup ([^DIC](#)) or the Finder ([FIND^DIC](#) or [\\$\\$FIND1^DIC](#)) do *not* use this index unless it is specified in the input parameters to those calls. The index is available for use by the VA FileMan Sort and Print ([EN1^DIP](#)).
  - **A** or **ACTION**—For MUMPS cross-reference that do *not* set an index. This is used for MUMPS cross-references that perform some actions other than building an index. The cross-reference name *must* start with **A**.

If **XREF("USE")** is *not* passed, CREIXN^DDMOD assumes a value based on the cross-reference name and type:

- If the name starts with **A**, **XREF("USE")** is assumed to be **S** (Sorting Only) for Regular indexes, and **A** (Action) for MUMPS cross-references.
- If the name does *not* start with an **A**, **XREF("USE")** is assumed to be **LS** (Lookup & Sorting).



**NOTE:** For clarity, it is *recommended* that you explicitly set **XREF("USE")**.

- (Optional; Defaults to **F** for simple cross-references, and **R** for compound cross-references) **XREF("EXECUTION")**:
  - **F** or **FIELD**—For field-level execution
  - **R** or **RECORD**—For record-level execution.

This indicates whether the cross-reference logic should be executed after a field in the cross-reference changes, or only after all fields in a record are updated in an editing session. The logic for most simple (single-field)



cross-references should be executed immediately after the field changes, and so should have an Execution of **F**. The logic for most compound (multi-field) cross-references should be executed only once after a transaction on the entire record is complete, and so should have an Execution of **R**.

- (Optional; Defaults to **IR**) **XREF("ACTIVITY")**—One or both of the following codes:
  - **I**—Installing an entry at a site.
  - **R**—Re-cross-referencing this index.

If Activity contains an **I**, VA FileMan fires the cross-references during a KIDS installation. If Activity contains an **R**, VA FileMan fires the cross-reference during a re-cross-referencing operation.



**NOTE:** VA FileMan automatically fires cross-references during an edit, regardless of Activity; although, you can control whether a cross-reference is fired by entering **SET** and **KILL** conditions.

Also, if you explicitly select a cross-reference for the following, that cross-reference is fired whether or not its Activity contains an **R**:

- [EN^DIK](#) API
  - [EN1^DIK](#) API
  - [ENALL^DIK](#) API
  - Re-Index File option [DIRDEX] on the Utility Functions menu [DIUTILITY]
- (Optional) **XREF("SET CONDITION")**—M code that sets the variable **X**. The **SET** logic of the cross-reference is executed only if the **SET** condition, if present, sets **X** to Boolean **true**, according to the M rules for Boolean interpretation.

The M code can assume the **DA** array describes the record to be cross-referenced, and that the **X(order#)** array contains values after the transform for storage is applied, but before the truncation to the maximum length. The variable **X** also equals **X(order#)** of the lowest order number.

When fields that make up a cross-reference are edited and the **KILL** and **SET** conditions are executed, the **X1(order#)** array contains the old field values, and the **X2(order#)** array contains the new field values. If a record is being added, and there is an **X1(order#)** array element that corresponds to the **.01** field, it is set to null. When a record is deleted, all **X2(order#)** array elements are null.
  - (Optional) **XREF("KILL CONDITION")**—M code, that sets the variable **X**. The **KILL** logic of the cross-reference is executed only if the **KILL** condition, if present, sets **X** to Boolean **true**, according to the M rules for Boolean interpretation.



**REF:** For a description of the **DA**, **X**, **X1**, and **X2** arrays that can be used in the MUMPS code, see **XREF**(“**SET CONDITION**”).

For MUMPS cross-references, you can also set the following nodes in the **XREF** array. (For Regular Indexes, the **SET** and **KILL** logic is determined automatically for you, and so these nodes, if passed in, are ignored.) The code can also make use of the **DA**, **X**, **X1**, and **X2** arrays as described in **XREF**(“**SET CONDITION**”) above.

- (Optional; Defaults to **Q**) **XREF**(“**SET**”)—M code that VA FileMan should be executed when the values of fields that make up the cross-reference are set or changed.
- (Optional; Defaults to **Q**) **XREF**(“**KILL**”)—M code that VA FileMan should be executed when the values of fields that make up the cross-reference are changed or deleted.
- (Optional) **XREF**(“**WHOLE KILL**”)—M code that can be executed to remove an entire index for all records in a file. When an entire file is reindexed, VA FileMan executes this code rather than looping through all the entries in the file and executing the **KILL** logic once for each entry.

Each value in the cross-reference is described in the **XREF**(“**VAL**”,**order#**) portion of the **XREF** array. The order numbers *must* be positive integers starting from **1**, and determine the order in which VA FileMan evaluates the cross-reference values to place in the **X**(**order#**) array during cross-reference execution.

- (Required) **XREF**(“**VAL**”,**order#**):
  - The field number (for field-type cross-reference values).
  - M code that sets **X** to the cross-reference value (for computed-type cross-reference values).

For computed-type cross-reference values, the **X**(**order#**) array is available for those cross-reference values with lower order numbers, and the **DA** array describes the IEN of the current record.

- (Optional) **XREF**(“**VAL**”,**order#**,”**SUBSCRIPT**”)—The subscript position number in the index, if this cross-reference value is used as a subscript in the index. The first subscript to the right of the index name is subscript number **1**. All subscripts *must* be consecutive integers starting from **1**.
- (Optional) **XREF**(“**VAL**”,**order#**,”**LENGTH**”)—The maximum length of the cross-reference value VA FileMan should use when storing the value as a subscript in the index.
- (Optional; Defaults to **F**) **XREF**(“**VAL**”,**order#**,”**COLLATION**”):
  - **F**—For “forwards.”
  - **B**—For “backwards.”

This indicates the direction VA FileMan's lookup utilities should **\$ORDER** through this subscript when entries are returned or displayed to the user.

- (Optional) **XREF("VAL",order#,"LOOKUP PROMPT")**—Text that becomes the prompt to the user when this index is used for lookup, and a value is requested for this subscript.

For field-type cross-reference values only, the following nodes can also be set:

- **XREF("VAL",order#,"XFORM FOR STORAGE")**—M code that sets the variable **X** to a new value. **X** is the only variable guaranteed to be defined and is equal to the internal value of the field. The Transform for Storage can be used to transform the internal value of the field before it is stored as a subscript in the index.
- **XREF("VAL",order#,"XFORM FOR LOOKUP")**—M code that sets the variable **X** to a new value. **X** is the only variable guaranteed to be defined and is equal to the lookup value entered by the user. During lookup, if the lookup value is *not* found in the index, VA FileMan executes the Transform for Lookup code to transform the lookup value **X** and tries the lookup again.
- **XREF("VAL",order#,"XFORM FOR DISPLAY")**—M code that sets the variable **X** to a new value. **X** is the only variable guaranteed to be defined and is set equal to the value of the subscript of in the index. During lookup, if a match or matches are made to the lookup value, the Transform for Display code is executed before displaying the index value to the user.

flags:

(Optional) Flags to control processing. The possible values are:

- **K**—When CREIXN^DDMOD calls [DELIXN^DDMOD](#) to initially delete the old cross-reference with the same name as the one it is creating:
  - Do *not* **KILL** the data in the old index if it is a Regular index.
  - Do *not* execute the old **KILL** logic if it is a MUMPS cross-reference. Whether or not this flag is passed, CREIXN^DDMOD deletes the old cross-reference definition, if it exists, before bringing in the new definition.
- **S**—For Regular indexes, **SET** the data in the index. For MUMPS cross-references, execute the **SET** logic for all entries in the file.
- **W**—Write messages to the current device as the index is created and cross-references and input templates are recompiled.

.result:

(Optional) Local variable that receives the IEN of the entry that was created in the INDEX (#.11) file:

- **Successful**—RESULT = IEN in INDEX (#.11) file ^ cross-reference name.
- **Unsuccessful**—RESULT = Null ("") if cross-reference could *not* be created.

output\_root: (Optional) The name of the array that should receive information about input templates and cross-references that may have been recompiled.



**REF:** See the “[Output](#)” section.

This *must* be a closed root, either local or global.

msg\_root: (Optional) The name of the array that should receive any error messages. This *must* be a closed root, either local or global. If *not* passed, errors are returned descendent from ^TMP(“DIERR”, \$J).

## Output

result: See [.result](#) under “[Input Parameters](#).”

- **Successful**—RESULT = IEN in INDEX (#.11) file ^ cross-reference name
- **Unsuccessful**—RESULT = Null (“”) if cross-reference could *not* be created.

output\_root: See [output\\_root](#) under “[Input Parameters](#).”

If a field used in the index is used in any compiled INPUT templates, those INPUT templates are recompiled. Information about the recompiled INPUT templates is stored descendant from **OUTPUT\_ROOT(“DIEZ”)**:

```
OUTPUT_ROOT( "DIEZ", input template #) =  
input template name ^ file # ^  
compiled routine name
```

If cross-references for the file are compiled, they are recompiled, and the compiled routine name is stored in **OUTPUT\_ROOT(“DIKZ”)**:

```
OUTPUT_ROOT( "DIKZ" ) = compiled routine name
```

### 3.5.1.1 Examples

#### 3.5.1.1.1 Example 1

In this example ([Figure 105](#) and [Figure 106](#)), a New-Style compound “C” index is created on (fictitious) File #16000. It contains two field-type cross-reference values, Fields #1 and #2, both of which are used as subscripts in the index. The following flags indicate:

- **S**—Index should be built after its definition is created.
- **W**—Messages should be written to the current device as the index is created and built, and as templates and cross-reference are recompiled.

**Figure 105: CREIXN^DDMOD API—Example 1: Test Routine**

```
ZZTEST ;Test routine
EXAMP1 ;Create a Regular "C" compound index
        S MYARRAY("FILE")=16000
        S MYARRAY("NAME")="C"
        S MYARRAY("USE")="LS"
        S MYARRAY("TYPE")="R"
        S MYARRAY("SHORT DESCR")="Regular compound index on fields 1 and
        2."
        S MYARRAY("DESCR",1)="This cross-reference contains as subscripts
        the values of"
        S MYARRAY("DESCR",2)="fields #1 and #2 in the file #16000."
        S MYARRAY("VAL",1)=1
        S MYARRAY("VAL",1,"SUBSCRIPT")=1
        S MYARRAY("VAL",2)=2
        S MYARRAY("VAL",2,"SUBSCRIPT")=2
        D CREIXN^DDMOD(.MYARRAY,"SW",.MYRESULT,"MYOUT")
        Q
```

**Figure 106: CREIXN^DDMOD API—Example 1: Input and Output**

```
>D EXAMP1^ZZTEST

Cross-reference definition created.
Building index ...

Compiling ZZTEST Input Template of File 16000...
`ZZCT' ROUTINE FILED.
`ZZCT1' ROUTINE FILED.

Compiling Cross-Reference(s) 16000 of File 16000.

...SORRY, HOLD ON...

`ZZCR1' ROUTINE FILED.
`ZZCR' ROUTINE FILED.

>ZW MYRESULT
MYRESULT=214^C

>ZW MYOUT
MYOUT("DIEZ",125)=ZZTEST^16000^ZZCT
MYOUT("DIKZ")=ZZCR
```

The MYRESULT output variable indicates that the “C” index definition was created with the internal entry number of 214 in the INDEX (#.11) file.

The MYOUT output array indicates that one or both of the fields in the index are also used in the compiled input template ZZTEST (#125), and that input template was recompiled. Cross-references on (fictitious) File #16000 were also recompiled into the ZZCR namespaced routines.

[Figure 107](#) is an example of a data dictionary listing of the index that was created:

**Figure 107: CREIXN^DDMOD API—Example 1: Sample Data Dictionary Listing of the Created Index**

```
C (#214)    RECORD    REGULAR    IR    LOOKUP & SORTING

Short Descr: Regular compound index on fields 1 and 2.
Description: This cross-reference contains as subscripts the values of
              fields #1 and #2 in the file #16000.

Set Logic:  S ^DIZ(16000,"C",X(1),X(2),DA)=""
Kill Logic: K ^DIZ(16000,"C",X(1),X(2),DA)
Whole Kill: K ^DIZ(16000,"C")

X(1):  AFIELD  (16000,1)  (Subscr 1)  (forwards)
X(2):  BFIELD  (16000,2)  (Subscr 2)  (forwards)
```

### 3.5.1.1.2 Example 2

In this example (Figure 108 and Figure 109), a New-Style “AC” index is created. It is a whole-file index based on fields in Subfile #16000.02, but stored one level up, at the Subfile #16000.01 level. (One level above #16000.01 is the top-level of the file, which has file number 16000.) The “AC” index contains two field-type cross-reference values, Fields #.01 and #1, neither of which are used as subscripts in the index. The third cross-reference value is computed and is the only subscript in the index. This computed subscript consists of the first five characters of Field #.01, which is the first cross-reference value, concatenated with Field #1, the second cross-reference value.

The S flag in the CREIXN^DDMOD call indicates that the index should be built after its definition is created.

**Figure 108: CREIXN^DDMOD API—Example 2: Test Routine**

```
ZZTEST      ;Test routine
EXAMP2      ;Create a whole-file "AC" index
            S MYARRAY("FILE")=16000.01 ;the file on which the index resides
            S MYARRAY("ROOT FILE")=16000.02 ;the file in which the fields in the
            index are defined.
            S MYARRAY("NAME")="AC"
            S MYARRAY("USE")="SORTING ONLY"
            S MYARRAY("TYPE")="REGULAR"
            S MYARRAY("SHORT DESCR")="Whole-file regular 'AC' index."
            S MYARRAY("DESCR",1)="This index stores at the 16000.01 file level
            values from fields"
            S MYARRAY("DESCR",2)="in subfile #16000.02."
            ;
            ;Cross-reference values 1 and 2 are field values
            ;defined so that cross-reference value 3 can
            ;reference their values via X(1) and X(2).
            S MYARRAY("VAL",1)=.01
            S MYARRAY("VAL",2)=1
            ;
            ;Cross-reference value 3 is a computed value
            ;based on cross-reference values 1 (field #.01)
            ;and 2 (field #1). It is used as a subscript in
            ;the index.
            S MYARRAY("VAL",3)="S X=$E(X(1),1,5)_X(2)"
            S MYARRAY("VAL",3,"SUBSCRIPT")=1
            ;
            D CREIXN^DDMOD(.MYARRAY,"S",.MYRESULT)
            Q
```

**Figure 109: CREIXN^DDMOD API—Example 2: Input and Output**

```
>D EXAMP2^ZZTEST

>ZW MYRESULT
MYRESULT=216^AC
```

The MYRESULT output variable indicates that the “AC” index definition was created with the internal entry number of 216 in the INDEX (#.11) file.

The resulting data dictionary listing of the new index definition is shown in [Figure 110](#):

**Figure 110: CREIXN^DDMOD API—Example 2: Sample Data Dictionary Listing of the Created Index**

```

AC (#216)      RECORD      REGULAR      IR      SORTING ONLY      WHOLE FILE (#16000.01)

Short Descr:  Whole-file regular 'AC' index.
Description:  This index stores at the 16000.01 file level values from
              fields in subfile #16000.02.

Set Logic:    S ^DIZ(16000,DA(2),100,"AC",X(3),DA(1),DA)="
Kill Logic:   K ^DIZ(16000,DA(2),100,"AC",X(3),DA(1),DA)
Whole Kill:   K ^DIZ(16000,DA(2),100,"AC")

X(1):  MULTIPLE NAME (16000.02,.01)
X(2):  CODE (16000.02,1)
X(3):  Computed Code: S X=$E(X(1),1,5)_X(2)
              (Subscr 1) (forwards)

```

### 3.5.1.1.3 Example 3

In this example ([Figure 111](#) and [Figure 112](#)), a New-Style MUMPS cross-reference is created with the name “AD”. It has one cross-reference value, Field #1 in File #16000. Whenever the value of Field #1 is deleted, the MUMPS cross-reference files today’s date into the DATE DELETED (#2) field. When the value of Field #1 changes from null to some *non-null* value, the MUMPS cross-reference deletes the contents of DATE DELETED. Since this cross-reference should *not* be executed during a reindexing operation or during a KIDS install, the Activity is set to null.

**Figure 111: CREIXN^DDMOD API—Example 3: Test Routine**

```

ZZTEST ;Test routine
EXAMP3 ;Create MUMPS cross-reference
S MYARRAY("FILE")=16012
S MYARRAY("NAME")="AD"
S MYARRAY("USE")="ACTION"
S MYARRAY("TYPE")="MUMPS"
S MYARRAY("ACTIVITY")=""
S MYARRAY("SHORT DESCR")="This MUMPS cross-reference updates field #2 when field
#1 is deleted."
S MYARRAY("DESCR",1)="The kill logic of this cross-reference calls the Filer to
stuff today's"
S MYARRAY("DESCR",2)="date into field #2 whenever the value of field #1 is
deleted."
S MYARRAY("DESCR",3)=""
S MYARRAY("DESCR",4)="The set logic calls the Filer to delete the contents of
field #2"
S MYARRAY("DESCR",5)="when a value is placed into field #1."
;
S MYARRAY("SET")="N ZZFDA,ZZMSG,DIERR S ZZFDA(16012,DA_"",",",2)=""" D
FILE^DIE("","",ZZFDA",ZZMSG")"
S MYARRAY("SET CONDITION")="S X=X1(1)="""
S MYARRAY("KILL")="N ZZFDA,ZZMSG,DIERR S ZZFDA(16012,DA_"",",",2)=DT D
FILE^DIE("","",ZZFDA",ZZMSG")"
S MYARRAY("KILL CONDITION")="S X=X2(1)="""
;
S MYARRAY("VAL",1)=1
D CREIXN^DDMOD(.MYARRAY,"W",.MYRESULT)
Q

```



**Figure 112: CREIXN^DDMOD API—Example 3: Input and Output**

```
>D EXAMP3^ZZTEST
Cross-reference definition created.

>ZW MYRESULT
MYRESULT=220^AD
```

The MYRESULT output variable indicates that the “AD” cross-reference definition was created with the internal entry number of 220 in the INDEX (#.11) file.

The new cross-reference definition is shown in [Figure 113](#):

**Figure 113: CREIXN^DDMOD API—Example 3: Sample Data Dictionary Listing of the Created Index**

```
AD (#220)    FIELD    MUMPS    ACTION

Short Descr: This MUMPS cross-reference updates field #2 when field #1 is
              deleted.
Description:  The kill logic of this cross-reference calls the Filer to
              stuff today's date into field #2 whenever the value of field
              #1 is deleted.

              The set logic calls the Filer to delete the contents of field
              #2 when a value is placed into field #1.

Set Logic:   N ZZFDA,ZZMSG,DIERR S ZZFDA(16012,DA_",",2)=" D FILE^DIE("",
              "ZZFDA","ZZMSG")
Set Cond:    S X=X1(1)=""
Kill Logic:  N ZZFDA,ZZMSG,DIERR S ZZFDA(16012,DA_",",2)=DT D FILE^DIE("",
              "ZZFDA","ZZMSG")
Kill Cond:   S X=X2(1)=""

X(1): MYFIELD (16012,1)
```

### 3.5.1.2 Error Codes Returned

[Table 38](#) lists the possible error codes returned with the CREIXN^DDMOD API:

**Table 38: CREIXN^DDMOD API—Error Codes Returned**

Code	Description
<a href="#">202</a>	The specified parameter is missing or invalid.
<a href="#">401</a>	The file does not exist.
<a href="#">402</a>	The global root is missing or invalid.
<a href="#">406</a>	The file has no .01 definition.
<a href="#">407</a>	A word-processing field is not a file.
<a href="#">502</a>	The field has a corrupted definition.

The New-Style Cross-Reference Creator may also return any error returned by:

- [CHK^DIE](#)
- [UPDATE^DIE](#)
- [WP^DIE](#)

### 3.5.2 DELIX^DDMOD(): Traditional Cross-reference Delete

The DELIX^DDMOD API deletes a traditional cross-reference definition from the data dictionary of a file. Optionally, it deletes the data in the index or executes the **KILL** logic for all entries in the file. Compiled INPUT templates that contain the field on which the cross-reference is defined are recompiled. If cross-references on the file are compiled, they are recompiled.

DELIX^DDMOD can be used as the pre-install or post-install routine of a Kernel Installation and Distribution System (KIDS) Build, for example, to delete a traditional cross-reference from the installing site.



**REF:** For information on the call to delete a New-Style index definition, see DELIXN^DDMOD.

#### Format

```
DELIX^DDMOD(file,field,cross_ref[,flags][,output_root][,msg_root])
```

#### Input Parameters

- file: (Required) File or subfile number.
- field: (Required) Field number.
- cross\_ref: (Required) Cross-reference number. Traditional cross-references are defined in the data dictionary under **^DD(file#,field#,1,cross-reference number)**.
- flags: (Optional) Flags to control processing. The possible values are:
- **K**—For Regular, KWIC, Mnemonic, and Soundex-type cross-references, delete the data in the index. For MUMPS and Trigger-type cross-references, execute the **KILL** logic of the cross-reference for all entries in the file. For Bulletin-type cross-references, the **K** flag is ignored; the **KILL** logic for Bulletin-type cross-references is never executed by this procedure.
  - **W**—**WRITE** messages to the current device as the index is deleted and cross-references and INPUT templates are recompiled.
- output\_root: (Optional) The name of the array that should receive information about INPUT templates and cross-references that may have been recompiled and a flag to indicate that the deletion was audited in the DD AUDIT (#.6) file.



**REF:** See the “[Output Parameters](#)” section.

This *must* be a closed root, either local or global.

- msg\_root: (Optional) The name of the array that should receive any error messages. This *must* be a closed root, either local or global. If *not* passed, errors are returned descendent from **^TMP(“DIERR”,\$J)**.

## Output Parameters

output\_root:

See the [output\\_root](#) parameter under “Input Parameters.”

If the field on which the deleted cross-reference was defined is used in any compiled INPUT t templates, those INPUT templates are recompiled. Information about the recompiled INPUT templates is stored descendant from OUTPUT\_ROOT(“DIEZ”):

OUTPUT\_ROOT(“DIEZ”, INPUT template #) = INPUT template name ^  
file # ^compiled routine name

If cross-references for the file are compiled, they are recompiled, and the compiled routine name is stored in OUTPUT\_ROOT(“DIKZ”):

OUTPUT\_ROOT(“DIKZ”) = compiled routine name

If the data dictionary for the file is audited, an entry is made in the DD AUDIT (#.6) file and OUTPUT\_ROOT(“DDAUD”) is set to 1:

OUTPUT\_ROOT(“DDAUD”) = 1

### 3.5.2.1 Examples

#### 3.5.2.1.1 Example 1

In this example ([Figure 114](#)), regular cross-reference #4 (the “C” index), defined on Field #12 in (fictitious) File #16200, is deleted. The **K** flag indicates that the entire ^DIZ(16200,”C”) index should be removed from the file.

**Figure 114: DELIX^DDMOD API—Example 1: Input and Output**

```
>D DELIX^DDMOD(16200,12,4,"K","MYOUT")
>ZW MYOUT
MYOUT("DDAUD")=1
MYOUT("DIEZ",100)=ZZTEST EDIT^16200^ZZIT
MYOUT("DIKZ")=ZZCR
```

The MYOUT output array indicates that the deletion was recorded in the DD AUDIT (#.6) file. The INPUT template ZZTEST EDIT (#100) was recompiled into the ZZIT namespaced routines, because Field #12 is used in that template. Cross-references on (fictitious) File #16200 are recompiled under the ZZCR namespace.

### 3.5.2.1.2 Example 2

In this example ([Figure 115](#)), the whole-file regular cross-reference #7 (the “N” index), defined on Field #15 within Subfile #16200.075, is deleted:

- The **K** flag indicates that the entire ^DIZ(16200,“N”) index should be removed.
- The **W** flag indicates that messages should be printed to the current device.

**Figure 115: DELIX^DDMOD API—Example 2: Input and Output**

```
>D DELIX(16200.075,15,7,"KW'
Removing index ...
Deleting cross-reference definition ...

Compiling ZZ TEST CR Input Template of File 16200...
'ZZIT1' ROUTINE FILED..
'ZZIT' ROUTINE FILED...
'ZZIT2' ROUTINE FILED.

Compiling Cross-Reference(s) 16200 of File 16200.

...SORRY, HOLD ON...

'ZZCR1' ROUTINE FILED.
'ZZCR2' ROUTINE FILED.
'ZZCR3' ROUTINE FILED.
'ZZCR4' ROUTINE FILED.
'ZZCR5' ROUTINE FILED.
'ZZCR' ROUTINE FILED.
```

### 3.5.2.2 Error Codes Returned

[Table 39](#) lists the possible error codes returned with the DELIX^DDMOD API.

**Table 39: DELIX^DDMOD API—Error Codes Returned**

Code	Description
<a href="#">202</a>	The specified parameter is missing or invalid.
<a href="#">301</a>	The passed flags are incorrect.
<a href="#">401</a>	The file does not exist.
<a href="#">406</a>	The file has no .01 definition.
<a href="#">407</a>	A word-processing field is not a file.
<a href="#">501</a>	The file does not contain the specified field.

### 3.5.3 DELIXN^DDMOD(): New-Style Index Delete

The DELIXN^DDMOD API deletes a New-Style index definition from the INDEX (#.11) file. Optionally, it deletes the data in the index or executes the **KILL** logic for all entries in the file. Compiled INPUT templates that contain one or more of the fields defined in the index are recompiled. If cross-references on the file are compiled, they are recompiled.

DELIXN^DDMOD can be used is the pre-install or post-install routine of a Kernel Installation and Distribution System (KIDS) build, (e.g., to delete a New-Style index from the installing site).



**REF:** For information on the call to delete a traditional cross-reference definition, see the [DELIX^DDMOD\(\): Traditional Cross-reference Delete](#) API.

#### Format

```
DELIXN^DDMOD(file,index[,flags][,output_root][,msg_root])
```

#### Input Parameters

file: (Required) File or subfile number. For whole-file indexes, this is the number of the file at the upper level where the data in the index resides.

index: (Required) Index name.

flags: (Optional) Flags to control processing. The possible values are:

- **K**—For Regular indexes, delete the data in the index. For MUMPS (M) indexes, execute the **KILL** logic for all entries in the file.
- **W**—WRITE messages to the current device as the index is deleted and cross-references and INPUT templates are recompiled.

output\_root: (Optional) The name of the array that should receive information about INPUT templates and cross-references that may have been recompiled.



**REF:** See the “[Output Parameters](#)” section.

This *must* be a closed root, either local or global.

msg\_root: (Optional) The name of the array that should receive any error messages. This *must* be a closed root, either local or global. If *not* passed, errors are returned descendent from ^TMP(“DIERR”,\$J).

#### Output Parameters

output\_root: See [output\\_root](#) under “Input Parameters.”

If a field used in the index is used in any compiled INPUT templates, those INPUT templates are recompiled. Information about the recompiled INPUT templates is stored descendant from **OUTPUT\_ROOT(“DIEZ”)**:

```
OUTPUT_ROOT(“DIEZ”, INPUT template #) = INPUT template name ^  
file # ^ compiled routine name
```

If cross-references for the file are compiled, they are recompiled, and the compiled routine name is stored in **OUTPUT\_ROOT("DIKZ")**:

```
OUTPUT_ROOT("DIKZ") = compiled routine name
```

### 3.5.3.1 Examples

#### 3.5.3.1.1 Example 1

In this example (Figure 116), the New-Style "G" index defined on (fictitious) File #16200 is deleted. The **K** flag indicates that the entire ^DIZ(16200,"G") index should be removed from the file.

**Figure 116: DELIXN^DDMOD API—Example 1: Input and Output**

```
>D DELIXN^DDMOD(16200,"G","K","MYOUT")  
  
>ZW MYOUT  
MYOUT("DIEZ",94)=ZZ TEST^16200^ZZIT  
MYOUT("DIEZ",100)=ZZ TEST A^16200^ZZITA  
MYOUT("DIKZ")=ZZCR
```

The MYOUT output array indicates that a field or fields used in the deleted index are also used in the compiled INPUT templates ZZ TEST (#94) and ZZ TEST 2 (#100). Those two INPUT templates were recompiled. Cross-references on (fictitious) File #16200 were also recompiled under the ZZCR namespace.

### 3.5.3.1.2 Example 2

In this example ([Figure 117](#)), the whole-file regular index (the “J” index) is deleted. The fields in the index come from fields in a Multiple, Subfile #16200.075, but the whole-file index resides at the top-level of (fictitious) File #16200:

- The **K** flag indicates that the entire ^DIZ(16200,”J”) index should be removed.
- The **W** flag indicates that messages should be printed to the current device.

**Figure 117: DELIXN^DDMOD API—Example 2: Input and Output**

```
>D DELIXN^DDMOD(16200,"J","KW","MYOUT")

Removing index ...
Deleting index definition ...

Compiling ZZ TEST Input Template of File 16200....
'ZZIT' ROUTINE FILED....
'ZZIT1' ROUTINE FILED.

Compiling ZZ TEST A Input Template of File 16200....
'ZZITA' ROUTINE FILED....
'ZZITA' ROUTINE FILED.

Compiling Cross-Reference(s) 16200 of File 16200.

...SORRY, JUST A MOMENT PLEASE...

'ZZCR1' ROUTINE FILED.
'ZZCR2' ROUTINE FILED.
'ZZCR3' ROUTINE FILED.
'ZZCR4' ROUTINE FILED.
'ZZCR5' ROUTINE FILED.
'ZZCR6' ROUTINE FILED.
'ZZCR7' ROUTINE FILED.
'ZZCR8' ROUTINE FILED.
'ZZCR9' ROUTINE FILED.
'ZZCR10' ROUTINE FILED.
'ZZCR' ROUTINE FILED.
```

### 3.5.3.2 Error Codes Returned

[Table 40](#) lists the possible error codes returned with the DELIXN^DDMOD API.

**Table 40: DELIXN^DDMOD API—Error Codes Returned**

Code	Description
<a href="#">202</a>	The specified parameter is missing or invalid.
<a href="#">301</a>	The passed flags are incorrect.

### 3.5.4 FILESEC^DDMOD(): Set File Protection Security Codes

The FILESEC^DDMOD API sets the security access codes for a file. The call allows developers to change only the File Security Codes at a target site without having to transport the entire file. The codes are stored in the following nodes:

- ^DIC(filename,0,"AUDIT")—AUDIT Access
- ^DIC(filename,0,"DD")—DATA DICTIONARY Access
- ^DIC(filename,0,"DEL")—DELETE Access
- ^DIC(filename,0,"LAYGO")—LAYGO Access
- ^DIC(filename,0,"RD")—READ Access
- ^DIC(filename,0,"WR")—WRITE Access

#### Format

```
FILESEC^DDMOD(file,.security_codes[,msg_root])
```

#### Input Parameters

file: (Required) File number. It *cannot* be less than 2.

.security\_codes: (Required) Array of security access codes:

- SECURITY\_CODES("AUDIT") = AUDIT Access
- SECURITY\_CODES("DD") = DATA DICTIONARY Access
- SECURITY\_CODES("DEL") = DELETE Access
- SECURITY\_CODES("LAYGO") = LAYGO Access
- SECURITY\_CODES("RD") = READ Access
- SECURITY\_CODES("WR") = WRITE Access

msg\_root: (Optional) The root of an array into which error messages are returned. If this parameter is *not* included, errors are returned in the default ^TMP("DIERR",\$J) array.

#### Output

None.



### 3.5.4.1 Examples

#### 3.5.4.1.1 Example 1

In this example ([Figure 118](#)), you are going to set all of the File Security Code nodes:

**Figure 118: FILESEC^DDMOD API—Example 1: Input and Output**

```
>D ^%G
. . . . Global ^DIC(16028
          DIC(16028
. . . . ^DIC(16028,0) = ZPATR FILE^16028
. . . . ^DIC(16028,0,"GL") = ^DIZ(16028,
. . . . ^DIC(16028,"%",0) = ^1.005^^0
. . . . Global ^

. . . . S SECURITY("DD")="@
. . . . S SECURITY("RD")=""
. . . . S SECURITY("WR")="A"
. . . . S SECURITY("DEL")="@
. . . . S SECURITY("LAYGO")="@
. . . . S SECURITY("AUDIT")="@
. . . . D FILESEC^DDMOD(16028,.SECURITY)

>D ^%G
. . . . Global ^DIC(16028
. . . . Global ^DIC(16028
          DIC(16028
. . . . ^DIC(16028,0) = ZPATR FILE^16028
. . . . ^DIC(16028,0,"AUDIT") = @
. . . . ^DIC(16028,0,"DD") = @
. . . . ^DIC(16028,0,"DEL") = @
. . . . ^DIC(16028,0,"GL") = ^DIZ(16028,
. . . . ^DIC(16028,0,"LAYGO") = @
. . . . ^DIC(16028,0,"RD") =
. . . . ^DIC(16028,0,"WR") = A
. . . . ^DIC(16028,"%",0) = ^1.005^^0
```

#### 3.5.4.1.2 Example 2

In this example ([Figure 119](#)), you are going to use the results from the previous example ([Figure 118](#)) and change just the Write Access.

**Figure 119: FILESEC^DDMOD API—Example 2: Input and Output**

```
>S SECURITY("WR")="a"
>D FILESEC^DDMOD(16028,.SECURITY)
>D ^%G

Global ^DIC(16028
          DIC(16028
^DIC(16028,0) = ZPATR FILE^16028
^DIC(16028,0,"AUDIT") = @
^DIC(16028,0,"DD") = @
^DIC(16028,0,"DEL") = @
^DIC(16028,0,"GL") = ^DIZ(16028,
^DIC(16028,0,"LAYGO") = @
^DIC(16028,0,"RD") =
^DIC(16028,0,"WR") = a
^DIC(16028,"%",0) = ^1.005^^0
Global ^
```

### 3.5.4.2 Error Codes Returned

[Table 41](#) lists the possible error codes returned with the FILESEC^DDMOD API:

**Table 41: FILESEC^DDMOD API—Error Codes Returned**

Code	Description
<a href="#">401</a>	The file does not exist or the File Number that was passed was less than 2.

### 3.5.5 BLD^DIALOG(): DIALOG Extractor

The BLD^DIALOG API performs the following functions:

1. Extracts a dialogue from a VA FileMan DIALOG (#.84) file entry.
2. Substitutes dialogue parameters into the text if requested.
3. Returns the text in an array.

If the DIALOG (#.84) file entry has a POST MESSAGE ACTION code, this code is executed *after* the message has been built, but *before* quitting.

#### Format

```
BLD^DIALOG(dialog#[, [.]text_param][, [.]output_param][, output_array][, flags])
```

#### Input Parameters

- dialog#:** (Required) Record number from the DIALOG (#.84) file for the text to be returned.
- [.]text\_param:** (Optional) Local array containing the dialogue parameters to substitute into the resulting text. Set the subscript of each node in this array to a dialogue parameter that is in a **|window|** in the referenced DIALOG (#.84) file entry's text. The value of each node should be in external, printable format and is substituted in the **DIALOG** text for that **dialog** parameter.
- If there is only one parameter in the list, you can pass its value in a local variable or as a literal; otherwise, pass it by reference.
- [.]output\_param:** (Optional) This is useful mainly if you are returning error messages as part of an API for other developers to use. Use it to pass dialogue parameters back to the user of your API, such that they can be accessed individually instead of just being embedded in the error text.
- Use only with DIALOG (#.84) file entries of type **Error**. Pass this local array by reference. Subscript each node by the parameter name and set the node to the corresponding parameter value. The parameter values can be in any format (external or internal).
- For example, if you pass **DIPAROUT** by reference and want to pass back standalone values for the “**1**” and “**FILE**” parameters in the output array along with dialogue text, set **DIPAROUT** to:

```
DIPAROUT(1)=TEST FILE  
DIPAROUT("FILE")=662001
```

Dialogue text is returned as expected but, in addition, **dialog** parameter values are returned in:

```
^TMP( "DIERR" , $J , msg# , "PARAM" , 1 )
^TMP( "DIERR" , $J , msg# , "PARAM" , "FILE" )
```



**NOTE:** If you only want to return one parameter, you can pass its value in a local variable or as a literal rather than in an array by reference. However, the subscript for such a parameter in the output array is always **1**.

output\_array:

(Optional) If provided, the text is output in the local or global array named by this parameter. If this parameter is null, output is returned in the **^TMP** global, under the **“DIERR”**, **“DIHELP”**, or **“DIMSG”** subscripts as documented in the DBS [“Contents of Arrays”](#) section.

If you specify **DIR(“A”)** or **DIR(“?”)** as the output array, special handling is provided for populating the output array for use in a call to the Response Reader, [^DIR](#). Text is output in the format needed for input to the Response Reader.



**NOTE:** You are responsible for cleaning up the output array or global before calling the **BLD^DIALOG** API. If the array already exists, **BLD^DIALOG** simply appends its output to the current contents of the output array, under a new message subscript.

flags:

(Optional) Flags to control processing. The possible values are:

- **S**—Suppress the blank line that is normally inserted between discrete blocks of text that are built by separate calls to this routine.
- **F**—Format the local array similar to the default output format of the **^TMP** global, so that you can call the [MSG^DIALOG](#) API to either Write the array to the current device or to a simple local array.

## Output

If the **output\_array** input parameter is *not* passed, **DIALOG(#.84)** file text is returned in **^TMP** under the **“DIERR”**, **“DIHELP”**, or **“DIMSG”** subscripts as documented in the DBS [“Contents of Arrays”](#) section. If the **DIALOG (#.84)** file text is returned in a local array instead, the name of the array and leading subscripts are defined by the name of the array passed to this routine.

In addition to the **DIALOG (#.84)** file text, a local variable is returned. [Table 42](#) lists the local variables:

**Table 42: BLD^DIALOG API—Output Variables Returned**

Variable Name	Returned if DIALOG Type Is:	Variable Value
DIERR	Error	Piece 1: # of discrete error messages returned. Piece 2: Total # of lines of text returned.
DIHELP	Help	Total # of lines of text returned.
DIMSG	General Message	Total # of lines of text returned.



**NOTE:**

- If the variable to be used (**DIHELP**, **DIERR**, or **DIMSG**) already exists before calling the BLD^DIALOG API, the number or numbers already stored in the variable are incremented (*not overwritten*) to reflect the cumulative total over repetitive calls to the BLD^DIALOG API.

The local variable (**DIHELP**, **DIERR**, or **DIMSG**) is *not* set if you ask for text to be built in the special variables **DIR("A")** and **DIR("?")**, used as input to [^DIR](#).

- To add entries to the DIALOG (#.84) file, you *must* use a numberspace assigned by the database administrator (DBA).



**REF:** For more information on the DIALOG (#.84) file, see the "[DIALOG File](#)" section.

### 3.5.5.1 Examples

The DIALOG (#.84) file entry numbers shown in the examples below are for demonstration purposes and are *not* distributed as part of VA FileMan.

#### 3.5.5.1.1 Example 1

In the case of errors, the output looks like the following example ([Figure 120](#)).

**^TMP("DIERR",\$J,error\_number)** is set equal to the IEN from the DIALOG (#.84) file. The actual error text is contained descendent from the **"TEXT"** subscript. If output parameters were passed to the routine, they are returned descendent from the **"PARAM"** subscript, where **"PARAM",0)** contains the total number of output parameters. Finally, there is an entry descendent from **"E"**, where the next subscript is the IEN from the DIALOG (#.84) file, and the final subscript refers to the error number in this output array. This serves as a sort of cross-reference by error code. When errors are generated by a routine called from developers' code, this cross-reference can be used by the developer to quickly check whether a specified error had been generated:

**Figure 120: BLD^DIALOG API—Example 1: Input**

```
DIPAROUT(1)=TEST FILE
DIPAROUT("FILE")=662001

>D BLD^DIALOG(10999,"Myfile",.DIPAROUT)
```

The output looks like [Figure 121](#):

**Figure 121: BLD^DIALOG API—Example 1: Output**

```
DIERR=1^1

^TMP("DIERR",591465626,1) = 10999
^TMP("DIERR",591465626,1,"PARAM",0) = 2
^TMP("DIERR",591465626,1,"PARAM",1) = TEST FILE
^TMP("DIERR",591465626,1,"PARAM","FILE") = 662001
^TMP("DIERR",591465626,1,"TEXT",1) = Entries in file Myfile cannot be edited.
^TMP("DIERR",591465626,"E",10999,1) =
```

### 3.5.5.1.2 Example 2

In this example ([Figure 122](#)), you generate a second error to show how it is appended to the previous error in the ^TMP global:

**Figure 122: BLD^DIALOG API—Example 2: Input**

```
DIPARIN(1)='B'  
DIPARIN("FILE")=662001  
DIPAROUT(1)='B'  
DIPAROUT("FILE")=662001  
  
>D BLD^DIALOG(10202, .DIPARIN, .DIPAROUT)
```

The output looks like [Figure 123](#):

**Figure 123: BLD^DIALOG API—Example 2: Output**

```
DIERR=2^2  
  
^TMP("DIERR",591465626,1) = 10999  
^TMP("DIERR",591465626,1,"PARAM",0) = 2  
^TMP("DIERR",591465626,1,"PARAM",1) = TEST FILE  
^TMP("DIERR",591465626,1,"PARAM","FILE") = 662001  
^TMP("DIERR",591465626,1,"TEXT",1) = Entries in file Myfile cannot be edited.  
^TMP("DIERR",591465626,2) = 10202  
^TMP("DIERR",591465626,2,"PARAM",0) = 2  
^TMP("DIERR",591465626,2,"PARAM",1) = 'B'  
^TMP("DIERR",591465626,2,"PARAM","FILE") = 662001  
^TMP("DIERR",591465626,2,"TEXT",1) = There is no 'B' index for File #662001.  
^TMP("DIERR",591465626,"E",10999,1) =  
^TMP("DIERR",591465626,"E",10202,2) =
```

### 3.5.5.1.3 Example 3

In this example ([Figure 124](#)), you build the same error message as in [Example 1](#), but this time you put the output into a local array. Notice that you do *not* send a flag in the **flags** parameter for this call, so only the error text is returned. This would ordinarily be done when the developer planned to process the output from their own routine.

**Figure 124: BLD^DIALOG API—Example 3: Input**

```
>D BLD^DIALOG(10999,"Myfile",.DIPAROUT,"MYARRAY")
```

The output looks like [Figure 125](#):

**Figure 125: BLD^DIALOG API—Example 3: Output**

```
DIERR=1^1  
  
MYARRAY(1)=Entries in file Myfile cannot be edited.
```

### 3.5.5.1.4 Example 4

In this example ([Figure 126](#)), you build the same error message as in [Example 3](#), again sending the output to a local array. This time, however, you pass the **F** flag in the **flags** parameter; so that all of the error information is returned in a format similar to that of the **^TMP** global, but without the **\$J** subscript. In this format, the developer could then call the [MSG^DIALOG](#) API to either write the array to the current device or to copy the text into a simple array. This might, for example, be done when the developer wanted to examine the error messages returned and **KILL** some of them before having VA FileMan write the remaining messages.

Figure 126; BLD^DIALOG API—Example 4: Input

```
>D BLD^DIALOG(10999,"Myfile",.DIPAROUT,"MYARRAY","F")
```

The output looks like [Figure 127](#):

Figure 127: BLD^DIALOG API—Example 4: Output

```
DIERR=1^1

MYARRAY("DIERR",1)=10999
MYARRAY("DIERR",1,"PARAM",0)=2
MYARRAY("DIERR",1,"PARAM",1)=TEST FILE
MYARRAY("DIERR",1,"PARAM","FILE")=662001
MYARRAY("DIERR",1,"TEXT",1)=Entries in file Myfile cannot be      edited.
MYARRAY("DIERR","E",10999,1)=
```

### 3.5.5.1.5 Example 5

In this example ([Figure 128](#)), you build a help message with a single input parameter. Notice that the only output is the **DIHELP** variable and the text. Similarly, other types of messages only return the **DIMSG** variable and the text.

Figure 128: BLD^DIALOG API—Example 5: Input

```
>D BLD^DIALOG(10335,"PRINT")
```

The output looks like [Figure 129](#):

Figure 129: BLD^DIALOG API—Example 5: Output

```
DIHELP=4

^TMP("DIHELP",591469242,1) = This number is used to determine how large to
make the generated
^TMP("DIHELP",591469242,2) = compiled PRINT routines. The size must be a number
greater
^TMP("DIHELP",591469242,3) = than 2400, the larger the better, up to the maximum
routine size for
^TMP("DIHELP",591469242,4) = your operating system.
```

### 3.5.5.1.6 Example 6

In this example ([Figure 130](#)), you build the same help message as [Example 5](#) but put it into a local array.

**Figure 130: BLD^DIALOG API—Example 6: Input**

```
>D BLD^DIALOG(10335,"PRINT","", "MYARRAY")
```

The output looks like [Figure 131](#):

**Figure 131: BLD^DIALOG API—Example 6: Output**

```
DIHELP=4  
  
MYARRAY(1)=This number is used to determine how large to make the generated  
MYARRAY(2)=compiled PRINT routines. The size must be a number greater  
MYARRAY(3)=than 2400, the larger the better, up to the maximum routine size for  
MYARRAY(4)=your operating system.
```

### 3.5.5.1.7 Example 7

In this example ([Figure 132](#)), you build the same help message as in [Example 6](#) but put it into the special array **DIR("?")**. Note that for the special local variables used for calls to the VA FileMan Response Reader, **^DIR**, this call puts the text into the format that the Response Reader expects. It does *not* set the **DIMSG**, **DIHELP**, or **DIERR** variables.

**Figure 132: BLD^DIALOG API—Example 7: Input**

```
>D BLD^DIALOG(10335,"PRINT","", "DIR("?")")
```

The output looks like [Figure 133](#):

**Figure 133: BLD^DIALOG API—Example 7: Output**

```
DIR("?")=your operating system.  
DIR("?",1)=This number is used to determine how large to make the generated  
DIR("?",2)=compiled PRINT routines. The size must be a number greater  
DIR("?",3)=than 2400, the larger the better, up to the maximum routine size for
```

## 3.5.5.2 Error Codes Returned

None.

## 3.5.6 \$\$EZBLD^DIALOG(): DIALOG Extractor (Single Line)

The \$\$EZBLD^DIALOG extrinsic function returns the first line of text from an entry in the DIALOG (#.84) file. It can be used when the text entry is only one line and when the output does *not* need to be put into an array. For example, use it to extract a single word or short phrase to use as a text parameter to embed into another DIALOG (#.84) file entry. If the DIALOG (#.84) file entry has a POST MESSAGE ACTION code, this code is executed *after* the message has been built but *before* quitting.

### Format

```
$$EZBLD^DIALOG(dialog#[, [. ]text_param])
```

### Input Parameters

**dialog#:** (Required) Record number from the DIALOG (#.84) file for the text to be returned.

**[.]text\_param:** (Optional) Name of local array containing the parameter list for those parameters that are to be incorporated into the resulting text. These parameters should be in external, printable format. If there is only one parameter in the list, it can be passed in a local variable or as a literal.

### Output

This extrinsic function returns the first line of text from a DIALOG (#.84) file entry. No output variables are returned.



**NOTE:** To add entries to the DIALOG (#.84) file, you *must* use a numberspace assigned by the database administrator (DBA).



**REF:** For more information on the DIALOG (#.84) file, see the “[DIALOG File](#)” section.

### 3.5.6.1 Examples

#### 3.5.6.1.1 Example 1

To write a single line of text with no parameters, do the following:

**Figure 134: \$\$EZBLD^DIALOG API—Example 1: Input and Output**

```
>W $$EZBLD^DIALOG(110)
The record is currently locked.
```

#### 3.5.6.1.2 Example 2

To write a single line of text with a single parameter passed as a literal, do the following:

**Figure 135: \$\$EZBLD^DIALOG API—Example 2: Input and Output**

```
>W $$EZBLD^DIALOG(201,"PARAM")
The input variable PARAM is missing or invalid.
```



### 3.5.6.1.3 Example 3

To write a single line of text with parameters in an input array, do the following:

Figure 136: \$\$EZBLD^DIALOG API—Example 3: Input and Output

```
>S TESTPAR(1)="PAR2"  
>W $$EZBLD^DIALOG(201,.TESTPAR)  
The input variable PAR2 is missing or invalid.
```

### 3.5.6.2 Error Codes Returned

None.

## 3.5.7 MSG^DIALOG(): Output Generator

The MSG^DIALOG API takes text from one of the VA FileMan dialogue arrays (for errors, help text, or other text) or from a similarly structured local array, writes it and, moves it into a simple local array.

The subscripting of these arrays tells the developer whether the dialogue is:

- A “Help” message.
- An “Error” message.
- Other dialogue, such as a prompt.

Different combinations of these messages can be returned from the DBS calls. In addition, error messages are returned whenever an error occurs, either in the way the call was made or in attempting to interact with the database.

With the DBS calls, it becomes the job of the developer to display dialogue to the end-user as needed, perhaps in a Graphical User Interface (GUI) box or in the bottom portion of a screen-oriented form. The developer can also save error messages in a file.

The MSG^DIALOG API is designed to make it easier for the developer to use the dialogue arrays. The developer can use the MSG^DIALOG API to do simple formatting of the dialogue and to either write dialogue to the current device or to move the dialogue to a simple local array for further processing.

### Format

```
MSG^DIALOG([flags][, .output_array][, text_width][, left_margin][, input_root])
```

### Input Parameters

flags: (Optional) Flags to control processing. If none of the text-type flags (**E**, **H**, or **M**) is entered, the routine behaves as if **E** were entered. If no flags are entered, it behaves as if the **flags** contained **WE**. The possible values are:

- **A**—Local Array specified by the second parameter receives the text.
- **W**—Writes the text to the current device.
- **S**—Saves the ^TMP or other designated input array (does *not* **KILL** the array).
- **E**—Error array text is processed.
- **H**—Help array text is processed.
- **M**—Message array text (other text) is processed.

- **B**—Blank lines are suppressed between error messages.
- **T**—Return **Total** number of lines in the top-level node of the local array specified by the second parameter.

`.output_array:` (Optional) This parameter contains the name of the local array to which the text is to be written. If **flags** contains an **A**, this parameter *must* be sent; otherwise, the parameter is ignored.



**NOTE:** The output array is **KILLED** *before* the text is added, *not* appended to what is already there.

`text_width:` (Optional) Maximum line length for formatting text. If specified, the text is broken into lines of this length when writing to the current device or when moving the text to the **output\_array**. Lines are *not* “joined” to fill out to this width.

If you do *not* specify **text\_width**:

- Text that is displayed on the current device is formatted to a line length of **IOM-5** if **IOM** is defined; otherwise, **75** characters.



**NOTE:** **IOM** is the right margin, and it is a Kernel variable defined by a call to the Device Handler, `^%ZIS`.

- Text written to an **output\_array** is *not* reformatted.

`left_margin:` (Optional) Left margin for writing text. If sent, the text is lined up in a column starting at this column number; otherwise, the text is lined up with the left margin (column **0**). This parameter has no effect on text sent to an array (**A** flag).

`input_root:` (Optional) Closed root of local input array in which text resides. If the text resides in a local array, this parameter *must* be sent. The last *non*-variable subscript of the local array *must* describe the type of text it contains, as the **^TMP** global normally does:

- “**DIERR**”—For errors.
- “**DIHELP**”—For help text.
- “**DIMSG**”—F or other text.

## Output

If **W** is passed in the **flags** parameter, the text is written to the current device. If **A** is passed in the **flags** parameter, the text is written to the local array whose name is specified in the second parameter. The format of that array is:

**ARRAY:** Total number of lines (only returned if the **T** flag is passed in the **flags** parameter).

**ARRAY(*n*):** A line of formatted text (*n* = sequential integer starting with **1**).

If the **flags** parameter does *not* contain **S**, then the input array and associated local variables (**DIMSG**, **DIHELP**, and **DIERR**) are **KILLED**.



**NOTE:** To add entries to the DIALOG (#.84) file, you *must* use a numberspace assigned by the Database Administrator.

**REF:** For more information on the DIALOG (#.84) file, see the “[DIALOG File](#)” section.

### 3.5.7.1 Examples

#### 3.5.7.1.1 Example 1

In this first example ([Figure 137](#)), you want to write the error text to the current device and **KILL** the input array. Notice that because no **flags** are sent to the call, the default **flags** for Write Error message (**WE**) are assumed. Thus, the call writes the single error message “The record is currently locked,” from the “**DIERR**” portion of the ^TMP global. It also **KILLS** ^TMP(“**DIERR**”,**\$J**) and the local variable **DIERR** as follows ([Figure 137](#)):

**Figure 137: MSG^DIALOG API—Example 1: “DIERR” Portion of the ^TMP Global**

```
^TMP("DIERR",698526778,1) = 110
^TMP("DIERR",698526778,1,"TEXT",1) = The record is currently locked.
^TMP("DIERR",698526778,"E",110,1) =

^TMP("DIHELP",698526778,1) = This number is used to determine how large to
make the generated
^TMP("DIHELP",698526778,2) = compiled PRINT TEMPLATE routines. The size must be a
number greater
^TMP("DIHELP",698526778,3) = than 2400, the larger the better, up to the maximum
routine size for
^TMP("DIHELP",698526778,4) = your operating system.

^TMP("DIMSG",698526778,1) = Records from list on ZZMYARRAY SEARCH template.
```

Then, write the error text to the current device and **KILL** the input array as shown in [Figure 138](#):

**Figure 138: MSG^DIALOG API—Example 1: Input and Output**

```
>D MSG^DIALOG()
The record is currently locked.
```

#### 3.5.7.1.2 Example 2

In this example ([Figure 139](#) and [Figure 140](#)), you want to write the help text from the “**DIHELP**” subscripted portion of the ^TMP global, both to the current device and to the local “**MYARRAY**” array. In addition, you want to format each line to 50 as follows ([Figure 139](#)):

**Figure 139: MSG^DIALOG API—Example 2: Input**

```
>D MSG^DIALOG("HAW",.MYARRAY,50,5)
```

This number is used to determine how large to make the generated compiled PRINT template routines. The size *must* be a number greater than **2400**, the larger the better, up to the maximum routine size for your operating system.

**Figure 140: MSG^DIALOG API—Example 2: Output**

```
>ZW MYARRAY
MYARRAY(1)=This number is used to determine how large to
MYARRAY(2)=make the generated
MYARRAY(3)=compiled PRINT TEMPLATE routines. The size must
MYARRAY(4)=be a number greater
MYARRAY(5)=than 2400, the larger the better, up to the
MYARRAY(6)=maximum routine size for
MYARRAY(7)=your operating system.
```

### 3.5.7.1.3 Example 3

In the third example ([Figure 141](#)), help text was returned from a DBS call in a local array. This was done because the developer specified to the DBS call that dialogue was to be returned in its own local array rather than in the ^TMP global. Suppose the local array looks like this ([Figure 141](#)):

**Figure 141: MSG^DIALOG API—Example 3: Sample Local Array with Help Text Returned**

```
MYHELP("DIHELP",1)=This number is used to determine how large to make the
generated
MYHELP("DIHELP",2)=compiled PRINT TEMPLATE routines. The size must be a number
greater
MYHELP("DIHELP",3)=than 2400, the larger the better, up to the maximum routine size
for
MYHELP("DIHELP",4)=your operating system.
```

If the developer wishes to write the text to the current device and to preserve the “MYHELP” local array, the call and the results look like this ([Figure 142](#)):

**Figure 142: MSG^DIALOG API—Example 3: Input**

```
>D MSG^DIALOG("WSH","","","MYHELP")
```

This number is used to determine how large to make the generated compiled PRINT template routines. The size *must* be a number greater than **2400**, the larger the better, up to the maximum routine size for your operating system.

### 3.5.7.2 Error Codes Returned

None.

### 3.5.8 FIND^DIC(): Finder

The FIND^DIC API (aka Finder) finds records in a file based on input values. The caller *must* specify:

- File number
- Input values to be used for the lookup

The caller can also specify:

- Indexes to be used in the search
- Data to output
- Number of records to retrieve
- Screening logic

By default, the Finder returns the IEN and the .01 field of the entries along with all identifiers. The developer can override the default output and return other information for the entries.

This call was designed as a *non*-interactive lookup, to find entries that are at least a partial match to the lookup values input to the call. This procedure *cannot* file data or add new records.



**NOTE:** The Finder does *not* honor the Special Lookup or Post-Lookup Action nodes defined in the data dictionary for a file.



**NOTE:** The VA FileMan Database Server (DBS) APIs typically work like their VA FileMan Classic counterparts. However, the DBS APIs listed below *do not* perform numeric lookups the way the classic [^DIC](#) API does:

- FIND^DIC(): Finder
- [\\$\\$FIND1^DIC\(\): Finder \(Single Record\)](#)
- [LIST^DIC\(\): Lister](#)

Rather, these three APIs perform numeric lookups the way [^DIC](#) performs them when the lowercase **n** flag is set.

**REF:** For information on the use of the lowercase **n** flag in conjunction with the **DIC(0)** input variable, see the “[^DIC: Lookup/Add](#)” section in the “[Classic VA FileMan API](#)” section.

#### Format

```
FIND^DIC(file[,iens][,fields][,flags],[.]value[,number][,[.]indexes][,[.]screen][,i  
dentifier][,target_root][,msg_root])
```

#### Input Parameters

**file:** (Required) The number of the file or subfile to search. If this parameter is a subfile, it *must* be accompanied by the **iens** parameter.

**iens:** (Optional) The IENS that identifies the subfile, if the **file** parameter is a subfile number. To identify a subfile, rather than a subfile entry, leave the first comma-piece empty. For example, a value of “,67,” indicates that the subfile within entry #67 should be used. If the **file** parameter is a file number, this parameter should be empty.

Defaults to no subfile.

fields:

(Optional) The fields to return with each entry found. This parameter can be set equal to any of the specifications listed below. The individual specifications should be separated by semicolons (;).



**NOTE:** In most cases, a developer wants to include the @ specifier (described below) to suppress the default output values normally returned by the Finder, and then specify the fields and other elements to return here in the **fields** parameters. This gives the developer full control over exactly what is returned in the output list and makes the call more self-documenting in the developer's code.

- **Field Number**—This specifier causes the Finder to return the value of the field for each record found. For example, specifying **.01** returns the value of the **.01** field. You can specify computed fields. You *cannot* specify word-processing or Multiple fields. By default, fields are returned in external format. The **I suffix** (described below) can be appended to the field number to get the VA FileMan internal format of the field.
- **Computed Expression**—This specifier causes the Finder to return the result of a computed expression.



**REF:** For more information on computed expression syntax, see the “Computed Expressions” section in the *VA FileMan Advanced User Manual*.

- **IX**—This returns for each record, the values from the index on which the lookup match was made. The number of index values returned depends on the number of data value subscripts in the starting lookup index. If a subscript in the index is derived from a field, the external format of that field is returned by default. Otherwise, the value is returned directly as it appears in the index. The **I suffix** (described below) can be appended to **IX** to get the internal index values. The index values are returned in the “**ID**” nodes as described in the “[Output](#)” section below.



**NOTE:** For records located on a mnemonic index entry, the value from the index entry is always returned, rather than its corresponding external field value.

- **FID**—This returns the fields display identifiers (i.e., field identifiers [FID]). By default, the field values are returned in external format. The **I suffix** (described below) can be appended to **FID** to get the VA FileMan internal format of the field identifiers.
- **WID**—This returns the fields WRITE (display only) identifiers (i.e., write identifiers [WID]). The Finder executes each WRITE identifier's M code and copies contents of **^TMP(“DIMSG”, \$J)** to the output. You *must* ensure that the WRITE identifier code issues no direct I/O, but instead calls [EN^DDIOL](#).



**NOTE:** The **I suffix** (described below) *cannot* be used with **WID** and generates an error.

- **E suffix**—You can append an **E** to a field number, the specifier **IX**, or the specifier **FID** to force the fields to be returned in external format. You can use both the **E** and **I suffix** together (e.g., **.01EI**) to return both the internal and external value of the field.
- **I suffix**—You can append an **I** to a field number, the specifier **IX**, or the specifier **FID** to force the fields to be returned in VA FileMan internal format. You can use both the **E** and **I suffix** together (e.g., **.01IE**) to return both the internal and external value of the field.
- **- prefix**—A minus sign (-) prefixing one of the other field specifiers tells the Finder to exclude it from the returned list. This could be used, for example, in combination with the **FID** specifier to exclude one of the identifier fields. For example, if Field #2 was one of the field identifiers for a file, **FID;-2** would output all of the field identifiers except for Field #2.
- **@**—This suppresses all the default values normally returned by the Finder, except for the IEN and any fields and values specified in the **fields** parameter. It is *recommended* that developers *always* use the **@** specifier in Finder calls. Use of the **@** specifier allows the developer to control exactly what is returned in the output.



**REF:** For the default values normally returned by the Finder, see the “[Default Values](#)” section.

### Default Values:

If you *do not* pass anything in the **fields** parameter, the Finder returns:

- IEN
- **.01** field in VA FileMan internal format
- Any field display identifiers (FID)
- Any WRITE (display-only) identifiers (WID)
- Results of executing the Finder’s **identifier** parameter

If you *do* pass a **fields** parameter, the Finder returns (unless you use the **@** field specifier):

- IEN
- **.01** field in VA FileMan internal format
- Fields and values specified by the **fields** parameter
- Any WRITE (display-only) identifiers (WID)
- Results of executing the Finder’s **identifier** parameter

flags:

(Optional) Flags to control processing. This parameter lets the caller adjust the Finder's algorithm. The possible values are:

- **A**—Allow pure numeric input to always be tried as an IEN. Normally, the Finder will only try pure numbers as IENs if:
  - File has a **.001** field.

Or:

- Its **.01** field is *not* numeric and the file has no lookup index.

When this flag is used, records that match other numeric interpretations of the input is found in addition to a record with a matching IEN. For example, a lookup value of “2” would match a record with a lookup field of “2FMPATIENT” as well as a record with an IEN of 2. If more than one match is found, all matching records are returned.



**NOTE:** If the numeric lookup value is preceded by an grave accent character ( ` ), lookup interprets the input as an IEN, and only attempts to match by IEN. The **A** flag is *not* required in this case.

- **B**—**B** index used on lookups to pointed-to files. Without the **B** flag, if there are cross-referenced pointer fields in the list of indexes to use for lookup then:
  - For each cross-referenced pointer field, VA FileMan checks *all* lookup indexes in each pointed-to file for a match to **X** (time-consuming).

And:

- If **X** matches any value in any lookup index (*not* just on the **.01** field) in a pointed-to file and the IEN of the matched entry is in the home file's pointer field cross-reference, VA FileMan considers this a match (perhaps *not* the lookup behavior desired).

The **B** flag prevents this behavior by looking for a match to **X** only in the “**B**” index (**.01** field) of files pointed to by cross-referenced pointer fields. This makes lookups quicker and avoids the risk of VA FileMan matching an entry in the pointed-to file based on something other than the **.01** field.



**REF:** For an explanation of the “Lookup Index” and for more information on use of the **B** flag, see the “[Details and Features](#)” and “[Examples](#)” sections.

- **C**—Use the Classic way of performing lookups on names (i.e., like the classic VA FileMan lookup routine [^DIC](#)). If **C** is passed in the **flags** parameter and, for example, the user enters a lookup value of “Fme,O”, the Finder finds “Fmemployee,One” but also “Fmemployee,Two O.” The Finder takes the first comma piece of the lookup value “Fme”, and looks for partial matches to that. It then takes the second comma piece of the lookup value “O” and looks for partial matches to “O” on the second



or any other piece of the value on the entry being examined. It uses any punctuation or space for a delimiter.

The default, *without* passing **C** in the **flag** parameter, look for partial matches *only* on the second comma-piece; thus, in our example, finding “Fmemployee,One” but not “Femployee,Two O.”. It uses only comma for a delimiter. The old style of comma-piece processing can be quite slow, especially with common names.

- **E**—Errors are ignored. When returning external values without the **E** flag, results are truncated if invalid data (e.g., an incorrect code in a set of codes field) is encountered. An error is produced. The **E** flag suppresses the error and continues the reporting of results. The data value for the entry with invalid data is set to null.

If internal values for a field are being returned, the value stored in the database for the field is returned even if that value is invalid whether or not the **E** flag is set.

To assure that every entry is returned, regardless of the validity of the data, set the **E** flag.

- **K**—Primary **Key** used for starting index. If no index is specified in the **indexes** parameter, this flag causes the Finder to use the Uniqueness index for the Primary Key as the starting index for the search. Without the **K** flag, or if there is no Primary Key for this file (in the KEY [#.31] file), the Finder defaults to the “**B**” index.
- **M**—Multiple index lookup allowed. If more than one index is passed in the **indexes** parameter, all indexes in the list are searched. Otherwise, the **M** flag causes the Finder to search the starting index and all indexes that alphabetically follow it. This includes both indexes from the traditional location in the data dictionary, as well as lookup indexes defined on the INDEX (#.11) file that have an **L** (for LOOKUP) in the “Use” field. The starting index is taken from the **indexes** parameter. If that is null, the search begins with the default starting index (see **K** flag description above).



**NOTE:** If the first index passed in the **indexes** parameter is a compound index, the **M** flag is removed and only that one index is searched.



**REF:** For more information, see “Lookup Index” in the “Details and Features” section.

- **O**—Only find exact matches if possible. The Finder first searches for exact matches on the requested indexes; if any are found, it returns all exact matches to the lookup value. Only if it finds none in the file does it search for partial matches, returning every partial match. For example, if the lookup value is “FMUSER” and the file contains entries “FMUSER” and “FMUSER,ONE”, only the first record is returned. If the first record did *not* exist, the Finder would return “FMUSER,ONE” as a match. If the **flags** parameter does *not* contain an **O**, the Finder returns all matches, partial and exact.

If the lookup is done on a compound index, exact matches *must* be made for every data value subscript in the index in order to consider the entry to be an exact match.

- **P**—Pack output. This flag changes the Finder’s output format to pack the information returned for each record onto a single node per record. A MAP node is introduced to make it easier to locate **di** data elements in the output.



**REF:** For more information, see the “Output,” “Details and Features,” and “Examples” sections.

- **Q**—Quick lookup. If this flag is passed, the Finder assumes the passed-in value is in VA FileMan internal format. The Finder performs NO transforms of the input value, but only tries to find the value in the specified lookup indexes. Therefore, when the **Q** flag is passed, the lookup is much more efficient. If the **flags** parameter does *not* contain a **Q**, the Finder assumes the lookup value is an external or user-entered value and performs all normal transforms as documented below.
- **U**—Unscreened lookup. This flag makes the Finder ignore any whole file screen [stored at ^DD(file#,0,”SCR”)] on the file specified in the **file** parameter.



**NOTE:** Passing this flag does *not* make the Finder ignore the **screen** parameter.

- **X**—EXact matches only. The Finder returns every exact match to the lookup value on the requested indexes. Any partial matches present in the file are ignored, and transforms, such as changing the lookup value to uppercase, are *not* performed. For example, in the scenarios described under the **O** flag, the Finder behaves identically in the first situation, but under the second it returns no matches, since “FMUSER,ONE” is *not* an exact match to “FMUSER”. If both the **O** and **X** flags are passed, the **O** flag is ignored. If the lookup is done on a compound index, exact matches *must* be made for every data value subscript in the index.

[.]value:

(Required) The lookup values. These should be in external format as they would be entered by an end-user, unless the **Q** flag is used. Except for special lookup values listed below, the lookup value is matched to entries on the lookup [indexes](#) specified in the call. If the lookup index is compound, then lookup values can be provided for each of the data value subscripts in the index. In that case, **value** is passed by reference as an array where VALUE(*n*) represents the lookup value to be matched to the *n*th subscript in the index. If only one lookup value is passed in **value**, it is assumed to apply to the first data value subscript in the index.

In addition, certain values generate special behavior by the Finder as follows:

- **Control Characters**—This value always results in no matches. Control characters are *not* permitted in the database.
- **^ (Caret)**—This value always results in no matches. This single character value signifies to VA FileMan that the current activity should be stopped.
- **"" (Empty String)**—On single field indexes, this value always results in no matches. The empty string, used by VA FileMan to designate fields that have no value, *cannot* be found in VA FileMan indexes. However, if the lookup uses a compound index, VALUE(*n*) can be null for any of the lookup values as long as at least one of them is *non-null*. If VALUE(1) is null, it can make the lookup slower. If VALUE(*n*) is null, all *non-null* values for that subscript position are returned.
- **" " (Space Character)**—This value indicates that the Finder should return the current user's previous selection from this file. This corresponds to the **"Spacebar Recall"** feature of VA FileMan's user interface. If VA FileMan has no such previous selection for this user, or if this selection is now prohibited from selection somehow (see discussion of the [screen](#) parameter below), then the Finder returns no matches. The Finder itself *never* preserves its found values for this recall; applications wishing to preserve found values should call the [RECALL^DILFD](#) API. The special lookup characters should appear either in VALUE or in VALUE(1).
- **`-Number (Grave Accent Character followed by a Number)**—This indicates that the Finder should select the entry whose internal entry number equals the number following the grave accent character (`). This corresponds to an equivalent feature of VA FileMan's user interface. If this entry is prohibited from selection, the Finder returns no match. The use of `-number input does *not* require passing **A** in the **flags** parameter. The special lookup characters should appear either in VALUE or in VALUE(1).
- **Numbers**—The Finder tries strictly numeric input as an IEN under any of the following four conditions:
  1. Caller passes **A** in the flags parameter.
  2. File has a **.001** field.
  3. File's **.01** field is *not* numeric and the file has no lookup index.
  4. The indexes parameter contains **#** as one of its index names.

In all cases, the numeric lookup value is expected to be in either **VALUE** or **VALUE(1)**.

In condition 4, if the **#** is the only **INDEX**, and if the lookup value does *not* match an IEN, the lookup fails; otherwise, the Finder continues the search using the other indexes.

In conditions 1, 2 and 3, strictly numeric input differs from `-numeric

input in that whether or *not* a record corresponding to this IEN exists or is selectable, the Finder proceeds with a regular lookup, using the numeric value to find matches in the file's indexes. Even used this way, however, numeric input has the following special restriction: it is *not* used as a lookup value in any indexed pointer or variable pointer field (unless **Q** is passed in the **flags** parameter).

For example, suppose an application performs a Finder call on the (fictitious) EMPLOYEE file, passing a lookup value of 12; that the (fictitious) EMPLOYEE file points to the STATE (#5) file, in which Washington is record number 12; and that the (fictitious) EMPLOYEE file's pointer to the STATE (#5) file is indexed. The application would *not* be able to use the input value of 12 to find every employee who lives in Washington state.

number: (Optional) The maximum number of entries to find. If the Finder actually matches the input to this many entries, it breaks out of its search and returns what it has found so far. In such a situation, there is no way for the Finder to resume its search later where it left off. A value of asterisk (\*) designates all entries.

Defaults to asterisk (\*).

[.]indexes: (Optional) The indexes the Finder should search for matches. This parameter should be set to a list of index names separated by ^ characters. This parameter specifies which indexes to check and the order in which to check them. The caller does *not* need to pass the **M** flag for the **indexes** parameter to work properly. For example, a value of "B^C^ZZALBERT^D" specifies four indexes to check in the order shown.

If the first index passed is a compound index, only that one index can be in the list. Attempting to put more than one index in the list when the first one is compound generates an error. If the first index in the list is a single subscript index, however, compound indexes can follow that one in the list. In that case, the lookup expects only one lookup value and only the first subscript of any compound index is checked for matches.

If no index name, or only one index name, is passed in the **indexes** parameter, and if the **flags** parameter contains an **M**, then the Finder does the search using the starting index, as well as all indexes that follow the starting one alphabetically (unless the starting index is compound; see paragraph above).



**REF:** See also the documentation on the **M** flag.

If the index is *not* specified, the default starting index is "**B**" unless the **flags** parameter contains a **K**, in which case the default is the Uniqueness Index defined for the Primary Key on the file.

Mnemonic cross-references folded into the specified index are included in the output.

When the first subscript of one of the indexes on the file you are searching indexes a pointer or variable pointer, then the Finder searches the pointed-to file for matches to the lookup value. Array entries can be passed in the **indexes**

parameter to control this search on the pointed-to file. Suppose the name of the array is NMSPIX. Then you can set:

```
NMSPIX("PTRIX",from_file#,pointer_field#,to_file#)="^" _delimited_in  
dex_list
```

This array entry allows the user to pass a list of indexes that is used when doing the search on the pointed-to file.

For example, if the (fictitious) File #662001 has a pointer Field #5 to File #200 (NEW PERSON), and you wanted the lookup on Field #5 to find entries in the NEW PERSON (#200) file only by name ("B" index), or by the first letter of the last name concatenated with the last 4 digits of the social security number ("BS5" index), set NMSPIX("PTRIX",662001,5,200)="B^BS5".

[.]screen:

(Optional) **Entry Screen.** The screen to apply to each potential entry in the returned list to decide whether or not to include it. This can be set to any valid M code that sets \$TEST to:

- **1**—If if the entry should be included.
- **0**—If if the entry should *not* be included.

This is exactly equivalent to the **DIC("S")** input variable for the Classic VA FileMan lookup [^DIC](#). The Finder executes this screen in addition to any **SCR** node (whole-file screen) defined on the data dictionary for the file. Optionally, the screen can be defined in an array entry subscripted by **S** [e.g., **SCR("S")**], allowing additional screen entries to be defined for variable pointer fields as described below.

The entry screen code can rely upon the following:

- **Naked Indicator**—Zero-node of entry's record.
- **D**—Index being traversed.
- **DIC**—Open global reference of file being traversed.
- **DIC(0)**—Flags passed to the Finder.
- **Y**—Record number of entry under consideration.
- **Y() Array**—For subfiles, descendants give record numbers for all upper levels. Structure resembles the **DA** array as used in a call to the Classic VA FileMan edit routine [^DIE](#).
- **Y1**—IENS equivalent to **Y** array.

The code can also safely change any of these values.

For example, "I Y<100" ensures that only records with an internal entry number less than 100 are accepted as matches.



**REF:** For an explanation of the other conditions and screens involved in finding an entry, see the "[Details and Features](#)" section.

Defaults to adding no extra conditions to those listed in that section.

**Variable Pointer Screen.** If one of the fields indexed by the cross-reference passed in the **indexes** parameter is a variable pointer, then additional screens

equivalent to the **DIC("V")** input variable to Classic VA FileMan lookup [^DIC](#) can also be passed. Suppose the screens are being passed in the SCR array. Then for a simple index with just one data value field, the code can be passed in **SCR("V")**. For simple or compound indexes, screens can be passed for any indexed fields that are variable pointers in the format **SCR("V",n)** where *n* represents the subscript location of the variable pointer field on the index.

The Variable Pointer screen restricts the user's ability to see entries on one or more of the files pointed-to by the variable pointer. The screen logic is set equal to a line of M code that returns a truth value when executed. If it evaluates:

- **TRUE**—Entries that point to the file can be included in the output.
- **FALSE**—Any entry pointing to the file is excluded.

At the time the code is executed, the variable **Y(0)** is set equal to the information for that file from the data dictionary definition of the variable pointer field. You can use **Y(0)** in the code set into the variable pointer screen parameter.

[Table 43](#) lists the contents of **Y(0)**:

**Table 43: FIND^DIC API—Variable Pointer Screen: Y(0)**

<b>^-Piece</b>	<b>Contents</b>
Piece 1	File number of the pointed-to file.
Piece 2	Message defined for the pointed-to file.
Piece 3	Order defined for the pointed-to file.
Piece 4	Prefix defined for the pointed-to file.
Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.
Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed-to file.

All of this information was defined when that file was entered as one of the possibilities for the variable pointer field.

For example, suppose your **.01** field is a variable pointer pointing to (fictitious) Files #1000, #2000, and #3000. If you only want the user to be able to enter values from Files #1000 or #3000, you could set up **SCR("V")** like this:

```
S SCR("V")="I +Y(0)=1000!(+Y(0)=3000)"
```

identifier:

(Optional) The text to accompany each found entry to help identify it to the end user. This should be set to M code that calls the [EN^DDIOL](#) utility to load identification text. The identification text generated by this parameter is listed *after* that generated by any WRITE identifiers on the file itself. The code should *not* issue WRITE commands.

For example, a value of "D EN^DDIOL(“KILROY WAS HERE!”)" would include that string with each entry returned, as a separate node under the "ID", "WRITE" nodes of the output array.

This code relies upon all of the same input as the **screen** parameter described above and can safely change the same things.

Defaults to no code.

**target\_root:** (Optional) The array that should receive the output list of found entries. This *must* be a closed array reference and can be either local or global.

If the **target\_root** parameter is *not* passed, the list is returned descendent from `^TMP("DILIST",$J)`.

**msg\_root:** (Optional) The array that should receive any error messages. This *must* be a closed array reference and can be either local or global. For example, if **msg\_root** equals `"OROUT(42)"`, any errors generated appear in `OROUT(42,"DIERR")`.

If the **msg\_root** parameter is *not* passed, errors are returned descendent from `^TMP("DIERR",$J)`.

## Output

**target\_root:** The examples in this section assume that the output from the Finder was returned in the default location descendent from `^TMP("DILIST",$J)`, but it could just as well be in an array specified by the caller in the **target\_root** parameter described above.

There are two different formats possible for the output:

- [Standard Output Format](#)
- [Packed Output Format](#) (returned when the **P** flag is included in the **flags** parameter)

## Standard Output Format

The format of the Output List is:

- **Header Node**

Unless the Finder has run into an error condition, it always returns a header node for its output list, even if the list is empty, because no matches were found. The header node, on the zero node of the output array, has this format:

```
^TMP("DILIST",$J,0) = # of entries found ^ maximum requested ^any more? ^
results flags
```

- The **#** of entries found is equal to or less than the maximum requested.
- The maximum requested should equal either of the following:
  - The **number** parameter.
  - Asterisk (\*), if **number** parameter was *not* passed.
- The **any more?** value is:
  - **1**—If there are more matching entries in the file than were returned in this list.
  - **0**—If not.

- The results flag at present is usually empty. If the output was packed and some of the data contained embedded ^ characters, the results flag contains the **H** flag. In the future the Finder may return other flags as well in this piece, so check whether it contains **H**, not whether it equals it.



**REF:** For more information, see the “[Details and Features](#)” section.

- **Record Data**

Standard output for the Finder returns its output with each field of each matching record on a separate node. Records are subscripted in this array by arbitrary sequence number that reflects the order in which the record was found.

- **.01 Field**

Unless suppressed with the at-sign (@) in the **fields** parameter (the suggested practice), the **.01** field of each record is returned under the **1** subtree of the array, in VA FileMan internal format.

```
^TMP("DILIST", $J, 1, seq#) = .01_field_value_in_internal_format
```



**NOTE:** This is different from the Lister, which returns the indexed field values in the **1** subtree.

- **IEN**

Each record’s IEN is returned under the **2** subtree:

```
^TMP("DILIST", $J, 2, seq#) = IEN
```

The other values returned for each record are grouped together under the “**ID**” subtree, and then by record.

- **Field Values or Field Identifiers**

The output format is the same whether the field value is one of the Field Identifiers from the data dictionary for the file or the field was requested in the **fields** parameter.

Field identifiers and field values are subscripted by their field numbers. Each node shows up as:

```
^TMP("DILIST", $J, "ID", seq#, field #) = field_value
```

If both the **I** and **E suffix** are specified, an additional subscript level with the values of **E** and **I** is used to distinguish the external and internal values of the field. If a field is only returned in one format, the extra subscript is never included. Values output with the extra format specifier look like:

```
^TMP("DILIST", $J, "ID", seq#, field#"E" or "I") = field_value
```



- **Output for field specifier IX in FIELDS**

A field specifier of **IX** in the **fields** parameter retrieves the value of the indexed fields. In the output, the values of these fields are returned as follows, where the final subscript is a sequential number indicating the subscript location in the index.

```
^TMP("DILIST", $J, "ID", seq#, 0, 1) = first_subscript_index_value
^TMP("DILIST", $J, "ID", seq#, 0, 2) = second_subscript_index_value
```

If both the **I** and **E** suffix are specified, an additional subscript level with the values of **E** and **I** is used to distinguish the external and internal values from the index. If the subscript on the index is *not* derived from a field (i.e., if it is a computed subscript), then the internal and external value both are the same; the value directly from the index).



**NOTE:** If both the **I** and **E** suffix are specified for a **COMPUTED** field type that evaluates to a date, the output will be in external format and will *not* have the additional subscript level.

- **WRITE Identifiers**

WRITE (display-only) identifiers are grouped under the “**WRITE**” subtree of the “**ID**” tree, then by record number. It is the caller’s responsibility to ensure that none of the WRITE identifiers issue direct READ or WRITE commands and that they issue any output through the [EN^DDIOL](#) API, so it can be collected by the Finder. The output from all the WRITE identifiers for a single record is listed as individual lines of text:

```
^TMP("DILIST", $J, "ID", "WRITE", seq#, line #) = text generated by
WRITE IDs
```

- **The identifier Parameter**

Any text generated by the caller’s **identifier** parameter is returned in the last lines of the WRITE identifier text.

- **MAP Node for Unpacked Format**

In order to facilitate finding information in the output, a MAP node is built for unpacked format. This node is returned in ^TMP(“**DILIST**”, \$J, 0, “**MAP**”).

The MAP node for unpacked format describes Field Identifier data in the “**ID**” output data nodes. It contains ^ delimited pieces described below. The position of the piece in the MAP node corresponds to the order in which it can be found in the “**ID**” output nodes. If the data is returned in VA FileMan internal format, the piece is followed by **I** (e.g., **2I** means that the internal value of Field #2 was returned in the output).

- **#**—Individually requested field number, where # is the field number, for each field requested in the **fields** parameter.
- **FID(#)**—Field Identifier, where # is the field number.

## Packed Output Format

If the **P** flag is used to request packed output, the Finder packs all the return values into one output node per record. You *must* ensure that all requested data fits onto a single node. Overflow causes error 206. Return values containing embedded ^ characters make the Finder encode the output data using HTML encoding (described in “[Details and Features](#)”).

- **Header Node**

Identical to Standard Output Format.

- **Record Data**

Values in the output are delimited by ^ characters. Piece 1 is *always* the IEN. The values of other pieces depend on the value of the **fields** parameter. If the **fields** parameter is *not* passed, each record’s packed node follows this format:

```
^TMP("DILIST", $J, seq#, 0) = IEN^Internal_.01_field_value^field_Identifier^Write_Identifier^Output_from_Identifier_parameter
```

Field Identifiers are sequenced by field number. Output values specified by the **fields** parameter are packed in the order in which they occur in the **fields** parameter. WRITE identifiers are packed in the same order as their subscripts occur in the **ID** subtree of the file’s data dictionary.

To parse the output of the packed nodes, use the MAP node described below.

- **MAP Node for Packed Format**

Because the packed format is *not* self-documenting and because individual field specifiers can correspond to a variable number of field values (e.g., **FID**), the Finder *always* includes a MAP node when returning output in Packed format. This node is returned in **^TMP("DILIST", \$J, 0, "MAP")**.

Its value resembles a data node’s value in that it has the same number of ^-pieces, but the value of each piece identifies the field or value used to populate the equivalent location in the data nodes. The possible values for each piece in the MAP node are:

- **IEN**—Internal Entry Number (IEN)
- **01**—**.01** field
- **FID(#)**—Field identifier, where # is the field number of the identifier
- **WID(string)**—WRITE identifier, where string is the value of the subscript in the ^DD where the identifier is stored (e.g., “WRITE”)
- **IDP**—Identifier parameter
- **IX(n)**—Indexed field values, where “n” refers to the subscript position in the index
- **#**—Individually requested field, by field number



**NOTE:** For any piece except **IEN**, **WID**, or **IDP**, if the internal value is to be returned, the piece is followed by **I**. Thus, instead of **IX(1)**, you would see **IX(1)I**, indicating that the internal index value was being returned.

For example, the MAP node for a Finder call on the OPTION (#19) file, if **FIELDS => “3.6I;3.6;4”**, might look like this:

```
^TMP("DILIST", $J, 0, "MAP") = "IEN^.01^3.6I^3.6^4"
```

### 3.5.8.1 Examples

#### 3.5.8.1.1 Example 1

First, do a lookup on the OPTION (#19) file, using the “C” index (Upper Case Menu Text). Let the Finder return default output, so you get the NAME (#.01) field, the IEN, and the MENU TEXT (#1) field (Identifier), as shown in [Figure 143](#):

**Figure 143: FIND^DIC API—Example 1: Input and Output**

```
>D FIND^DIC(19,"","","STAT","","C","","","OUT")

OUT("DILIST",0)=2^*^0^
OUT("DILIST",0,"MAP")=FID(1)
OUT("DILIST",1,1)=DISTATISTICS
OUT("DILIST",1,2)=ZISL STATISTICS MENU
OUT("DILIST",2,1)=15
OUT("DILIST",2,2)=187
OUT("DILIST","ID",1,1)=Statistics
OUT("DILIST","ID",2,1)=Statistics Menu
```

#### 3.5.8.1.2 Example 2

This example ([Figure 144](#)) looks in the OPTION (#19) file for entries that are at least partial matches to “DIS”. It uses the “B” index and, since you do *not* include the M flag to search multiple indexes. Look *only* on the “B” index; use the @ in the **fields** parameter to suppress the default values and specify that you want the .01 field (NAME), field 1 (DESCRIPTION), and the index values in the output.

**Figure 144: FIND^DIC API—Example 2: Input and Output**

```
>D FIND^DIC(19,"","@;.01;1;IX","","DIS",5,"B","","","OUT")

OUT("DILIST",0)=2^5^0^
OUT("DILIST",0,"MAP")=IX(1)^.01^1
OUT("DILIST",2,1)=11
OUT("DILIST",2,2)=15
OUT("DILIST","ID",1,0,1)=DISEARCH
OUT("DILIST","ID",1,.01)=DISEARCH
OUT("DILIST","ID",1,1)=Search File Entries
OUT("DILIST","ID",2,0,1)=DISTATISTICS
OUT("DILIST","ID",2,.01)=DISTATISTICS
OUT("DILIST","ID",2,1)=Statistics
```

### 3.5.8.1.3 Example 3

Next, do a call almost identical to [Example 2](#), but this time use the **M** flag to indicate that you want to search all the lookup indexes starting from “**B**”, as shown in [Figure 145](#). This time you get more records back and looking at the index values in the entries OUT(“DILIST”,”ID”,seq#,0,subscript\_location), you see that the new entries were found on an index other than the “**B**” index (since the values do *not* match the .01 field). In fact, they were found on the index for the field UPPER CASE MENU TEXT (index “**C**” on the file).

**Figure 145: FIND^DIC API—Example 3: Input and Output**

```
>D FIND^DIC(19,"","@;.01;1;IX","M","DIS",5,"B","","","OUT")

OUT("DILIST",0)=5^5^1^
OUT("DILIST",0,"MAP")=IX(1)^.01^1
OUT("DILIST",2,1)=11
OUT("DILIST",2,2)=15
OUT("DILIST",2,3)=468
OUT("DILIST",2,4)=470
OUT("DILIST",2,5)=469
OUT("DILIST","ID",1,0,1)=DISEARCH
OUT("DILIST","ID",1,.01)=DISEARCH
OUT("DILIST","ID",1,1)=Search File Entries
OUT("DILIST","ID",2,0,1)=DISTATISTICS
OUT("DILIST","ID",2,.01)=DISTATISTICS
OUT("DILIST","ID",2,1)=Statistics
OUT("DILIST","ID",3,0,1)=DISK DRIVE RAW DATA STATISTICS
OUT("DILIST","ID",3,.01)=XUCM DISK
OUT("DILIST","ID",3,1)=Disk Drive Raw Data Statistics
OUT("DILIST","ID",4,0,1)=DISK DRIVE REQUEST QUEUE LENGT
OUT("DILIST","ID",4,.01)=XUCM DSK QUE
OUT("DILIST","ID",4,1)=Disk Drive Request Queue Length
OUT("DILIST","ID",5,0,1)=DISK I/O OPERATION RATE
OUT("DILIST","ID",5,.01)=XUCM DSK IO
OUT("DILIST","ID",5,1)=Disk I/O Operation Rate
```

### 3.5.8.1.4 Example 4

In this example ([Figure 146](#)), use the **K** flag to do a lookup on a file with a Primary Key made up of the .01 field (NAME) and field 1 (DATE OF BIRTH). Suppress all of the output with @ and then ask only for both the internal and external index values. Notice that the **P** flag causes the output to be returned in Packed format. The MAP node tells you what is in each ^ piece of the output.

**Figure 146: FIND^DIC API—Example 4: Input and Output**

```
>K VAL S VAL(1)="ADD",VAL(2)="01/01/69"
>D FIND^DIC(662001,"","@;IXIE","PK",.VAL,"","","","OUT")

OUT("DILIST",0)=1^*^0^
OUT("DILIST",0,"MAP")=IEN^IX(1)I^IX(2)I^IX(1)^IX(2)
OUT("DILIST",1,0)=15^ADDFIFTEEN^2690101^ADDFIFTEEN^JAN 01, 1969
```

### 3.5.8.1.5 Example 5

This example (Figure 147) demonstrates how the **B** flag works. You have a file whose **.01** field points to the NEW PERSON (#200) file. When you do a lookup without the **B** flag, you find several entries; but if you look at the **.01** field, you see that *not* all of them begin with the lookup value **F**. The entry FMPERSON,FOUR was found because his initials **FF** begin with **F** and FMPERSON,FIVE was found because her nickname “FILLY” begins with **F**.

Figure 147: FIND^DIC API—Example 5: Input and Output

```
>D FIND^DIC(662002,"","@;.01","P","F","","","B","","","OUT")

OUT("DILIST",0)=5^^^0^
OUT("DILIST",0,"MAP")=IEN^.01
OUT("DILIST",1,0)=7^FMPERSON,FOUR
OUT("DILIST",2,0)=3^FMPERSON,SIX
OUT("DILIST",3,0)=4^FMPERSON,SEVEN
OUT("DILIST",5,0)=1^FMPERSON,FIVE
OUT("DILIST",6,0)=13^FMPERSON,FIVE
```

When you use the **B** flag, the FINDER looks *only* at the “**B**” index of the NEW PERSON (#200) file.

Figure 148: FIND^DIC API—Example 5: Input with “**B**” Flag and Output

```
>D FIND^DIC(662002,"","@;.01","PB","F","","","B","","","OUT")

>ZW OUT
OUT("DILIST",0)=2^^^0^
OUT("DILIST",0,"MAP")=IEN^.01
OUT("DILIST",1,0)=3^FMPERSON,SIX
OUT("DILIST",2,0)=4^FMPERSON,SEVEN
```

### 3.5.8.1.6 Example 6

This example shows use of the **index** parameter array that can control lookup on a pointed-to file. In this example, the **.01** field of (fictitious) File #662002 points to the NEW PERSON (#200) file. [Figure 149](#) and [Figure 150](#) demonstrate the different results you get when you control the list of indexes used when the Finder goes off to File #200 to look for matches to your lookup value. It shows the same call, with and without the new **index** parameter array.

First, make a call without the new parameter, using a lookup value of **T**. There are indexes on both the NICKNAME and the INITIALS field. Because you did *not* specify which indexes to use, VA FileMan uses all lookup indexes during the lookup on the pointed-to file. In this call, you pick up several entries. The NICKNAME for EIGHT FMPERSON happens to be “TOAD”, and the INITIALS field for TWO FMPERSON is **TF**.

**Figure 149: FIND^DIC API—Example 6: Input with “T” Lookup Value and Output**

```
>S INDEX="B^C^E"

>LD FIND^DIC(662002,, ".01;IXIE;@", "PM", "T", , INDEX, , , "TKW")

>ZW TKW
TKW("DILIST",0)=4^*^0^
TKW("DILIST",0,"MAP")=IEN^.01^IX(1)I^IX(1)
TKW("DILIST",1,0)=4^ FMPERSON,EIGHT^9^FMPERSON,EIGHT
TKW("DILIST",2,0)=12^T_FMPERSON,TWENTY^12^T_FMPERSON,TWENTY
TKW("DILIST",3,0)=1^FMPERSON,TWO^4^FMPERSON,TWO
TKW("DILIST",4,0)=13^FMPERSON,TWO^4^FMPERSON,TWO
```

This time, the **index** parameter still contains **B** and **E**, so you still look at those indexes on the starting (fictitious) File #662002, but you set the new parameter so that it only looks at the “**B**” and “**BS5**” indexes on the pointed-to File #200. This time you do *not* find any entries whose INITIALS or NICKNAME field start with **T**. You just pick up the person whose last name starts with **T**.

**Figure 150: FIND^DIC API—Example 6: Input with “B” and “BS5” Lookup Values and Output**

```
>S INDEX("PTRIX",662002,.01,200)="B^BS5"

>D FIND^DIC(662002,, ".01;IXIE;@", "PM", "T", , .INDEX, , , "TKW")

>ZW TKW
TKW("DILIST",0)=1^*^0^
TKW("DILIST",0,"MAP")=IEN^.01^IX(1)I^IX(1)
TKW("DILIST",1,0)=12^T_FMUSER,TWENTY^12^T_FMUSER,TWENTY
```

### 3.5.8.2 Error Codes Returned

[Table 44](#) lists the possible error codes returned with the Find^DIC API:

**Table 44: FIND^DIC API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">202</a>	An input parameter is missing or not valid.
<a href="#">204</a>	The input value contains control characters.
<a href="#">205</a>	The File and IENS represent different subfile levels.
<a href="#">206</a>	The data requested for the record is too long to pack together.
<a href="#">207</a>	The value is too long to encode into HTML.
<a href="#">301</a>	The passed flags are unknown or inconsistent.
<a href="#">304</a>	The IENS lacks a final comma.
<a href="#">306</a>	The first comma-piece of the IENS should be empty.
<a href="#">401</a>	The file does not exist.
<a href="#">402</a>	The global root is missing or not valid.
<a href="#">406</a>	The file has no .01 field definition.
<a href="#">407</a>	A word-processing field is not a file.
<a href="#">420</a>	The index is missing.
<a href="#">501</a>	The file does not contain that field.
<a href="#">520</a>	That kind of field cannot be processed by this utility.
<a href="#">8090</a>	Pre-lookup transform (7.5 node).
<a href="#">8095</a>	First lookup index is compound, so “M”ultiple index lookups not allowed.

The Finder can also return any error returned by [\\$\\$EXTERNAL^DILFD](#).

### 3.5.8.3 Details and Features

#### 3.5.8.3.1 Lookup Index

If the “Use” flag for an index entry in the INDEX (#.11) file is set to **L** for Lookup, the index name *must* be **B** or *must* alphabetically follow **B**. Also, traditional indexes whose names follow “**B**” are considered to be Lookup type indexes.

What does this mean? For a Finder call (FIND^DIC or [\\$\\$FIND1^DIC](#)), it means that if **M** is passed in the **flags** parameter and a list of indexes is *not* specified in the **indexes** parameter, then VA FileMan automatically uses any lookup type index it finds by ordering through the index name alphabetically, starting with the beginning index (“**B**”, unless a different one is specified in the input parameters). Any index, however, can be used for lookup if it is specified in the **indexes** parameter. The developer should be careful to make sure the MUMPS-type indexes are formatted similar to VA FileMan regular indexes,

with the data subscripts followed by the IEN at the level of the file/subfile passed in the **file** input parameter.

### 3.5.8.3.2 Screens Applied

**Valid Entry Conditions.** To be considered for selection, an entry *must* have a properly formatted index to get the Finder’s attention and a defined zero-node with a *non*-null first piece.

**File Pre-Lookup Action (7.5 Node).** Prior to performing any search of the database whatsoever, the Finder executes the 7.5 Node for the file. This code can alter the variable **X**, the lookup value, to alter the value used by the Finder in its search.



**NOTE:** The 7.5 node only works on a simple index, *not* a compound one. It assumes just one lookup value **X**.

**Call Pre-Selection Action.** The **screen** parameter is executed once a potential match has been identified (as described in the “Input Parameters” section).

**File Pre-Selection Action.** If the file has a pre-selection action defined (the **SCR** node), then after passing the pre-selection action for the call, the entry *must* also pass the action for the whole file.

### 3.5.8.3.3 Partial Matches

For most values on most indexes, an input value partially matches an entry if the index value begins with the input value (e.g., index value of “FMEMPLOYEE,ONE” partially matches input value of “FMEMPLOYEE”). The exception is numeric input. On a numeric field’s index, a numeric input *must* match exactly.

If the lookup value is numeric but the cross-referenced field is free-text, the Finder finds all partial matches to the numeric lookup value. For example, lookup value 1 matches to 1, 199, 1000.23 and 1ABC.

### 3.5.8.3.4 Spacebar Recall

Although the Finder honors the “**Spacebar Recall**” feature whenever passed the input value “ ”, selections made through the Finder are *not* stored for later use by **Spacebar Recall** because the Finder has no way of knowing whether the selection results from interaction with the user. Only deliberate user selections should affect the **Spacebar Recall** value. As a result, to support this feature, applications should call the [RECALL^DILFD](#) API when managing the user interface whenever the user makes a selection.

### 3.5.8.3.5 Lookup Value Transforms List

The original lookup values passed to the Finder are *not* the only values used during the lookup. Certain transforms are done on the original lookup value and matches are made for these transformed values along with the original ones. The **Q** flag suppresses all of these transforms and looks on the indexes only for the original lookup value.



**REF:** for more information, see the “[Uppercase](#)”, “[Long Input](#)”, “[Comma-Piecing](#)” and “[Data Type Transforms](#)” sections.

### 3.5.8.3.6 Uppercase

The first basic transform ensures that lookups succeed when users leave their **Caps Lock** keys off. If the **value** parameter contains any lowercase characters, the Finder also looks for an all-uppercase version of the value.



### 3.5.8.3.7 Long Input

The second basic transform ensures that lookups work properly when lookup and field values are longer than the maximum length of a data-values subscript in the index. This is 30 characters for traditional indexes, but is set by the developer for indexes defined in the INDEX (#.11) file.

### 3.5.8.3.8 Comma-Piecing

The third and final basic transform provides a special feature of VA FileMan's lookup. This feature, known as comma-piecing, helps the user enter fewer characters to distinguish between similar entries. VA FileMan uses lookup values that contain embedded commas to build a pattern match based on all the comma-pieces. For example, distinguishing between "FMUSER,ONE FRANCIS" and "FMUSER,TWO FRANK" would normally take eight keystrokes—"FMUSER,T"—but comma-piecing lets the user do it in three: "**F,T**".

Although commas are used to trigger the comma-piecing feature, the characters used to break up the entry in the file can be any kind of punctuation, not only commas. For example, "**T,R**" matches "THE ROAD LESS TRAVELED".

If the **C** flag is used in the **flags** parameter, then the second comma-piece of the lookup value can be a match to any of the pieces in the file entry following the first one. So, for example, "**F,S**" distinguishes "FMUSER,ONE SEBASTIAN" from his sons "FMUSER,ONE CHRISTIAN" and "FMUSER,ONE CHRISTOPH FRIEDRICH".

### 3.5.8.3.9 Data Type Transforms

Indexes store the VA FileMan internal format of field values, but users typically enter the external format as lookup values. Therefore, the Finder attempts to do conversions of the lookup values when it searches an index on any of the following field data types:

- DATE
- SET OF CODES
- POINTER
- VARIABLE POINTER

For example, a lookup value of **t** would also be evaluated as today's date in internal VA FileMan format, if the Finder is searching the index on a date type field, since VA FileMan normally recognizes a user entry of **T** at a date prompt as meaning "**TODAY**".

If a **Q** flag is passed in the **flags** parameter, no data type transforms are attempted.



**NOTE:** The data type transform for indexes on pointer and variable pointer fields involves a complete lookup on the pointed-to file. For example, if an application calls the Finder with the input value "**W**" on a file with an indexed pointer to the STATE (#5) file, the Finder locates every state starting with **W** (Washington, West Virginia, Wisconsin, and Wyoming). It returns every record in the pointing file that points to one of those states.

Also, if the pointed-to file has indexed pointers or variable pointers, the search continues to these pointed-to files.

Therefore, to make more efficient searches, and to find just the entries desired, applications should make use of all available features of the Finder to narrow down the search. For example, use the **indexes** parameter when appropriate to limit the list of indexes searched, and the **B** flag when appropriate to make sure that only the "**B**" index is searched on any pointed-to file.

### 3.5.8.3.10 HTML Encoding

Since the Finder uses the ^ character as its delimiter for packed output, it *cannot* let any of the data contain that character. If any does, it encodes all of the data using an HTML encoding scheme.

In this scheme:

- All ampersand (&) characters are replaced with the substring **&amp;**;
- All caret (^) characters with the string **&#94**

This keeps the data properly parsable and decodable. The data for all records found, *not* just the ones with embedded carets (^), are encoded if embedded carets (^) are found in the data of any of the records.

If the Finder has encoded the output, it includes an **H** flag in ^-piece four of the output header node.

Data can be decoded using the VA FileMan library function call [\\$\\$HTML^DILF](#)(encoded string,-1). It can properly decode individual fields or complete packed data nodes.

### 3.5.8.3.11 WRITE ID Nodes

The Finder executes each individual **WRITE ID** node from the data dictionary. If an individual node results in creating multiple lines in the output from the [EN^DDIOL](#) calls it contains, then in Standard Output Format the results appear on multiple lines in the output array. Thus, there is *not* a direct correlation between the number of **WRITE ID** nodes and the number of nodes that are returned in the output array of a Finder call for each record. In packed output format, each **WRITE ID** node appears in a separate ^ piece, and line feeds are designated with a tilde (~) character.

### 3.5.8.3.12 Repeating a Field in FIELDS parameter

If a field is listed multiple times in the **fields** parameter, it is returned multiple times in packed output, but only once in unpacked output. This is because the field number is one of the subscripts of unpacked output. The exception is when the occurrences are for different formats, internal and external.

### 3.5.9 \$\$FIND1^DIC(): Finder (Single Record)

The \$\$FIND1^DIC extrinsic function finds a single record in a file based on input values. If more than one match is found, the function returns an error. The caller *must* specify a file number and the input values to be used for the lookup. The caller can also specify the indexes to be used in the search, and can also pass screening logic.



**NOTE:** \$\$FIND1^DIC does *not* honor the Special Lookup or Post-Lookup Action nodes defined in the data dictionary for a file.



**NOTE:** The VA FileMan Database Server (DBS) APIs typically work like their VA FileMan Classic counterparts. However, the DBS APIs listed below *do not* perform numeric lookups the way the classic [^DIC](#) API does:

- [FIND^DIC\(\): Finder](#)
- \$\$FIND1^DIC(): Finder (Single Record)
- [LIST^DIC\(\): Lister](#)

Rather, these three APIs perform numeric lookups the way [^DIC](#) performs them when the lowercase **n** flag is set.

**REF:** For information on the use of the lowercase **n** flag in conjunction with the **DIC(0)** input variable, see the “[^DIC: Lookup/Add](#)” section in the “[Classic VA FileMan API](#)” section.

#### Format

```
$$FIND1^DIC(file[,iens][,flags],[.]value[,[.]indexes][,[.]screen][,msg_root])
```

#### Input Parameters

- file:** (Required) The number of the file or subfile to search. If this parameter is a subfile, it *must* be accompanied by the **iens** parameter.
- iens:** (Optional) The IENS that identifies the subfile, if **file** is a subfile number. To identify a subfile, rather than a subfile entry, leave the first comma-piece empty. For example, a value of “,67,” indicates that the subfile within entry #67 should be used. If **file** is a file number, this parameter should be empty.  
Defaults to no subfile.
- flags:** (Optional) Flags to control processing. This parameter lets the caller adjust the Finder’s algorithm. The possible values are:
- **A**—Allow pure numeric input to always be tried as an IEN. Normally, the Finder only tries pure numbers as IENs if:
    - File has a **.001** field.
- Or:
- The **.01** field is *not* numeric and the file has no lookup index.
- When this flag is used, records that match other numeric interpretations of the input are found in addition to a record with a matching IEN. For example, a lookup value of “2” would match a record with a lookup field of “2ONE” as well as a record with an IEN of 2.



**NOTE:** If the numeric lookup value is preceded by a grave accent character ( ` ), lookup interprets the input as an IEN, and only attempts to match by IEN. The **A** flag is *not* required in this case.

- **B—B** index used on lookups to pointed-to files. Without the **B** flag, if there are cross-referenced pointer fields in the list of indexes to use for lookup then:
  - For each cross-referenced pointer field, VA FileMan checks *all* lookup indexes in each pointed-to file for a match to **X** (time-consuming).

And:

- If **X** matches any value in any lookup index (*not* just on the **.01** field) in a pointed-to file and the IEN of the matched entry is in the home file's pointer field cross-reference, VA FileMan considers this a match (perhaps *not* the lookup behavior desired).

The **B** flag prevents this behavior by looking for a match to **X** only in the “**B**” index (**.01** field) of files pointed to by cross-referenced POINTER fields. This makes lookups quicker and avoids the risk of VA FileMan matching an entry in the pointed-to file based on something other than the **.01** field.



**REF:** For an explanation of the “Lookup Index” and for more information on use of the **B** flag, see the “[Details and Features](#)” and “[Examples](#)” sections.

- **C**—Finder uses the Classic way of performing lookups on names (i.e., like the classic VA FileMan lookup routine [^DIC](#)). If **C** is passed in the **flags** parameter and, for example, the user enters a lookup value of “FMU,J”; the Finder finds “FMUSER,ONE” but also “FMUSER,ONEHUNDRED J.” The Finder takes the first comma piece of the lookup value “ONE”, and looks for partial matches to that. It then takes the second comma piece of the lookup value **J** and looks for partial matches to **J** on the second or any other piece of the value on the entry being examined. It uses any punctuation or space for a delimiter.

The default, without passing **C** in the **flags** parameter, looks for partial matches *only* on the second piece; thus, in the example, finding “FMUSER,ONE” but *not* “FMUSER,ONEHUNDRED J.”. The old style of comma-piece processing can be quite slow, especially with common names.

- **K**—Primary **Key** used for starting index. If no index is specified in the **indexes** parameter, this flag causes the Finder to use the Uniqueness index for the Primary Key as the starting index for the search. Without the **K** flag, or if there is no Primary Key for this file (in the KEY [#.31] file), the Finder defaults to the “**B**” index.
- **M**—Multiple index lookup allowed. If more than one index is passed in the **indexes** parameter, all indexes in the list are searched. Otherwise, the

**M** flag causes the Finder to search the starting index and all indexes that alphabetically follow it. This includes both indexes from the traditional location in the data dictionary, as well as lookup indexes defined on the INDEX (#.11) file that have an **L** (for LOOKUP) in the “Use” field.

The starting index is taken from the **indexes** parameter. If that is null, the search begins with the default starting Index (see **K** flag description above).



**NOTE:** If the first index passed in the **indexes** parameter is a compound index, the **M** flag is removed and only that one index is searched.

**REF:** For more information, see “[Lookup Index](#)” in the “[Details and Features](#)” section.

- **O**—Only find an exact match if possible. The Finder first searches for an exact match on the requested indexes; if one is found, it is returned. Only if it does *not* find one in the file does it search for a partial match. For example, if the lookup value is “FMUSER” and the file contains entries “FMUSER” and “FMUSER,ONE”, only the first record is returned. If the first record did *not* exist, the Finder would return “FMUSER,ONE” as a match.



**NOTE:** The presence of a partial match does *not* constitute an error condition, because a single exact match is present. If the **flags** parameter does *not* contain **O** (or an **X**, see below), the presence of both partial and exact matches is treated as an error condition.

If the lookup is done on a compound index, exact matches *must* be made for every data value subscript in the index in order to consider the entry to be an exact match.

- **Q**—Quick lookup. If this flag is passed, the Finder assumes the passed-in value is in VA FileMan internal format. The Finder performs *no* transforms of the input value, but only tries to find the value in the specified lookup indexes. Therefore, when the **Q** flag is passed, the lookup is much more efficient. If the **flags** parameter does *not* contain a **Q**, the Finder assumes the lookup value is an external or user-entered value and performs all normal transforms as documented below.
- **U**—Unscreened lookup. This flag makes the Finder ignore any whole file screen [stored at `^DD(file#,0,"SCR")`] on the file specified in the **file** parameter.



**NOTE:** Passing this flag does *not* make the Finder ignore the **screen** parameter.

- **X**—EXact match only. The Finder returns only an exact match to the lookup value on the requested indexes. Any partial matches present in the file are ignored, and transforms (e.g., changing the lookup value to

uppercase) are *not* performed. For example, in the scenarios described under the **O** flag, the Finder behaves identically in the first situation, but under the second it returns no match, since “FMUSER,ONE” is *not* an exact match to “FMUSER”. If both the **O** and **X** flags are passed, the **O** flag is ignored. If the lookup is done on a compound index, exact matches *must* be made for every data value subscript in the index.

[.]value:

(Required) The lookup values. These should be in external format as they would be entered by an end-user, unless the **Q** flag is used. If the lookup index is compound, then lookup values can be provided for each of the data value subscripts in the index. In that case, **value** is passed by reference as an array where **VALUE(*n*)** represents the lookup value to be matched to the *n*th subscript in the index. If only one lookup value is passed in **value**, it is assumed to apply to the first data value subscript in the index.

In addition, certain values generate special behavior by the Finder as follows:

- **Control Characters**—This value always results in no matches. Control characters are *not* permitted in the database.
- **^ (Caret)**—This value always results in no matches. This single character value signifies to VA FileMan that the current activity should be stopped.
- **“” (Empty String)**—On single field indexes, this value always results in no matches. The empty string, used by VA FileMan to designate fields that have no value, *cannot* be found in VA FileMan indexes. However, if the lookup uses a compound index, **VALUE(*n*)** can be null for any of the lookup values as long as at least one of them is *non*-null. If **VALUE(1)** is null, it can make the lookup slower. If **VALUE(*n*)** is null, all *non*-null values for that subscript position is returned.
- **“ ” (Space Character)**—This value indicates that the Finder should return the current user’s previous selection from this file. This corresponds to the “**Spacebar Recall**” feature of VA FileMan’s user interface. If VA FileMan has no such previous selection for this user, or if this selection is now prohibited from selection somehow (see discussions of [screen](#) input parameter), then the Finder returns no matches. The Finder itself never preserves its found values for this recall; applications wishing to preserve found values should call [RECALL^DILFD](#). The special lookup characters should appear either in **VALUE** or in **VALUE(1)**.
- **`-Number (Grave Accent Character followed by a number)**—This indicates that the Finder should select the entry whose internal entry number equals the number following the grave accent character (`). This corresponds to an equivalent feature of VA FileMan’s user interface. If this entry is prohibited from selection, the Finder returns no match. The use of `*n*-number input does *not* require passing **A** in the **flags** parameter. The special lookup characters should appear either in **VALUE** or in **VALUE(1)**.

- **Numbers**—The Finder tries strictly numeric input as an IEN under any of the following four conditions:
  1. Caller passes **A** in the **flags** parameter.
  2. File has a **.001** field.
  3. File's **.01** field is *not* numeric and the file has no lookup index.
  4. The **indexes** parameter contains **#** as one of its index names.

In all cases, the lookup value is expected to be in either **VALUE** or **VALUE(1)**. In condition 4, if the **#** is the only **index**, and if the lookup value does *not* match an IEN, the lookup fails, otherwise, the Finder continues the search using the other indexes.

In conditions 1, 2 and 3, strictly numeric input differs from ``-numeric` input in that whether or *not* a record corresponding to this IEN exists or is selectable, the Finder proceeds with a regular lookup, using the numeric value to find matches in the file's indexes. Even used this way, however, numeric input has the following special restriction: it is *not* used as a lookup value in any indexed pointer or variable pointer field (unless **Q** is passed in the **flags** parameter).

For example, suppose an application performs a Finder call on the (fictitious) EMPLOYEE file, passing a lookup value of 12; that the (fictitious) EMPLOYEE file points to the STATE (#5) file, in which Washington is record number 12; and that the (fictitious) EMPLOYEE file's pointer to the STATE (#5) file is indexed. The application would *not* be able to use the input value of 12 to find every employee who lives in Washington state.

[.]indexes:

(Optional) The indexes the Finder should search for a match. This parameter should be set to a list of index names separated by `^` characters. This parameter specifies which indexes to check and the order in which to check them. The caller does *not* need to pass the **M** flag for the **indexes** parameter to work properly. For example, a value of `"B^C^ZZALBERT^D"` specifies four indexes to check in the given order.

If the first index passed is a compound index, only that one index can be in the list. Attempting to put more than one index in the list when the first one is compound generates an error. If the first index in the list is a single subscript index, however, compound indexes can follow that one in the list. In that case, the lookup expects only one lookup value and only the first subscript of any compound index is checked for matches.

If no index name, or only one index name, is passed in the **indexes** parameter, and if the **flags** parameter contains an **M**, then the Finder does the search using the starting index, as well as all indexes that follow the starting one alphabetically (unless the starting index is compound; see paragraph above).



**REF:** See also the documentation on the **M** flag.

If the index is *not* specified, the default starting index is **"B"** unless the **flags** parameter contains a **K**, in which case the default is the Uniqueness Index defined for the Primary Key on the file.

Mnemonic cross-references folded into the specified index are included in the output.



When the first subscript of one of the indexes on the file you are searching indexes a pointer or variable pointer, then the Finder searches the pointed-to file for matches to the lookup value. Array entries can be passed in the **indexes** parameter to control this search on the pointed-to file. Suppose the name of the array is NMSPIX. Then you can set  
NMSPIX("PTRIX",from\_file#,pointer\_field#,to\_file#)="^"\_delimited\_index\_list  
. This array entry allows the user to pass a list of indexes that is used when doing the search on the pointed-to file.

For example, if the (fictitious) File #662001 has a pointer Field #5 to File #200 (NEW PERSON), and you wanted the lookup on Field #5 to find entries in the NEW PERSON (#200) file only by name ("B" index), or by the first letter of the last name concatenated with the last 4 digits of the social security number ("BS5" index), set NMSPIX("PTRIX",662001,5,200)="B^BS5".

[.]screen:

(Optional) **Entry Screen**. The screen to apply to each potential entry in the returned list to decide whether or *not* to include it. This may be set to any valid M code that sets \$TEST to

- **1**—If the entry should be included.
- **0**—If the entry should *not* be included.

This is exactly equivalent to the **DIC("S")** input variable for the Classic VA FileMan lookup [^DIC](#). The Finder executes this screen in addition to any SCR node (whole-file screen) defined on the data dictionary for the file. Optionally, the screen can be defined in an array entry subscripted by **S** [e.g., SCR("S")], allowing additional screen entries to be defined for variable pointer fields as described below.

The entry screen code can rely upon the following:

- **Naked Indicator**—Zero-node of entry's record.
- **D**—Index being traversed.
- **DIC**—Open global reference of file being traversed.
- **DIC(0)**—Flags passed to the Finder.
- **Y**—Record number of entry under consideration.
- **Y() Array**—For subfiles, descendants give record numbers for all upper levels. Structure resembles the **DA** array as used in a call to the Classic VA FileMan edit routine [^DIE](#).
- **Y1**—IENS equivalent to **Y** array.

The code can also safely change any of these values.

For example, "I Y>99" ensures that only a record numbered 100 or higher can be accepted as a match.



**REF:** For an explanation of the other conditions and screens involved in finding an entry, see "[Details and Features](#)."



If duplicate entries exist, but only one passes the screens, then that one is returned and no error is generated. Defaults to adding no extra conditions to those listed in that section.

**Variable Pointer Screen.** If one of the fields indexed by the cross-reference passed in the **indexes** parameter is a VARIABLE POINTER, then additional screens equivalent to the **DIC("V")** input variable for Classic VA FileMan lookup [^DIC](#) can also be passed. Suppose the screens are being passed in the **SCR** array, then for a simple index with just one data value field, the code can be passed in **SCR("V")**. For simple or compound indexes, screens can be passed for any indexed fields that are variable pointers in the format **SCR("V",n)** where **n** represents the subscript location of the variable pointer field on the index.

The Variable Pointer screen restricts the user's ability to see entries on one or more of the files pointed to by the variable pointer. The screen logic is set equal to a line of M code that returns a truth value when executed. If it evaluates:

- **TRUE**—Entries that point to the file can be included in the output.
- **FALSE**—Any entry pointing to the file is excluded.

At the time the code is executed, the variable **Y(0)** is set equal to the information for that file from the data dictionary definition of the variable pointer field. You can use **Y(0)** in the code set into the variable pointer screen parameter. [Table 45](#) lists the contents of **Y(0)**:

**Table 45: \$\$FIND1^DIC API—Variable Pointer Screen: Y(0)**

^-Piece	Contents
Piece 1	File number of the pointed-to file.
Piece 2	Message defined for the pointed-to file.
Piece 3	Order defined for the pointed-to file.
Piece 4	Prefix defined for the pointed-to file.
Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.
Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed-to file.

All of this information was defined when that file was entered as one of the possibilities for the variable pointer field.

For example, suppose your **.01** field is a VARIABLE POINTER pointing to (fictitious) Files #1000, #2000, and #3000. If you only want the user to be able to enter values from Files #1000 or #3000, you could set up **SCR("V")** like this:

```
S SCR("V")="I +Y(0)=1000!(+Y(0)=3000)"
```

msg\_root:

(Optional) The array that should receive any error messages. This *must* be a closed array reference and can be either local or global. For example, if **msg\_root** equals "OROUT(42)", any errors generated appear in OROUT(42,"DIERR").

If the `msg_root` is *not* passed, errors are returned descendent from `^TMP("DIERR",$J)`.

## Output

The function evaluates to:

- **Internal Entry Number (IEN)**—if a single match is found.
- **0**—If no matches are found.
- **“”**—if an error occurred.

### 3.5.9.1 Examples

#### 3.5.9.1.1 Example 1

In this example ([Figure 151](#)), you look for a DIFG option on the OPTION (#19) file. You use the **M** flag to search all indexes and the **X** flag to specify that you want exact matches only. It returns the IEN of the entry found.

**Figure 151: \$\$FIND1^DIC API—Example 1: Input and Output**

```
>W $$FIND1^DIC(19,"","MX","DIFG","","","ERR")
327
```

#### 3.5.9.1.2 Example 2

In this example ([Figure 152](#)), you look for an option that is *not* on the OPTION (#19) file. You set up the call exactly the same as [Example 1](#). This time it returns **0**, because no matching entry was found.

**Figure 152: \$\$FIND1^DIC API—Example 2: Input and Output**

```
>W $$FIND1^DIC(19,"","MX","DIFG ZZZZ","","","ERR")
0
```

#### 3.5.9.1.3 Example 3

In this example ([Figure 153](#)), you do the exact same call as in [Example 1](#), but this time you do *not* include the **X** flag, so it finds not only “DIFG”, but also any partial matches to “DIFG”. Since there are several, it *cannot* find just one match, so the call fails. The return is null and an error message is returned as well.

**Figure 153: \$\$FIND1^DIC API—Example 3: Input and Output**

```
>W $$FIND1^DIC(19,"","M","DIFG","","","ERR")
DIERR=1^1

ERR("DIERR")=1^1
ERR("DIERR",1)=299
ERR("DIERR",1,"PARAM",0)=2
ERR("DIERR",1,"PARAM",1)=DIFG
ERR("DIERR",1,"PARAM","FILE")=19
ERR("DIERR",1,"TEXT",1)=More than one entry matches the value(s) 'DIFG'.
ERR("DIERR","E",299,1)=
```

### 3.5.9.1.4 Example 4

In this example ([Figure 154](#)), you do two different calls to find an entry on a test file. There are two entries whose **.01** field equals “ADDFIFTEEN”. In the first call, you do the lookup on the “**B**” index and the call fails, because there are two entries that match the lookup value.

**Figure 154: \$\$FIND1^DIC API—Example 4: Input and Output: Failure**

```
>W $$FIND1^DIC(662001,"","","ADDFIF","B","","ERR")

>ZW ERR
ERR("DIERR")=1^1
ERR("DIERR",1)=299
ERR("DIERR",1,"PARAM",0)=2
ERR("DIERR",1,"PARAM",1)=ADDFIF
ERR("DIERR",1,"PARAM","FILE")=662001
ERR("DIERR",1,"TEXT",1)=More than one entry matches the value(s) 'ADDFIF'.
ERR("DIERR","E",299,1)=
```

However, if you try the call again and this time use the “**BB**” index for the file, which indexes the NAME (#.01) field and also DATE OF BIRTH (#1) field, you can pass lookup values for both the fields; the call is successful, because you now have a single match. The two entries with the same **.01** field have different values in their DATE OF BIRTH field.

**Figure 155: \$\$FIND1^DIC API—Example 1: Input and Output: Success**

```
>K VAL S VAL(1)="ADDFIF",VAL(2)="1/1/69"

>W $$FIND1^DIC(662001,"","",.VAL,"BB","","ERR")
15
```

### 3.5.9.2 Error Codes Returned

[Table 46](#) lists the possible error codes returned with the \$\$FIND1^DIC API:

**Table 46: \$\$FIND1^DIC API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">202</a>	An input parameter is missing or not valid.
<a href="#">204</a>	The input value contains control characters.
<a href="#">205</a>	The File and IENS represent different subfile levels.
<a href="#">299</a>	More than one entry matches that value.
<a href="#">301</a>	The passed flags are unknown or inconsistent.
<a href="#">304</a>	The IENS lacks a final comma.
<a href="#">306</a>	The first comma-piece of the IENS should be empty.
<a href="#">401</a>	The file does not exist.
<a href="#">402</a>	The global root is missing or not valid.
<a href="#">406</a>	The file has no .01 field definition.

Code	Description
<a href="#">407</a>	A word-processing field is not a file.
<a href="#">420</a>	The index is missing.
<a href="#">501</a>	The file does not contain that field.
<a href="#">520</a>	That kind of field cannot be processed by this utility.
<a href="#">8090</a>	Pre-lookup transform (7.5 node).
<a href="#">8095</a>	First lookup index is compound, so "M"ultiple index lookups not allowed.

The Finder can also return any error returned by [\\$\\$EXTERNAL^DILFD](#).

### 3.5.9.3 Details and Features

The details and features of [\\$\\$FIND1^DIC](#) and [FIND^DIC](#) are the same *except* that [FIND^DIC](#) has the following three features that [\\$\\$FIND1^DIC](#) does *not* have:

- HTML Encoding
- WRITE ID nodes
- Repeating a field in FIELDS parameter

The following describes the details and features of [\\$\\$FIND1^DIC](#).

#### 3.5.9.3.1 Lookup Index

If the **Use** flag for an index entry in the INDEX (#.11) file is set to **L** for Lookup, the index name *must* be **B** or *must* alphabetically follow **B**. Also, traditional indexes whose names follow **B** are considered to be Lookup type indexes.


What does this mean? For a Finder call ([FIND^DIC](#) or [\\$\\$FIND1^DIC](#)), it means that if **M** is passed in the **flags** parameter and a list of indexes is *not* specified in the **indexes** parameter, then VA FileMan automatically uses any lookup type index it finds by ordering through the index name alphabetically, starting with the beginning index ("**B**", unless a different one is specified in the input parameters). Any index, however, can be used for lookup if it is specified in the **indexes** parameter. The developer should be careful to make sure the MUMPS-type indexes are formatted similar to VA FileMan regular indexes, with the data subscripts followed by the IEN at the level of the file/subfile passed in the **file** input parameter.

#### 3.5.9.3.2 Screens Applied

[Table 47](#) lists the VA FileMan screens that are applied:

**Table 47: \$\$FIND1^DIC API—Screens Applied**

Screen	Description
Valid Entry Conditions	To be considered for selection, an entry <i>must</i> have a properly formatted index to get the Finder's attention and a defined zero-node with a <i>non</i> -null first piece.
File Pre-Lookup Action (7.5 Node)	Prior to performing any search of the database whatsoever, the Finder executes the <b>7.5</b> node for the file. This code can alter the variable <b>X</b> , the lookup value, to alter the value used by the Finder in

Screen	Description
	its search.   <b>NOTE:</b> The <b>7.5</b> node only works on a simple index, <i>not</i> a compound one. It assumes just one lookup value <b>X</b> .
Call Pre-Selection Action	The <b>screen</b> parameter is executed once a potential match has been identified (as described under the <a href="#">“Input Parameters”</a> section).
File Pre-Selection Action	If the file has a pre-selection action defined (the <b>SCR</b> node), then after passing the pre-selection action for the call, the entry <i>must</i> also pass the action for the whole file.

### 3.5.9.3.3 Partial Matches

For most values on most indexes, an input value partially matches an entry if the index value begins with the input value (e.g., index value of “FMUSER,ONE” partially matches input value of “FMUSER”). The exception is numeric input. On a numeric field’s index, a numeric input *must* match exactly.

If the lookup value is numeric but the cross-referenced field is free-text, the Finder finds all partial matches to the numeric lookup value. For example, lookup value 1 matches to 1, 199, 1000.23, and 1ABC.

### 3.5.9.3.4 Spacebar Recall

Although the Finder honors the **Spacebar Recall** feature whenever passed the input value “”, selections made through the Finder are *not* stored for later use by **Spacebar Recall**, because the Finder has no way of knowing whether the selection results from interaction with the user. Only deliberate user selections should affect the **Spacebar Recall** value. As a result, to support this feature, applications should call [RECALL^DILFD](#) when managing the user interface whenever the user makes a selection.

### 3.5.9.3.5 Lookup Value Transforms List

The original lookup values passed to the Finder are not the only values used during the lookup. Certain transforms are done on the original lookup value and matches are made for these transformed values along with the original ones. The **Q** flag suppresses all of these transforms and looks on the indexes only for the original lookup value.



**REF:** For more information, see the [“Uppercase”](#), [“Long Input”](#), [“Comma-Piecing”](#) and [“Data Type Transforms”](#) sections.

### 3.5.9.3.6 Uppercase

The first basic transform ensures that lookups succeed when users leave their **Caps Lock** keys off. If the **value** parameter contains any lowercase characters, the Finder also looks for an all-uppercased version of the value.

### 3.5.9.3.7 Long Input

The second basic transform ensures that lookups work properly when lookup and field values are longer than the maximum length of a data-values subscript in the index. This is **30** characters for traditional indexes, but is set by the developer for indexes defined in the INDEX (#.11) file.

### 3.5.9.3.8 Comma-Piecing

The third and final basic transform provides a special feature of VA FileMan’s lookup. This feature, known as comma-piecing, helps the user enter fewer characters to distinguish between similar entries. VA FileMan uses lookup values that contain embedded commas to build a pattern match based on all the comma-pieces. For example, distinguishing between “MFUSER,ONE FRANCIS” and “FMUSER,TWO FITZGERALD” would normally take eight keystrokes— “FMUSER,O”—but comma-piecing lets the user do it in three: “F,O”.

Although commas are used to trigger the comma-piecing feature, the characters used to break up the entry in the file can be any kind of punctuation, not only commas. For example, “T,R” matches “THE ROAD LESS TRAVELED”.

If the **C** flag is used in the **flags** parameter, then the second comma piece of the lookup value can be a match to any of the pieces in the file entry following the first one. So, for example, “F,S” distinguishes “FMUSER,ONE SEBASTIAN” from his sons “ FMUSER,ONE CHRISTIAN” and “ FMUSER,ONE CHRISTOPH FRIEDRICH”.

### 3.5.9.3.9 Data Type Transforms

Indexes store the VA FileMan internal format of field values, but users typically enter the external format as lookup values. Therefore, the Finder attempts to do conversions of the lookup values when it searches an index on a field of data type:

- DATE
- SET OF CODES
- POINTER
- VARIABLE POINTER

For example, a lookup value of **t** would also be evaluated as today’s date in internal VA FileMan format, if the Finder is searching the index on a date type field, since VA FileMan normally recognizes a user entry of **T** at a date prompt as meaning “**TODAY**”.

If a **Q** flag is passed in the **flags** parameter, no data type transforms are attempted.



**NOTE:** The data type transform for indexes on pointer and variable pointer fields involves a complete lookup on the pointed-to file. For example, if an application calls the Finder with the input value **W** on a file with an indexed pointer to the STATE (#5) file, the Finder locates every state starting with **W** (Washington, West Virginia, Wisconsin and Wyoming). It returns every record in the pointing file that points to one of those states.

Also, if the pointed-to file has indexed pointers or variable pointers, the search continues to these pointed-to files.

Therefore, to make more efficient searches, and to find just the entries desired, applications should make use of all available features of the Finder to narrow down the search. For example, use the **indexes** parameter when appropriate to limit the list of indexes searched, and the **B** flag when appropriate to make sure that only the “**B**” index is searched on any pointed-to file.

### 3.5.10 LIST^DIC(): Lister

The LIST^DIC API (aka Lister) returns a sorted list of entries from a file. Callers *must* specify a file number. Callers can also specify any of the following:

- Index to be used in sorting the output.
- Starting location.
- Number of records to retrieve.
- Partial match value.

They can also pass screening logic. By default, the Lister returns the:

- **.01** field of the entries, along with the index values used to retrieve them.
- All identifiers for the entries.

The developer can override the default output and return other information for the entries.

This call is designed to populate a GUI Listbox gadget. It merely returns a list of entries from an index. Starting values *must* be in the same format as the index, unlike a lookup that allows search values to be in external format. The caller can make an initial call to the Lister to return a number of records *n* from the file and follow that by subsequent calls to return the next *n* records.



**NOTE:** The VA FileMan Database Server (DBS) APIs typically work like their VA FileMan Classic counterparts. However, the DBS APIs listed below *do not* perform numeric lookups the way the classic [^DIC](#) API does:

- [FIND^DIC\(\): Finder](#)
- [\\$\\$FIND1^DIC\(\): Finder \(Single Record\)](#)
- LIST^DIC(): Lister

Rather, these three APIs perform numeric lookups the way [^DIC](#) performs them when the lowercase **n** flag is set.

**REF:** For information on the use of the lowercase **n** flag in conjunction with the **DIC(0)** input variable, see the “[^DIC: Lookup/Add](#)” section in the “[Classic VA FileMan API](#)” section.


#### Format

```
LIST^DIC(file[,iens][,fields][,flags][,number][,[.]from][,[.]part][,index][,[.]screen][,identifier][,target_root][,msg_root])
```

#### Input Parameters

- file:** (Required) The file whose entries are to be listed. This should equal the file or subfile number, depending on what the caller wishes to list.
- iens:** (Optional) If the **file** parameter equals a file number, the Lister ignores the **iens** parameter. If the **file** parameter equals a subfile number, the Lister needs the **iens** parameter to help identify which subfile to list. In other words, files can be specified with the **file** parameter alone, but subfiles require both the **file** and **iens** parameters.
- When the **iens** parameter is used, it *must* equal an IENS that identifies the parent record of the exact subfile to list. Since this parameter identifies the subfile under

that record, and *not* the subrecord itself, the first comma-piece of the parameter should be empty. If the first comma-piece of the IENS is *not* empty, that first comma-piece is ignored.


 **REF:** For more information on the IENS, see the discussion in the DBS “[Introduction](#)” and “[IENS: Identify Entries and Subentries](#)” sections.

For example, to specify the MENU ITEM subfile under option number 67, you *must* pass FILE = 19.01 (the subfile number for the MENU subfile) and IENS = “;67,” (showing that record number 67 holds the MENU subfile you want to list).

Defaults to empty string.

fields:


(Optional) The fields to return with each entry found. This parameter can be set equal to any of the specifications listed below. The individual specifications should be separated by semicolons (;).

 **NOTE:** In most cases, a developer wants to include the @ specifier (described below) to suppress the default output values normally returned by the Lister and then specify the fields and other elements to return here in the **fields** parameters. This gives the developer full control over exactly what is returned in the output list and makes the call more self-documenting in the developer’s code.


- **Field Number**—This specifier makes the Lister return the value of the field for each record found. For example, specifying **.01** returns the value of the **.01** field. You can specify computed fields. You *cannot* specify word-processing or Multiple fields. By default, fields are returned in external format. The **I suffix** (described below) can be appended to the field number to get the VA FileMan internal format of the field.

If a field is listed multiple times in the **fields** parameter, it is returned multiple times in packed output, but only once in unpacked output, since the field number is one of the subscripts of the unpacked output.

- **Computed Expression**—This specifier causes the Finder to return the result of a computed expression.

 **REF:** For more information on computed expression syntax, see the “Computed Expressions” section in the *VA FileMan Advanced User Manual*.

- **IX**—This returns, for each record, the values from the index used in the call. If a subscript in the index is derived from a field, the external format of that field is returned by default. Otherwise, the value is returned directly as it appears in the index. The **I suffix** (described below) can be appended to **IX** to get the internal index values. The index values are returned in the “**ID**” nodes as described in the “[Output](#)” section.

 **NOTE:** For records located on a mnemonic index entry, the value from the index entry is always returned, rather than its corresponding external field value.



- **FID**—This returns the fields display identifiers (i.e., field identifiers). By default, the field values are returned in external format. The **I suffix** (described below) can be appended to **FID** to get the VA FileMan internal format of the field identifiers.
- **WID**—This returns the fields WRITE (display only) identifiers. The Lister executes each WRITE identifier’s M code and copies contents of ^TMP(“DIMSG”, \$J) to the output. You *must* ensure that the WRITE identifier code issues no direct I/O, but instead calls [EN^DDIOL](#).



**NOTE:** The **I suffix**, described below, *cannot* be used with **WID** and generates an error.

- **.E suffix**—You can append an **E** to a field number, the specifier **IX**, or the specifier **FID** to force the fields to be returned in external format. You can use both the **E** and **I suffix** together (e.g., **.01EI**) to return both the internal and external values of the field.
- **.I suffix**—You can append an **I** to a field number, the specifier **IX**, or the specifier **FID** to force the fields to be returned in VA FileMan internal format. You can use both the **E** and **I suffix** together (e.g., **.01IE**) to return both the internal and external value of the field.
- **- prefix**—A minus sign (-) prefixing one of the other field specifiers tells the Lister to exclude it from the returned list. This could be used, for example, in combination with the **FID** specifier to exclude one of the identifier fields. For example, if Field #2 was one of the field identifiers for a file, “FID;-2” would output all of the field identifiers except for Field #2.
- **@**—This suppresses all the default values normally returned by the Lister, except for the IEN and any fields and values specified in the **fields** parameter. It is *recommended* that developers *always* use the **@** specifier in their Lister calls. Use of the **@** specifier allows the developer to control exactly what is returned in the output.



**REF:** To see what is normally returned by the Lister, see the “[Default Values](#)” section.

### Default Values:

If you *do not* pass a **fields** parameter, the Lister returns:

- IEN.
- Indexed field value, in external format.



**NOTE:** For mnemonic cross-referenced entries, this would be the mnemonic subscript, *not* a field value.

- **.01** field, in external format, if the indexed field value is *not* **.01**.
- Any field display identifiers.
- Any WRITE (display-only) identifiers.

- Results of executing the Lister’s **identifier** parameter.

If you *do* pass a **fields** parameter but it does *not* contain the @ specifier, the Lister returns:

- IEN.
- Indexed field value, in external format.



**NOTE:** For mnemonic cross-referenced entries, this would be the mnemonic subscript, *not* a field value.

- **.01** field, in external format, if the indexed field value is *not* **.01**.
- Fields and values specified by the **fields** parameter.
- Any WRITE (display-only) identifiers.
- Results of executing the Lister’s **identifier** parameter.

flags:

(Optional) Flags to control processing:

- **B—Backwards.** Traverses the index in the opposite direction of normal traversal.
- **E—Errors are ignored.** When returning external values without the **E** flag, results will be truncated if invalid data (e.g., an incorrect code in a set of codes field) is encountered. An error will be produced. The **E** flag suppresses the error and continues the reporting of results. The data value for the entry with invalid data is set to null.

If internal values for a field are being returned, the value stored in the database for the field will be returned even if that value is invalid whether or not the **E** flag is set.

To assure that every entry is returned regardless of the validity of the data, set the **E** flag.

- **I—Internal format is returned.** All output values are returned in VA FileMan internal format (the default is external). Because the **I suffix** can be used in the **fields** parameter to return information in VA FileMan internal format, using **I** in the **flags** parameter is virtually obsolete. It greatly simplifies the call to use the @ specifier in the **field** parameter to suppress return of default values, and to specify in the **fields** parameter exactly what other data elements are to be returned. You can use the **I suffix** to have them returned in VA FileMan internal format.
- **K—Primary Key** used for default index.
- **M—Mnemonic suppression.** Tells the Lister to ignore any mnemonic cross-reference entries it finds in the index.
- **P—Pack output.** This flag changes the Lister’s output format to pack the information returned for each record onto a single node per record.



**REF:** For more details, see the information in the “Output”, “Details and Features,” and “Examples” sections.

- **Q**—Quick List. If this flag is passed, the Lister uses the order of the index to return the output, rather than sorting the information into a more user-friendly order. This makes a difference when doing Lister calls where the index value is a pointer or variable pointer. The call is more efficient but the output may *not* be in an intuitive order.

When the **Q** flag is used, both the **from** and **part** parameters *must* be in the same format as the subscripts found in the index whose name is passed in the **index** parameter. In the case of a pointer, for example, the **from** and **part** parameters would be an internal pointer value.



**REF:** For more information, see the description of the **from**, **part**, and **index** parameters.

- **U**—Unscreened lookup. This flag makes the Lister ignore any whole file screen [stored at `^DD(file#,0,"SCR")`] on the file specified in the **file** parameter.



**NOTE:** Passing this flag does *not* make the Lister ignore any code passed in the **screen** parameter.

- **X**—If **X** flag is used then the **index** parameter can be any of the following:
  - [Field](#)
  - [Sort Template](#)
  - [Computed Expression](#)
  - Field #1:

```
>K TMP D LIST^DIC(5,, ".01", "X", 3, "I", , 1, , , "TMP") ZW TMP
TMP ("DILIST", 0) = "3^3^1^"
TMP ("DILIST", 0, "MAP") = ".01"
TMP ("DILIST", 1, 1) = "IA"
TMP ("DILIST", 1, 2) = "ID"
TMP ("DILIST", 1, 3) = "IL"
```

- Sort Template:

```
>D LIST^DIC(5,, ".01;COUNT(COUNTY)", , , , "[ZZD STATE SORT
3]", , , "TMP")
ZW TMP
TMP ("DILIST", 0) = "82^*^0^"
TMP ("DILIST", 0, "MAP") = ".01^C2"
TMP ("DILIST", 1, 1) = "ALABAMA"
TMP ("DILIST", 1, 2) = "ALASKA"
TMP ("DILIST", 1, 3) = "ALBERTA"
TMP ("DILIST", 1, 4) = "AMERICAN SAMOA"
```

- Computed Expression:

```

>K TMP D LIST^DIC(5,, ".01", "X", 3, "A",, "AB",, "TMP") ZW TMP
TMP ("DILIST", 0) = "3^3^1^"
TMP ("DILIST", 0, "MAP") = .01
TMP ("DILIST", 1, 1) = "AA"
TMP ("DILIST", 1, 2) = "AB"
TMP ("DILIST", 1, 3) = "AE"

```

number: (Optional) The number of entries to return. If the Lister reaches the end of its list, the number of entries output can be fewer than this parameter. A value of asterisk (\*) or no value in this parameter designates *all* entries. The developer has the option to make multiple calls to the Lister, in order to control the number of records returned. In that case, the **from** value (described below) *must* be passed by reference, and should *not* be altered between calls. The Lister returns, in the **from** parameter, the values needed to find the next record on a subsequent call.

Defaults to asterisk (\*).

[.]from: (Optional) The index entries from which to begin the list (e.g., a **from** value of **XQ** would list entries following **XQ**). The **from** values *must* be passed as they appear in the index, *not* in external value. The index entry for the **from** value itself is *not* included in the returned list.

If the **index** parameter specifies a compound index (i.e., one with more than one data-valued subscript), then the **from** parameter should be passed by reference as an array; where **FROM(n)** represents the *n*th subscript on the compound index. This array helps VA FileMan find a single entry in the index. Generally, the developer can set the **FROM** array to establish a starting point from which the Lister should traverse the index. However, the **FROM** array is especially useful when making multiple calls to the Lister to return records in discrete chunks. The Lister sets the **FROM** array to information about the last record returned, so the developer can simply pass this array unchanged from one Lister call to the next to return the next set of records.

This parameter can contain an array node **FROM("IEN")**. This subscript can be set equal to a record number that identifies the specific entry from which to begin the list. This can alternately be passed as **FROM(m)** where *m* is equal to the number of data value subscripts in the index plus 1. This array entry would be passed only when there is more than one entry in the index with the same values in all of the data value subscripts. For example, using a regular single-field index on a NAME field, if there were two "FMUSER,ONE" entries in the file with IENs of 30 and 43, then passing **FROM(1)**="FMUSER,ONE" and either **FROM(2)** or **FROM("IEN")**=30 would return a list of entries starting with name of FMUSER,ONE and IEN of 43. If the list is built using the upright file (**index** parameter="#"), then **FROM**, **FROM(1)**, and **FROM("IEN")** would all be the same and would represent the starting internal entry number for the list.

When listing an index on a POINTER or VARIABLE POINTER field, the **FROM** value should equal a value from the "B" index at the end of the pointer chain, *not* a pointer value. However, the **FROM("IEN")** should still equal the number of a record in the pointing file as it does for other Lister calls. For example, suppose you have listed entries from a simple index that points to the STATE (#5) file and the previous call finished with entry 12 that points to Utah

(record 49 in the STATE [#5] file). Then **FROM(1)** would be set to “UTAH” and **FROM(“IEN”)** or **FROM(2)** would be set to 12. Again, you would only want to set **FROM(2)** if there were other entries in your file that pointed to Utah, with IENs that followed 12.

This parameter lets the caller make multiple calls to the Lister to return a limited number of records with each call, rather than one large one. If the **from** parameter values are passed by reference, then the Lister returns, in the **FROM** array, information that tells it which record to start with on subsequent Lister calls.

To start a new list, pass the **from** parameter undefined or equal to the empty string. This starts the list with the first entry in the index unless you are traversing the index backwards; in which case, it starts the list with the last entry in the index.



**REF:** For more help on how to use this parameter, see the “[Details and Features](#)” and “[Examples](#)” sections.

[.]part

(Optional) The partial match restriction. For example, a **part** parameter value of **DI** would restrict the list to those entries starting with the letters **DI**. Again, this value *must* be a partial match to an index value, *not* the external value of a field. This can be passed by reference and subscripted the same as the **from** parameter so that the **part** parameter values can be specified for any subscript in a compound index.

The **part** parameter is often a partial match to the **from** parameter. For example, **FROM(1)="ZTMMGR"**, and **PART(1)="ZTM"** would return only entries that began with **ZTM** and came after **ZTMMGR**. It would *not* include **ZTZERO**, even though it comes after **ZTMMGR**. (If traversing the index backwards, it would find only entries that came before **ZTMMGR**).

If the **from** parameter is passed and the **part** parameter is *not* a partial match to **from**, then the Lister returns all partial matches to **part** that come after **from**. Thus, if **FROM(1)="DI"** and **PART(1)="ZTM"**, then the Lister returns all partial matches to **ZTM**. If in this example you were traversing the index backwards, then the Lister would return nothing, because there would be nothing that came before **DI** and started with **ZTM**.

For indexes on POINTERS or VARIABLE POINTERS, the **part** parameter should refer to values on the “**B**” index of the pointed-to file at the end of the pointer chain. For example, if the index was on a field pointing to the STATE [#5] file, **PART(1)** could be set to **A** to find all states whose name begins with **A**.

index:

(Optional) The name of the index from which to build the list. For example, setting this to **C** could refer to the **Upper Case Menu Text** index on the OPTION (#19) file. Whether the specified index is simple (single data-value subscript like the “**B**” index on most files) or compound (more than one data-value subscript) affects the **from** and **part** parameters as previously described.

If the index is *not* specified, the default is **B** unless the **flags** parameter contains a **K**, in which case, the default is the Uniqueness Index defined for the Primary Key on the file.

If there is no “**B**” index and either **B** is passed in the **index** parameter or is the default index, then a temporary index is built on the file (which could take some time). The index is removed after the Lister call.

If # is passed in the **index** parameter, then the list is built from the upright file (i.e., in order by internal entry number) rather than from an index. In that case, if a **from** value is passed, it should be an IEN and could be passed either as a literal or in **FROM(1)** or **FROM(“IEN”)**, all of which are equivalent (see **from** parameter above).

Unless the **M** flag is used to suppress them, mnemonic cross-references folded into the specified index are included in the output.



**NOTE:** Index can also be a [Field](#), [Sort Template](#), or [Computed Expression](#).

[.]screen:

(Optional) **Entry Screen.** The screen to apply to each potential entry in the returned list to decide whether or not to include it. This can be set to any valid M code that sets **\$TEST** to

- **1**—If the entry should be included.
- **0**—If the entry should *not* be included.

This is exactly equivalent to the **DIC(“S”)** input variable to Classic VA FileMan lookup [^DIC](#). The Lister executes this screen in addition to any SCR node (whole-file screen) defined for the file. Optionally, the screen can be defined in an array entry subscripted by **S** [for example, **SCR(“S”)**], allowing additional screen entries to be defined for variable pointer fields as described below.

The Entry Screen code can rely upon the following:

- **Naked Indicator**—Zero-node of entry’s record.
- **D**—Index being traversed.
- **DIC**—Open global reference of file being traversed.
- **DIC(0)**—Flags passed to the Lister.
- **Y**—Record number of entry under consideration.
- **Y() Array**—For subfiles, descendants give record numbers for all upper levels. Structure resembles the **DA** array as used in a call to the Classic VA FileMan edit routine [^DIE](#).
- **Y1**—IENS equivalent to **Y** array.

The **screen** parameter can safely change any of these values. For example, suppose there is a set of codes field defined as the 5<sup>th</sup> piece of the **0** node on the file, and you only want to find entries that have the value **Y** in that field. Then the code might look like “**I \$P(^0,U,5)=“Y”**”. All other variables used, however, *must* be carefully namespaced.

Defaults to no extra screening.

**Variable Pointer Screen.** If one of the fields indexed by the cross-reference passed in the **index** parameter is a VARIABLE POINTER, then additional screens equivalent to the **DIC(“V”)** input variable to Classic VA FileMan lookup [^DIC](#) can also be passed. Suppose the screens are being passed in the **SCR** array.

Then for a simple index with just one data value field, the code can be passed in **SCR("V")**. For simple or compound indexes, screens can be passed for any indexed fields that are variable pointers in the format **SCR("V",n)** where *n* represents the subscript location of the variable pointer field on the index from the **index** parameter.

The Variable Pointer screen restricts the user's ability to see entries on one or more of the files pointed to by the variable pointer. The screen logic is set equal to a line of M code that returns a truth value when executed:

- **TRUE**—If it evaluates **TRUE**, then entries that point to the file can be included in the output.
- **FALSE**—If **FALSE**, then any entry pointing to the file is excluded.

At the time the code is executed, the variable **Y(0)** is set equal to the information for that file from the data dictionary definition of the variable pointer field. You can use **Y(0)** in the code set into the **DIC("V")** variable. [Table 48](#) lists the contents of **Y(0)**:

**Table 48: LIST^DIC API—Variable Pointer screen—Y(0)**

^-Piece	Contents
Piece 1	File number of the pointed-to file.
Piece 2	Message defined for the pointed-to file.
Piece 3	Order defined for the pointed-to file.
Piece 4	Prefix defined for the pointed-to file.
Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.
Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed to file.

All of this information was defined when that file was entered as one of the possibilities for the VARIABLE POINTER field.

For example, suppose your **.01** field is a VARIABLE POINTER pointing to (fictitious) Files #1000, #2000, and #3000. If you only want the user to be able to enter values from (fictitious) Files #1000 or #3000, you could set up **DIC("V")** like this:

```
S DIC("V")="I +Y(0)=1000!(+Y(0)=3000)"
```

identifier:

(Optional) The text to accompany each potential entry in the returned list to help identify it to the end user. This can be set to any valid M code that calls the [EN^DDIOL](#) utility to load identification text. The Lister lists this text *after* that generated by any M identifiers on the file itself. This parameter takes and can change the same input as the **screen** parameter.

For example, a value of "D EN^DDIOL("KILROY WAS HERE!")" would include that string with each entry returned as a separate node under the "ID", "WRITE" nodes of the output array.

This parameter should issue no READ or WRITE commands itself nor should it call utilities that issue READs or WRITEs (except for [EN^DDIOL](#) itself).

Defaults to no extra identification text.



**REF:** For more information, see the description of [EN^DDIOL](#).

**target\_root:** (Optional) The array that should receive the output list. This *must* be a closed array reference and can be either local or global. For example, if **target\_root** equals OROUT(42), the output list appears in OROUT(42,“DILIST”).

If the **target\_root** is *not* passed, the list is returned descendent from ^TMP(“DILIST”,\$J).

**msg\_root:** (Optional) The array that should receive any error messages. This *must* be a closed array reference and can be either local or global. For example, if **msg\_root** equals “OROUT(42)”, any errors generated appear in OROUT(42,“DIERR”).

If the **msg\_root** is *not* passed, errors are returned descendent from ^TMP(“DIERR”,\$J).

## Output and Output Parameters

**from:** See the **from** parameter under “[Input Parameters](#).” If the **from** parameter is passed by reference and if there are more entries to return in the list, then the **FROM** array is set to information about the last entry returned in the current Lister call. Subsequent Lister calls use this information to know where to start the next list.

Other than **FROM(1)**, none of the other **from** values from the index contains data unless the next entry to return has the same index value as the last entry returned by the current Lister call. For example, if the index is on NAME and DATE\_OF\_BIRTH: if the last entry returned was for “FMUSER,ONE” and there is only one “FMUSER,ONE” in the file, then **FROM(1)**=“FMUSER,ONE”, **FROM(2)**= “”, and **FROM(3)**= “”. However, if there is another “FMUSER,ONE”, with a different DOB, then you might have **FROM(1)**=“FMUSER,ONE” and **FROM(2)**=2690101. If there are two “FMUSER,ONE” entries with the same DOB, then **FROM(1)**=“FMUSER,ONE”, **FROM(2)**=2690101, and **FROM(3)**=the IEN of the last entry output.

**target\_root:** The examples in this section assume that the output from the Lister was returned in the default location descendent from ^TMP(“DILIST”,\$J), but it could just as well be in an array specified by the caller in the **target\_root** parameter described above.

There are two different formats possible for the output:

- [Standard Output Format](#)
- [Packed Output Format](#)  
(returned when the **P** flag is included in the **flags** parameter)



## Standard Output Format

The format of the Output List is:

- **Header Node**

Unless the Lister has run into an error condition, it *always* returns a header node for its output list, even if the list is empty because no matches were found. The header node on the zero node of the output array, has this format:

```
^TMP("DILIST",$J,0) = # of entries found ^ maximum requested ^ any more?
^ results flags
```

- The # of entries found is equal to or less than the maximum requested.
- The maximum requested should equal the **number** parameter, or, if **number** was *not* passed \*.
- The **any more?** value is:
  - 1—If there are more matching entries in the file than were returned in this list.
  - 0—If there are *no* more matching entries in the file than were returned in this list.
- The results flags at present is usually empty. If the output was packed, and some of the data contained embedded ^ characters, the results flag contains the flag **H**. Check for the results containing **H** rather than results equal to **H**.



**REF:** For more information, see “[Details and Features.](#)”

- **Record Data**

Standard output for the Lister returns each field of each matching record on a separate node. Records are subscripted in this array by arbitrary sequence number that reflects the order in which the record was found.

- Indexed Field (Simple Index):

Unless suppressed with the @ in the **fields** parameter (the suggested practice), the indexed values are returned descendent from the **1** nodes in external format.

```
^TMP("DILIST",$J,1,seq#) = index_value
```



**NOTE:** This is different from the Finder, which returns the **.01** field value in the **1** subtree.

- Indexed Field (Compound Index):

If the Lister call used a compound index, an additional sequential integer reflects the subscript position at which the value was found.

```
^TMP("DILIST",$J,1,seq#,1) = first_subscript_index_value
^TMP("DILIST",$J,1,seq#,2) = second_subscript_index_value
```

- IEN:

Each record's IEN is returned under the **2** subtree:

```
^TMP("DILIST", $J, 2, seq#) = IEN
```

The other values returned for each record are grouped together under the "**ID**" subtree, then by record.

- Field Values or Field Identifiers:

The output format is the same whether the field value is one of the Field Identifiers from the data dictionary for the file, or the field was requested in the **fields** parameter. In addition, if the **.01** field is *not* one of the indexed fields and is *not* suppressed by use of **@** in the **fields** parameter, then it is also returned along with the other field values. By default, field values are returned in external format.

Field identifiers and field values are subscripted by their field numbers. Each node shows up as:

```
^TMP("DILIST", $J, "ID", seq#, field#) = field_value
```

Fields default to external format unless **I** is passed in the **flags** parameter (obsolete) or the **I suffix** is specified in the **fields** parameter (*recommended* way to get internal field values).

If both the **I** and **E suffix** are specified, an additional subscript level with the values of **E** and **I** is used to distinguish the external and internal values of the field. If a field is only returned in one format, the extra subscript is *never* included. Values output with the extra format specifier look like:

```
^TMP("DILIST", $J, "ID", seq#, field#, "E" or "I") = field_value
```

- Output for field specifier **IX** in **fields** parameter:

A field specifier of **IX** in the **fields** parameter retrieves the value of the indexed fields. In the output, the values of these fields are returned as follows, where the final subscript is a sequential number indicating the subscript location in the index.

```
^TMP("DILIST", $J, "ID", seq#, 0, 1) = first_subscript_index_value
^TMP("DILIST", $J, "ID", seq#, 0, 2) = second_subscript_index_value
```

If both the **I** and **E suffix** are specified, an additional subscript level with the values of **E** and **I** is used to distinguish the external and internal values from the index. If the subscript on the index is *not* derived from a field (i.e., if it's a computed subscript, then the internal and external value is both the same, the value directly from the index).

- WRITE Identifiers:

WRITE (display-only) identifiers are grouped under the “**WRITE**” subtree of the “**ID**” tree, then by record number. It is the caller’s responsibility to ensure that none of the WRITE identifiers issue direct READ or WRITE commands and that they issue any output through [EN^DDIOL](#) so it can be collected by the Lister. The output from all the WRITE identifiers for a single record is listed as individual lines of text:

```
^TMP( "DILIST", $J, "ID", "WRITE", seq#, line #) = text generated by WRITE IDs
```

- The **identifier** parameter:

Any text generated by the caller’s **identifier** parameter is returned in the last lines of the WRITE identifier text.

- **MAP Node for Unpacked Format**

In order to facilitate finding information in the output, a MAP node is built for unpacked format. This node is returned in ^TMP(“**DILIST**”, \$J, 0, “**MAP**”).

The MAP node for unpacked format describes what Field Identifier data can be found in the “**ID**” output data nodes. It contains ^-delimited pieces described below. The position of the piece in the MAP node corresponds to the order in which it can be found in the “**ID**” output nodes. If the data is returned in VA FileMan internal format, the piece is followed by **I** (e.g., “**2I**” means that the internal value of Field #2 was returned in the output).

- #—Individually requested field number, where # is the field number, for each field requested in the FIELDS parameter.
- **FID(#)**—Field Identifier, where # is the field number.

## Packed Output Format

If the **P** flag is used to request packed output, the Lister packs all the return values into one output node per record. You *must* ensure that all requested data will fit onto a single node. Overflow causes [error 206](#). Return values containing embedded ^ characters make the Lister encode the output data using HTML encoding (see “[Details and Features](#)”).

- **Header Node**

Identical to Standard Output Format.

- **Record Data**

Values in the output are delimited by ^ characters. Piece **1** is always the IEN. The values of other pieces depend on the value of the **fields** parameter. If the **fields** parameter is *not* passed, each record’s packed node follows this format:

```
^TMP( "DILIST", $J, seq#, 0) = IEN^Indexed_field_
values^field_Identifier^Write_Identifier^
Output_from_Identifier_parameter
```

Field Identifiers are sequenced by field number. Output values specified by the **fields** parameter are packed in the order in which they occur in the **fields** parameter. WRITE identifiers are packed in the same order as their subscripts occur in the **ID** subtree of the file’s data dictionary.

To parse the output of the packed nodes, use the MAP node described below.

- **MAP Node for Packed Format**

Because the packed format is *not* self-documenting and because individual field specifiers such as **FID** can correspond to a variable number of field values, the Lister *always* includes a MAP node when returning output in Packed format. This node is returned in `^TMP("DILIST", $J, 0, "MAP")`.

Its value resembles a data node's value in that it has the same number of ^-pieces, but the value of each piece identifies the field or value used to populate the equivalent location in the data nodes. The possible values for each piece in the MAP node are:

- **IEN**—The IEN.
- **.01**—The **.01** field.
- **FID(#)**—Field identifier, where # is the field number of the identifier.
- **WID(string)**—Write identifier, where string is the value of the subscript in the ^DD where the identifier is stored (e.g., "**WRITE**").
- **IDP**—Identifier parameter.
- **IX(n)**—Indexed field values, where *n* refers to the subscript position in the index.
- **#**—Individually requested field, by field number.



**NOTE:** For any piece except **IEN**, the **WID**, or the **IDP**, if the internal value is to be returned, the piece is followed by **I**. Thus, instead of "**IX(1)**", you would have "**IX(1)I**", indicating that the internal index value was being returned.

For example, the MAP node for a Lister call on the OPTION (#19) file, if **fields =>** "3.6I;3.6;4", might look like this:

```
^TMP("DILIST", $J, 0, "MAP") = "IEN^.01^3.6I^3.6^4"
```

### 3.5.10.1 Examples

#### 3.5.10.1.1 Example 1

[Figure 156](#) is an example of a forward traversal of the “B” index on the OPTION (#19) file, limited to five entries that all begin with the characters “DIFG”, but skipping any first entry that might equal “DIFG” (the **from** parameter value is always skipped):

**Figure 156: LIST^DIC API—Example 1: Input and Output**

```
>D LIST^DIC(19,"","","B",5,"DIFG","DIFG","","","OUT")

OUT("DILIST",0)=5^5^1^
OUT("DILIST",0,"MAP")=FID(1)
OUT("DILIST",1,1)=DIFG CREATE
OUT("DILIST",1,2)=DIFG DISPLAY
OUT("DILIST",1,3)=DIFG GENERATE
OUT("DILIST",1,4)=DIFG INSTALL
OUT("DILIST",1,5)=DIFG SPECIFIERS
OUT("DILIST",2,1)=321
OUT("DILIST",2,2)=322
OUT("DILIST",2,3)=323
OUT("DILIST",2,4)=326
OUT("DILIST",2,5)=325
OUT("DILIST","ID",1,1)=Create/Edit Filegram Template
OUT("DILIST","ID",2,1)=Display Filegram Template
OUT("DILIST","ID",3,1)=Generate Filegram
OUT("DILIST","ID",4,1)=Install/Verify Filegram
OUT("DILIST","ID",5,1)=Specifiers
```

#### 3.5.10.1.2 Example 2

[Figure 157](#) is a related example revealing that there is a DIFG option (Filegrams option). When you traverse backward, starting with the first entry from the previous example, DIFG is the only option that meets both the **from** and **part** parameter criteria. The sequence number is 5. When you traverse an index backward to get a set number of records, the sequence number counts backward from that number in order to make the output come out in the same order as when you traverse forward. This type of Lister call is normally used in a GUI ListBox when the user is backing up on a list.

**Figure 157: LIST^DIC API—Example 2: Input and Output**

```
>D LIST^DIC(19,"","B",5,"DIFG CREATE","DIFG","","","OUT")

OUT("DILIST",0)=1^5^0^
OUT("DILIST",0,"MAP")=FID(1)
OUT("DILIST",1,5)=DIFG
OUT("DILIST",2,5)=327
OUT("DILIST","ID",5,1)=Filegrams
```

### 3.5.10.1.3 Example 3

In this example ([Figure 158](#)), you return just one entry from a file using a compound index. This index is on the **.01** field (NAME) and field **1** (DATE OF BIRTH). Note how the two index entries are returned in the **1** nodes. Also, note that this file has several field identifiers and WRITE identifiers. After the call, because there are two different entries in the file with a **.01** equal to “ADDFIFTEEN”, but different dates of birth, the **DIFR** array has been set up ready for a subsequent call. On this index, the DATE OF BIRTH field has a collation of “backwards”, so you see the most current date first in the output.

**Figure 158: LIST^DIC API—Example 3: Input and Output**

```
>K DIFR,DIPRT S DIPRT(1)="ADD"

>D LIST^DIC(662001,"","",",",1,.DIFR,.DIPRT,"BB","","OUT")

OUT("DILIST",0)=1^1^1^
OUT("DILIST",0,"MAP")=FID(2)^FID(4)^FID(10)
OUT("DILIST",1,1,1)=ADDFIFTEEN
OUT("DILIST",1,1,2)=JAN 03, 1997
OUT("DILIST",2,1)=17
OUT("DILIST","ID",1,2)=SEVENTEEN*
OUT("DILIST","ID",1,4)=MITTY,WALTER
OUT("DILIST","ID",1,10)=MAY 02, 1997@09:00
OUT("DILIST","ID","WRITE",1,1)=2970103
OUT("DILIST","ID","WRITE",1,2)=
OUT("DILIST","ID","WRITE",1,3)= FIRST LINE
OUT("DILIST","ID","WRITE",1,4)=
OUT("DILIST","ID","WRITE",1,5)= SECOND LINETHIRD LINE
OUT("DILIST","ID","WRITE",1,6)=SIXTHCODE

>ZW DIFR

DIFR=ADDFIFTEEN
DIFR(1)=ADDFIFTEEN
DIFR(2)=2970103
DIFR(3)=
DIFR("IEN")=
```

### 3.5.10.1.4 Example 4

However, if you do another Lister call on the same file, using the **DIFR** array that was passed back from the previous call, this time it returns two records ([Figure 159](#)). You get back the second record in the index with “ADDFIFTEEN” as the **.01** field, and the next one that follows it alphabetically. In this call, you suppressed the normal default values returned by the call, and instead asked for the index field values **IX**, the internal value of the field identifiers **FIDI**, both the internal and external values of field #3 (a SET OF CODES type field), and the external value of computed Field #8. All of this was done with entries in the **fields** parameter. As you see, Field #4 is a pointer, Field #10 is a variable pointer. Note how the **MAP** node describes what is found in the “**ID**” nodes.

**Figure 159: LIST^DIC API—Example 4: Input and Output**

```
>D LIST^DIC(662001,"","@;IX;FIDI;3IE;8","",2,.DIFR,.DIPRT,"BB","","","OUT")

OUT("DILIST",0)=2^2^1^
OUT("DILIST",0,"MAP")=IX(1)^IX(2)^FID(2)I^3^3I^FID(4)I^8^FID(10)I
OUT("DILIST",2,1)=15
OUT("DILIST",2,2)=14
OUT("DILIST","ID",1,0,1)=ADDFIFTEEN
OUT("DILIST","ID",1,0,2)=JAN 01, 1969
OUT("DILIST","ID",1,2)=FIFTEEN
OUT("DILIST","ID",1,3,"E")=SIXTHCODE
OUT("DILIST","ID",1,3,"I")=SIX
OUT("DILIST","ID",1,4)=1
OUT("DILIST","ID",1,8)=0
OUT("DILIST","ID",1,10)=327;DIC(19,
OUT("DILIST","ID",2,0,1)=ADDFOURTEEN
OUT("DILIST","ID",2,0,2)=JAN 01, 1949
OUT("DILIST","ID",2,2)=FOURTEEN
OUT("DILIST","ID",2,3,"E")=
OUT("DILIST","ID",2,3,"I")=
OUT("DILIST","ID",2,4)=
OUT("DILIST","ID",2,8)=32.6
OUT("DILIST","ID",2,10)=10;DIZ(662003,
```

### 3.5.10.1.5 Example 5

In this example ([Figure 160](#)), you use the **P** flag to return the next two records in Packed output format. You revert to letting the Lister return default values, rather than controlling them with the **fields** parameter, but it returns additional output by using the **identifier** parameter. Note that although you asked for two records, there was only one left that fit the **PART** criteria:

- First piece of the header node tells you one record was returned.
- Second piece tells you that two records were requested.
- Third piece tells you there are no records left that meet the criteria.

[Figure 160](#) illustrates what the **from** parameter values are set to going into the call:

**Figure 160: LIST^DIC API—Example 5: Input and Output**

```
DIFR=ADDFOURTEEN
DIFR(1)=ADDFOURTEEN
DIFR(2)=
DIFR(3)=
DIFR("IEN")=

>D LIST^DIC(662001,"","P",2,.DIFR,.DIPRT,"BB","","D EN^DDIOL("Hi there"),"
OUT")

OUT("DILIST",0)=1^2^0^
OUT("DILIST",0,"MAP")=IEN^IX(1)^IX(2)^FID(2)^FID(4)^FID(10)^WID(WRITE1)^WID(WRITE2)
^WID(WRITE3)^WID(WRITE4)^IDPOUT("DILIST",1,0)=16^ADDSIXTEEN^MAR 28, 1970^MA HERE
TOO^^DIFG^2700328^^ FIRST LINE~~ SECOND LINETHIRD LINE^Hi there
```

### 3.5.10.2 Error Codes Returned

[Table 49](#) lists the possible error codes returned with the LIST^DIC API:

**Table 49: LIST^DIC API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">202</a>	Missing or invalid input parameter.
<a href="#">205</a>	The File and IENS represent different subfile levels.
<a href="#">206</a>	The data requested for the record is too long to pack together.
<a href="#">207</a>	The value is too long to encode into HTML.
<a href="#">301</a>	The passed flags are missing or inconsistent.
<a href="#">304</a>	The IENS lacks a final comma.
<a href="#">306</a>	The first comma-piece of the IENS should be empty.
<a href="#">401</a>	The file does not exist.
<a href="#">402</a>	The global root is missing or not valid.
<a href="#">406</a>	The file has no .01 field definition.
<a href="#">407</a>	A word-processing field is not a file.
<a href="#">420</a>	The index is missing.
<a href="#">501</a>	The file does not contain that field.
<a href="#">520</a>	That kind of field cannot be processed by this utility.

The Lister can also return any error returned by the [\\$EXTERNAL^DILFD](#) API.



### 3.5.10.3 Details and Features

#### 3.5.10.3.1 Screens Applied

Aside from the optional screen parameter, the Lister applies one other screen to each index entry before adding it to the output list as follows: `^DD(file#,0,"SCR")`. Other screens, such as the **7.5** node and field-level screens on various data types, are *not* checked because they relate specifically to entry and editing, not selection.

#### 3.5.10.3.2 Output Transform

It is possible for any field with an output transform to sort differently than a user would expect. Although the value displayed is the output value, the value that determines its order is its internal value. When the **I** flag is used, the output transform is never executed, and the output always appears in the expected order.

#### 3.5.10.3.3 HTML Encoding

Since the Lister uses the `^` character as its delimiter for packed output, it *cannot* let any of the data contain that character. If any does, it will encode all of the data using an HTML encoding scheme.

In this scheme:

- All ampersand (&) characters are replaced with the substring “&amp;”.
- All caret (^) characters with the string “&#94”.

This keeps the data properly parsable and decodable. The data for all records found, *not* just the ones with embedded carets (^), is encoded if embedded carets (^) are found in the data of any of the records.

If the Lister has encoded the output, it includes an **H** flag in `^`-piece four of the output header node.

Data can be decoded using the VA FileMan library function call `$$HTML^DILE`(encoded string,-1). It can properly decode individual fields or complete packed data nodes.

#### 3.5.10.3.4 Pointers and Variable Pointers

The Lister treats indexes on fields of these two data types specially. For every other data type, the value of the indexed field is completely contained in the file indicated by the **file** parameter. For pointer and variable pointers, this is *not* the case. All index values come from the “**B**” index of the pointed-to file. The Lister uses the values in the pointed-to file, extending the search to the end of the pointer chain, to select records in the pointing file at the beginning of the chain.

For example, suppose the **file** parameter picks File A, and the **index** parameter picks the **X** index, a cross-reference on a pointer field. Suppose further that field points to File B, whose **.01** field points to File C, and File C’s **.01** is a SET OF CODES. Then, this Lister call selects records in File A (the pointing file) based on the index values it finds in File C (the pointed-to file).

The **from**(“**IEN**”), **screen**, and **identifier** parameters always apply to the pointing file, the one identified by the **file** parameter, because they deal with actual record selection. However, for pointers and variable pointers, the **from** and **part** parameters apply to the “**B**” index on the pointed-to file, since they deal with index values.

Variable pointers work similarly, except that their index values usually come from more than one pointed-to file.

#### 3.5.10.3.5 WRITE ID nodes

The Lister executes each individual WRITE ID node from the data dictionary. If an individual node results in creating multiple lines in the output from the `EN^DDIOL` calls it contains, then in Standard Output Format the results appear on multiple lines in the output array. Thus, there is *not* a direct correlation between the number of WRITE ID nodes and the number of nodes that are returned in the

output array of a Lister call for each record. In Packed output format, each WRITE ID node appears in a separate ^ piece and line feeds are designated with a tilde (~) character.

### 3.5.10.3.6 The from Parameter with Compound Indexes

The **from** parameter designates only a starting point on the index defined in the **index** parameter. For example, you have a compound index where the first subscript is a NAME and the second is a DATE OF BIRTH. Supposing that after a Lister call, **FROM(1)**="FMUSER,ONE" and **FROM(2)**="2690101. A subsequent Lister call assumes that there *must* be another entry with the name "FMUSER,ONE", but a date-of-birth that follows 1/1/69. Any other entries returned will have names that equal or follow FMUSER,ONE, but after processing all of the FMUSER,ONE entries, other output entries could have any date-of-birth. This is *not* like a sort where you say that you want only entries where the date-of-birth follows 1/1/69.

## 3.5.11 FIELD^DID(): DD Field Retriever

The FIELD^DID API retrieves the values of the specified field-level attributes for the specified field.

### Format

```
FIELD^DID(file,field[,flags],attributes,target_root[,msg_root])
```

### Input Parameters

- file: (Required) File or subfile number.
- field: (Required) Field name or number.
- flags: (Optional) Flags to control processing. The possible values are:
- **N**—No entry in the target array is created if the attribute is null.
  - **Z**—Word-processing attributes include **Zero (0)** nodes with text.
- attributes: (Required) A list of attribute names separated by semicolons. Full attribute names *must* be used. Following are the attributes that can be requested:
- AUDIT
  - AUDIT CONDITION
  - COMPUTE ALGORITHM
  - COMPUTED FIELDS USED
  - DATE FIELD LAST EDITED
  - DECIMAL DEFAULT
  - DELETE ACCESS
  - DESCRIPTION
  - FIELD LENGTH
  - GLOBAL SUBSCRIPT LOCATION
  - HELP-PROMPT
  - INPUT TRANSFORM
  - LABEL

- MULTIPLE-VALUED
- OUTPUT TRANSFORM
- POINTER
- READ ACCESS
- SOURCE
- SPECIFIER
- TECHNICAL DESCRIPTION
- TITLE
- TYPE
- WRITE ACCESS
- EXECUTABLE HELP

target\_root: (Required) The closed root of the array that should receive the attributes.

msg\_root: (Optional) The name of a closed root reference that is used to pass error messages. If *not* passed, ^TMP("DIERR", \$J) is used.

### Output Parameters

target\_root: The array is subscripted by the attribute names.

### 3.5.11.1 Example

**Figure 161: FIELD^DID API—Example: Input and Output**

```
>D FIELD^DID(999000, .01, "", "LABEL;TYPE", "TEST1")

>ZW TEST1
TEST1("LABEL")=NAME
TEST1("TYPE")=FREE TEXT
```

### 3.5.11.2 Error Codes Returned

[Table 50](#) lists the possible error codes returned with the FIELD^DID API:

**Table 50: FIELD^DID API—Error Codes Returned**

Code	Description
<a href="#">200</a>	There is an error in one of the variables passed.
<a href="#">202</a>	Missing or invalid input parameter.
<a href="#">301</a>	Flags passed are unknown or incorrect.
<a href="#">401</a>	The specified file or subfile does not exist.
<a href="#">403</a>	The file lacks a Header Node.
<a href="#">404</a>	The file Header Node lacks a file #.

Code	Description
<a href="#">501</a>	The field name or number does not exist.
<a href="#">505</a>	The field name passed is ambiguous.
<a href="#">510</a>	The data type for the specified field cannot be determined.
<a href="#">520</a>	An incorrect kind of field is being processed.
<a href="#">537</a>	Field has a corrupted pointer definition.

### 3.5.12 FIELDLST^DID(): DD Field List Retriever

The FIELDLST^DID API returns a list of field-level attributes that are supported by VA FileMan. It shows specifically which attributes the data dictionary (DD) field list retriever calls can return.

#### Format

```
FIELDLST^DID(target_root)
```

#### Input Parameters

target\_root: (Required) The root of an output array.

#### Output

target\_root: The descendants of the array root are subscripted by the attribute names. “**WP**” nodes indicate that the attribute consists of a word-processing field.

#### 3.5.12.1 Example

[Figure 162](#) is a partial capture of what is returned:

**Figure 162: FIELDLST^DID API—Example: Input and Output**

```
>D FIELDLST^DID("TEST")

>ZW TEST
TEST("AUDIT")=
TEST("AUDIT CONDITION")=
TEST("COMPUTE ALGORITHM")=
TEST("COMPUTED FIELDS USED")=
.
.
.
```

### 3.5.13 FILE^DID(): DD File Retriever

The FILE^DID API retrieves the values of the file-level attributes for the specified file. It does *not* return subfile attributes.

#### Format

```
FILE^DID(file[, flags], attributes, target_root, msg_root)
```

#### Input Parameters

- file: (Required) File number (but *not* subfile attributes).
- flags: (Optional) Flags to control processing. The possible values are:
- **N**—No entry in the target array is created if the attribute is null.
  - **Z**—Word-processing attributes include **Zero (0)** nodes with text.
- attributes: (Required) A list of attribute names separated by semicolons. Full attribute names *must* be used:
- ARCHIVE FILE
  - AUDIT ACCESS
  - DATE
  - DD ACCESS
  - DEL ACCESS
  - DESCRIPTION
  - DEVELOPER
  - DISTRIBUTION PACKAGE
  - ENTRIES
  - GLOBAL NAME
  - LAYGO ACCESS
  - LOOKUP PROGRAM
  - NAME
  - PACKAGE REVISION DATA
  - REQUIRED IDENTIFIERS
  - RD ACCESS
  - VERSION
  - WR ACCESS
- target\_root: (Required) The name of a closed array reference.
- msg\_root: (Optional) The name of a closed root array reference that is used to pass error messages. If *not* passed, messages are returned in ^TMP(“DIERR”,\$J).

## Output Parameters

target\_root: The array is subscripted by the attribute names. Some attributes can have multiple sub-attributes and these are further subscripted with a sequence number and the sub-attribute name. Attributes that contain word-processing text also have a sequence number for each line of text.

### 3.5.13.1 Example

**Figure 163: FILE^DID API—Example: Input and Output**

```
>D FILE^DID(999000,"","NAME;GLOBAL_NAME;REQUIRED IDENTIFIERS","TEST")

>ZW TEST
TEST("GLOBAL_NAME")=^DIZ(999000,
TEST("NAME")=ZZZDLTEST
TEST("REQUIRED IDENTIFIERS")=TEST("REQUIRED IDENTIFIERS")
TEST("REQUIRED IDENTIFIERS",1,"FIELD")=.01
TEST("REQUIRED IDENTIFIERS",2,"FIELD")=1
```

### 3.5.13.2 Error Codes Returned

[Table 51](#) lists the possible error codes returned with the FILE^DID API:

**Table 51: FILE^DID API—Error Codes Returned**

Code	Description
<a href="#">200</a>	There is an error in one of the variables passed.
<a href="#">202</a>	Missing or invalid input parameter.
<a href="#">301</a>	Flags passed are unknown or incorrect.
<a href="#">401</a>	The specified file or subfile does not exist.
<a href="#">403</a>	The file lacks a Header Node.
<a href="#">404</a>	The file Header Node lacks a file #.
<a href="#">501</a>	The field name or number does not exist.
<a href="#">505</a>	The field name passed is ambiguous.
<a href="#">510</a>	The data type for the specified field cannot be determined.
<a href="#">520</a>	An incorrect kind of field is being processed.
<a href="#">537</a>	Field has a corrupted pointer definition.

### 3.5.14 FILELST^DID(): DD File List Retriever

The FILELST^DID API returns a list of file-level attributes that are supported by VA FileMan. It shows specifically which attributes the data dictionary (DD) file list retriever calls can return.

#### Format

```
FILELST^DID(target_root)
```

#### Input Parameters

target\_root: (Required) The root of an output array.

#### Output Parameters

target\_root: The descendants of the array root are subscripted by the attribute names. “**WP**” nodes indicate that the attribute consists of a word-processing field. “**M**” nodes indicate that the attribute can consist of multiple sub-attributes.

#### 3.5.14.1 Example

Figure 164: FILELST^DID API—Example: Input and Output

```
>D FILELST^DID("TEST")

>ZW TEST
TEST("ARCHIVE FILE")=
TEST("AUDIT ACCESS")=
TEST("DATE")=
TEST("DD ACCESS")=
TEST("DEL ACCESS")=
TEST("DESCRIPTION")=
TEST("DESCRIPTION", "#(word-processing)")=
TEST("DEVELOPER")=
TEST("DISTRIBUTION PACKAGE")=
TEST("ENTRIES")=
TEST("GLOBAL NAME")=
TEST("LAYGO ACCESS")=
TEST("LOOKUP PROGRAM")=
TEST("NAME")=
TEST("PACKAGE REVISION DATA")=
TEST("REQUIRED IDENTIFIERS")=
TEST("REQUIRED IDENTIFIERS", "#", "FIELD")=
TEST("RD ACCESS")=
TEST("VERSION")=
TEST("WR ACCESS")=
```



**NOTE:** “RD ACCESS” in [Figure 164](#) is a new **attributes** input parameter.

### 3.5.15 \$\$GET1^DID(): Attribute Retriever

The \$\$GET1^DID extrinsic function retrieves a single attribute from a single file or field.

#### Format

```
$$GET1^DID(file[,field][,flags],attribute[,target-root][,msg-root])
```

#### Input Parameters

file: (Required) File number.

field: (Optional with exceptions) Field number or name.

Required only when field attributes are being requested; otherwise, this function assumes a file attribute is being requested.

flags: (Optional) Flag to control processing:

**Z**—Zero nodes on word-processing attributes are included in the array subscripts.

attribute: (Required) A list of data dictionary attribute names separated by semicolons. Full attribute names *must* be used.



**REF:** For a list of file attributes that you can use, see [FILE ATTRIBUTES](#).

For a list of the field attributes that you can use, see [FIELD ATTRIBUTES](#).

target-root: (Optional with exceptions) Closed array reference where multi-lined attributes are returned.

Required only when multi-line values are returned, such as word-processing attributes like “DESCRIPTION”.

msg-root: (Optional) The name of a closed root reference that is used to pass error messages. If *not* passed, ^TMP(“DIERR”,\$J) is used.

#### Output

A successful call returns the attribute requested. This can either be set into a variable or written to the output device.



### 3.5.15.1 Examples

#### 3.5.15.1.1 Example 1

Figure 165: \$\$GET1^DID API—Example 1: Input and Output

```
>S X=$$GET1^DID(999000,"","","DESCRIPTION","ARRAY","ERR") ZW @X
ARRAY("DESCRIPTION",1)= "This is the actual date and time of the encounter. This
date and time may"
ARRAY("DESCRIPTION",2)= "be different than the visit date and time specified in the
Visit file."
ARRAY("DESCRIPTION",3)= "However it must be within 30 days of the Visit date and
Not be a future"
ARRAY("DESCRIPTION",4)= "date. "
ARRAY("DESCRIPTION",5)= " "
ARRAY("DESCRIPTION",6)= "This field is useful for capturing the actual time
encounters take place,"
ARRAY("DESCRIPTION",7)= "or when, during the encounter, something happened."
```

#### 3.5.15.1.2 Example 2

Figure 166: \$\$GET1^DID API—Example 2: Input and Output

```
>W $$GET1^DID(999000,"","","GLOBAL NAME")
^DIZ(999000,
```

#### 3.5.15.1.3 Example 3

Figure 167: \$\$GET1^DID API—Example 3: Input and Output

```
>W $$GET1^DID(999000,.01,"","LABEL")
NAME
```

#### 3.5.15.1.4 Example 4

Figure 168: \$\$GET1^DID API—Example 4: Input and Output

```
>S X=$$GET1^DID(999000,.01,"Z","DESCRIPTION","ARRAY","ERR") ZW @X
ARRAY("DESCRIPTION",1,0)=This is the description of the .01 field
ARRAY("DESCRIPTION",2,0)=in file 999000.

>W X
ARRAY
```

### 3.5.15.2 Error Codes Returned

[Table 52](#) lists the possible error codes returned with the \$\$GET1^DID API:

Table 52: \$\$GET1^DID API—Error Codes Returned

Code	Description
<a href="#">200</a>	Parameter is invalid or missing.
<a href="#">202</a>	Specified parameter in missing or invalid.
<a href="#">505</a>	Ambiguous field.

### 3.5.15.3 Details and Features

#### 3.5.15.3.1 File/Field

This attribute retriever call differentiates whether the request is for a file or a field by the second parameter. If the second parameter is null, the retriever assumes (since no field is passed) that a file attribute is desired. If the second parameter is *not* null, the retriever assumes a field attribute is requested.

### 3.5.16 CHK^DIE(): Data Checker

The CHK^DIE API (aka Data Checker) checks user-supplied data against the data dictionary definition of a field. If the input data passes the validation, the internal and, optionally, the external forms of the data are returned. In this respect, CHK^DIE is the inverse of the [\\$EXTERNAL^DILFD](#) API.

While this API indicates that a user's response is valid according to a field's definition, it does *not* assure that a value can be filed in a particular record. In order to verify that a value can be filed, use the [VAL^DIE](#) or [FILE^DIE](#) calls (with the **E** flag). CHK^DIE does *not* have IENS as input; it is ignorant of the state of the data.

Do *not* pass a VALUE of null or @ to CHK^DIE. This API *cannot* verify that deletion of values from the database is appropriate. Again, use [VAL^DIE](#) or [FILE^DIE](#) (with **E** flag) for this purpose.

#### Format

```
CHK^DIE(file,field[,flags],value,.result,msg_root)
```

#### Input Parameters

- file: (Required) File or subfile number.
- field: (Required) Field number for which data is being validated.
- flags: (Optional) Flags to control processing. The possible values are:
- **H**—Help (single ?) is returned if **value** is *not* valid.
  - **E**—External value is returned in **RESULT(0)**.
- value: (Required) Value to be validated, as entered by a user. The **value** parameter can take several forms depending on the DATA TYPE field value involved, such as a partial, unambiguous match for a pointer or any of the supported ways to input dates (e.g., "**TODAY**" or "11/3/93").
- .result: (Required) Local variable that receives output from the call. If **value** is:
- **Valid**—The internal value is returned.
  - **Not Valid**—^ is returned.

If the **E** flag is passed, external value is returned in **RESULT(0)**.



**NOTE:** This array is KILLED at the beginning of each call.

- msg\_root: (Optional) Root into which error, help, and message arrays are put. If this parameter is *not* passed, these arrays are put into nodes descendent from ^TMP.

## Output

See input parameters `.result` and `msg_root`.

- **RESULT** = internal value or ^ if the passed **value** is *not* valid.
- **RESULT(0)** = external value if the passed **value** is valid and **E** flag is present.

### 3.5.16.1 Example

In [Figure 169](#), data for a DATA TYPE field value of DATE/TIME is being checked. Note that the external form of the user's input, which was "T-180", is passed. In this case, the value was acceptable, as shown in [Figure 169](#):

**Figure 169: CHK^DIE API—Example: Input and Output**

```
>S FILE=16200,FIELD=201,FLAG="E",VALUE="T-180"

>D CHK^DIE(FILE,FIELD,FLAG,VALUE,.RESULT)

>ZW RESULT
RESULT=2930625
RESULT(0)=JUN 25,1993
```

### 3.5.16.2 Error Codes Returned

In addition to errors that indicate that the input parameters are invalid, [Table 53](#) lists the possible error codes returned with the CHK^DIE API:

**Table 53: CHK^DIE API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">701</a>	Value is invalid.

### 3.5.16.3 Details and Features

#### 3.5.16.3.1 What is Checked

This call verifies that the **value** passed is valid by passing it through the field's INPUT transform. Also, if the field has any screens, those screens *must* be passed. If the field is a POINTER or VARIABLE POINTER, this call verifies that there is an unambiguous match (or partial match) for **value**.

#### 3.5.16.3.2 Entry Number Caution

No internal entry numbers are available when the INPUT transform or screens for the field are executed. Therefore, the INPUT transform and screens *cannot* reference any entry numbers using either the **DA()** array or the **D0, D1, D2**, etc., variables. Likewise, Executable Help *cannot* reference an entry number if the **H** flag is sent.

## 3.5.17 FILE^DIE(): Filer

The FILE^DIE API (aka Filer) does either of the following:

- Puts validated data that is in internal VA FileMan format into the database.
- Validates data that is in external (user-provided) format, converts it to internal VA FileMan format, and files valid data into the database.

If the data to be filed is in external format, you can specify that nothing is filed unless the values for every field being filed are valid. (Use the **T** and **E** flags.)

Uniqueness and completeness of keys are enforced (unless the **U** flag is used). This check is performed on values passed in both internal and external formats.

The associated functions of firing cross-references and of performing data audits are also performed.



**NOTE:** The Filer only files data into existing entries and subentries. To add new entries or subentries, use the [UPDATE^DIE\(\): Updater](#) API.

## Format

```
FILE^DIE([flags],fda_root[,msg_root])
```

## Input Parameters

flags:

(Optional) Flags to control processing. The possible values are:

- **E**—External values are processed. If this flag is set, the values in the **FDA** *must* be in the format input by the user. The value is validated and filed if it is valid.  
If the flag is *not* set, values *must* be in VA FileMan internal format and *must* be valid; no validation or transformation is done by the Filer, but key integrity is enforced.
- **K**—Locking is done by the Filer. (See discussion of [Locking](#).)
- **S**—Save **FDA**. If this flag is *not* set and there were no errors during the filing process, the **FDA** is deleted. If this flag is set, the array is never deleted.
- **T**—Transaction is either completely filed or nothing is filed. If you use the **T** flag, you *must* also pass the **E** flag, and pass values in external format. If any value is invalid, nothing is filed, and the error array specifies which fields were invalid.

Without this flag, valid values are filed and only the invalid ones are not. If neither the **T** nor the **U** flag is sent, simple keys are checked as they are encountered in the **FDA**. Compound keys are checked only after the entire record is filed. If the key is invalid, changes to fields making up that key are backed out.

**U**—Do *not* enforce key Uniqueness or completeness. Without the **U** flag, the values in the **FDA** are checked to ensure that the integrity of any key in which an included field participates is *not* violated.



**CAUTION:** If this flag is used, the FILE^DIE API call can result in records that contain null key fields or records with duplicate keys. It is the developer's responsibility to ensure that the database is *not* left in a state in which the integrity of keys is violated.

fda\_root:

(Required) The root of the **FDA** that contains the data to file. The array can be a local or global one. The root is the closed array reference to be used with subscript indirection not the traditional VA FileMan root.



**REF:** For details of the structure of the **FDA**, see the [“Introduction”](#) section in the [“Database Server \(DBS\) API”](#) section.

**msg\_root:** (Optional) The root of an array (local or global) into which error messages are returned. If this parameter is *not* included, error messages are returned in the default array-**^TMP(“DIERR”,\$J)**.

## Output

Ordinarily the “output” of this call is the updating of the database. Error messages and information supplied via the [EN^DDIOL](#) API are returned in the standard array in **^TMP** or in the array specified by **msg\_root**.

### 3.5.17.1 Error Codes Returned

This call returns error messages in many circumstances. Most of the messages report bad input parameters or input to a file, field, or record that does *not* exist. [Table 54](#) list the primary user-oriented codes returned with the **FILE^DIE** API:

**Table 54: FILE^DIE: Filer—Error Codes Returned**

Code	Description
<a href="#">110</a>	Record is locked.
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">701</a>	Input data was invalid.
<a href="#">712</a>	Deletion was attempted but not allowed.
<a href="#">740</a>	New values are invalid because they would create a duplicate key.
<a href="#">742</a>	Deletion was attempted on a key field.
<a href="#">744</a>	A key field was not assigned a value.

### 3.5.17.2 Details and Features

#### 3.5.17.2.1 +Security

The Filer does *not* check user access when filing. This check *must* be done by the client application.

#### 3.5.17.2.2 Deleting Data

You can delete the value in a field by setting the value for the field equal to null or @.

This works for **WORD-PROCESSING** fields, too. Instead of setting the value for the field equal to the root of the array where the new word-processing text is to be found, set it equal to null or @.



**NOTE:** When the **E** (external) flag is used, you *cannot* delete the field value if the field is either Required or Uneditable. Without the **E** flag, deletion occurs in both cases. When key integrity is checked (the **U** flag is *not* used), you *cannot* delete the value of a key field whether the **E** flag is used or not.

You can delete an entire entry or subentry by setting the value of the **.01** field to @ or null. In this case, it does *not* matter whether the **.01** field is Required, Uneditable, or a key field.

The Filer *never* asks for confirmation of the deletion.

### 3.5.17.2.3 Scope of a Single Filer Call

Data passed to the Filer should comprise one logical record. Thus, the data can consist of values for fields in the primary file and its Multiples and in related files. (“Navigation” to other files is handled by the calling application, *not* by the Filer.)

### 3.5.17.2.4 Cross-References

New-Style indexes that have an execution value of **RECORD** are fired once after all the data for a single record or subrecord is filed.

All other cross-references (and data audits) are fired as the data is filed (i.e., on a field-by-field basis).

Any possible conflict between the cross-reference and updated data *must* be noted by the client application and resolved by modifying the cross-reference. The most common situation in which conflicts can arise is when a cross-reference (most frequently a trigger or MUMPS cross-reference) has been used to provide information to the user while data is being edited. Default values that are dependent on the values of other fields being edited can be provided in this way. These “user interface” cross-references are fired by the Filer with the rest of the cross-references after the data editing is complete. Thus, they *cannot* have their desired effect of providing the user with information during the editing session. However, they can have the undesired effect of overwriting user-entered values. This type of cross-reference *must* be removed from the DD as part of the preparation for using the DBS. Also, if the functionality provided by these cross-references is still desirable during the editing session, the client application needs to provide it.

### 3.5.17.2.5 Locking

If requested, the Filer incrementally locks records and subrecords before beginning to file any data. If a lock on any record fails, no filing is done and an error message is returned to the calling program.

It is *recommended* that locking be done outside of the Filer by the client application. There are several reasons for this:

- It can be frustrating to the user to edit a screen’s worth of data and then to have the **SAVE** fail, because the necessary lock could *not* be obtained.
- Data successfully validated can become invalid before it is filed.
- The client application can more selectively determine which records to lock. Of necessity, the Filer locks *all* entries and subentries referenced in the **FDA** passed to it. In many instances, this is more than is actually required.
- Locking inside the Filer requires additional processing that slows the filing action down.

However, there are situations in which it is appropriate for the Filer to do the locking. For example, if only a single file is involved and the source of the data is *not* an interactive editing session.

### 3.5.18 HELP^DIE(): Helper

The HELP^DIE API (aka Helper) retrieves user-oriented help for a field from the data dictionary (DD) and other sources. The help is returned in arrays. Use the [MSG^DIALOG](#) API to display the help.


You control the kind of help obtained by using the **flags** input parameter:

- Specific kind of help.
- Help normally returned with one or two question marks.
- All available help for a field.

#### Format

```
HELP^DIE(file[,iens],field,flags[,msg_root])
```

#### Input Parameters

- file: (Required) File or subfile number.
- iens: (Optional) Standard IENS indicating internal entry numbers. This parameter is only needed if code in the Data Dictionary for Executable Help or Screen on a SET OF CODES references the entry number using **DA()** array or **D0, D1**, etc., and if that kind of help is being requested.
- field: (Required) Field number for which help is requested.
- flags: (Required) Flags used to determine what kind of help is returned by the call. If a lowercase letter is shown, use it to suppress that kind of help; useful in conjunction with **?** or **??**. The possible values are:
- **?**—Help equivalent to user entering one **?** at an edit prompt. Also, help returned for an invalid response.
  - **??**—Help equivalent to user entering **??** at an edit prompt.
  - **A**—All available help for the field.
  - **B (b)**—Brief variable pointer help. A single line beginning with “To see the entries ...”.
-  **REF:** See also “[Limitations](#)” under the “[Details and Features](#)” section.
- **C**—Set of Codes screen description.
  - **D**—Description text for the field; this can be multiple lines.
  - **F**—Fields that can be used for lookups. Returned for top-level **.01** fields and for pointed-to files for a DATA TYPE field value of POINTER data. For pointed-to files, the **F** flag is effective only if the **G** flag is also sent.
  - **G (g)**—Getting help from pointed-to file. Help for the **.01** field of pointed-to file is returned.
  - **H**—Help prompt text.
  - **M**—More variable pointer help. Detailed description of how to enter VARIABLE POINTER data.

- **P**—Pointer screen description.
- **S**—Set of codes possible choices. Any screen that exists on the SET OF CODES field is applied so that only actually selectable choices are presented.
- **T**—Date/Time generic help. This help text is customized based on the allowable and required elements of the particular DATE/TIME field.
- **U**—Unscreened SET OF CODES choices.
- **V**—Variable pointer help that lists the prefixes and messages associated with a particular VARIABLE POINTER field.
- **X**—EXecutable help-the M code contained in executable help is executed. In order to have the help returned in an array, the executed code *must* use [EN^DDIOL](#) to load the help message.

msg\_root: (Optional) Closed root into which the output from the call is put. If *not* supplied, output is returned in ^TMP (see [Output](#)).

## Output

The default output from this call is:

DIHELP: Number of lines of help text returned.

^TMP("DIHELP",\$J,n): Array containing the lines of help text. The text is found in integer subscripted nodes (*n*), beginning with 1. A blank node is inserted between each different type of help returned.

If error messages are necessary, they are returned in the standard manner.

If the **msg\_root** is included in the input parameters, output is returned there instead of ^TMP. The help text is returned in nodes descendent from **MSG\_ROOT("DIHELP")**.

### 3.5.18.1 Example

[Figure 170](#) illustrates the use of this call to return help text from a field that has a DATA TYPE field value of SET OF CODES. This is the same help that can be obtained with a ? in a traditional VA FileMan call.



**NOTE:** The help is returned in the specified array descendent from **MYHELP(1)**.

**Figure 170: HELP^DIE API—Example: Input and Output**

```
>D HELP^DIE(16200,"",5,"?", "MYHELP(1)")
>ZW MYHELP
MYHELP(1,"DIHELP")=5
MYHELP(1,"DIHELP",1)=Only YES and MAYBE are acceptable.
MYHELP(1,"DIHELP",2)=
MYHELP(1,"DIHELP",3)=Choose from:
MYHELP(1,"DIHELP",4)=Y          YES
MYHELP(1,"DIHELP",5)=M          MAYBE
```



### 3.5.18.2 Error Codes Returned

[Table 55](#) lists the possible error codes returned with the HELP^DIE API:

**Table 55: HELP^DIE API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">301</a>	An invalid flag was passed.
<a href="#">501</a>	Field does not exist.

### 3.5.18.3 Details and Features

#### 3.5.18.3.1 Helper and Validator

Based on a flag passed to the Validator call, single question mark help is returned by the Validator if the value being checked is invalid.

#### 3.5.18.3.2 Pointed-to Files

By default you receive help for the .01 field of pointed-to files with ? or ?? when the field on which you are requesting help is a POINTER. If you do *not* want this extended help returned, use the (lowercase) **g** flag.

#### 3.5.18.3.3 Limitations

This call does *not* return lists of entries for .01, POINTER, or VARIABLE POINTER fields. Use the Lister utility to obtain these lists.

The (lowercase) **b** flag suppresses the line of Variable Pointer help that indicates a user can get a list of entries if they type <Prefix.?.>. Use this flag with ? if you are *not* supporting this capability.

## 3.5.19 \$\$KEYVAL^DIE(): Key Validator

The \$\$KEYVAL^DIE extrinsic function (aka Key Validator) verifies that new values contained in the **FDA** do *not* produce an invalid key. All keys in which any field in the **FDA** participates are checked. If the value for a field in a key being checked is *not* present in the **FDA**, the value used to verify the key is obtained from the previously filed data.

### Format

```
$$KEYVAL^DIE([flags,]fda_root[,msg_root])
```

### Input Parameters

flags: (Optional) Flags to control processing. The possible value is:

**Q**—Quit when the first problem in the **FDA** is encountered.

fda\_root: (Required) The root of the **FDA** that contains the data to be checked. The array can be a local or global one.



**REF:** For details of the structure of the **FDA**, see the Database Server [Introduction](#).

The value of fields in the **FDA** *must* be the internal value. Do *not* pass external (e.g., unresolved pointer values, *non-* VA FileMan dates) in the **FDA**.

No action is taken on fields in the referenced **FDA** if those fields do *not* participate in a key defined in the KEY (#.31) file.

msg\_root: (Optional) The root of an array into which error messages are returned. If this parameter is *not* included, errors are returned in the default array:  
^TMP("DIERR", \$J).

## Output

This Boolean function returns the following:

- **1**—If key integrity is *not* violated by any value in the **FDA**.
- **0**—If an invalid key was produced by any of the values.

Error messages and **DIERR** are also returned when necessary.

### 3.5.19.1 Example

In [Figure 171](#), two fields from (fictitious) File #99999 are set into an **FDA**. These are values for a new record; therefore, the IENS is **+1**. The values (".111" and "One Fmuser") are valid internal values for fields **.01** and **.02**. **\$\$KEYVAL^DIE** returns **0** indicating that key integrity is violated by these values. The returned error message states the values create a duplicate key. The key that is duplicated is the **A** key.

Figure 171: **\$\$KEYVAL^DIE** API—Example: Input and Output

```
>K MYERRORS,MYFDA
>S MYFDA(99999,"+1,",.01)=.111
>S MYFDA(99999,"+1,",.02)="One Fmuser"
>W $$KEYVAL^DIE("", "MYFDA", "MYERRORS")
0
>W DIERR
1^1
>ZW MYERRORS
MYERRORS("DIERR")=1^1
MYERRORS("DIERR",1)=740
MYERRORS("DIERR",1,"PARAM",0)=3
MYERRORS("DIERR",1,"PARAM","FILE")=99999
MYERRORS("DIERR",1,"PARAM","IENS")=+1,
MYERRORS("DIERR",1,"PARAM","KEY")=11
MYERRORS("DIERR",1,"TEXT",1)=New values are invalid because they create a duplicate
Key 'A' for the SAMPLE file.
MYERRORS("DIERR","E",740,1)=
```

### 3.5.19.2 Error Codes Returned

[Table 56](#) lists the possible error codes returned with the \$\$KEYVAL^DIE API:

**Table 56: \$\$KEYVAL^DIE API—Error Codes Returned**

Code	Description
<a href="#">740</a>	A duplicate key is produced by a field's new value.
<a href="#">742</a>	A value for a field in a key is being deleted.
<a href="#">744</a>	Not all fields in a key have a value.

### 3.5.19.3 Details and Features

#### 3.5.19.3.1 Possible IENS

The only placeholder the IENS in the **FDA** can contain is the + for records *not* yet added to the database. You *cannot* use the ? or ?+ placeholders, since the Key Validator does *not* attempt to look up an entry to obtain existing values for a key.



**REF:** For details of the IENS, see the Database Server [Introduction](#).

For description of placeholders, see the [UPDATE^DIE](#) API.

### 3.5.20 UPDATE^DIE(): Updater

The UPDATE^DIE API (aka Updater) adds new entries in files or subfiles. The caller uses a standard **FDA** structure to specify the field values of the new entries. The caller should restrict each Updater call to one logical entry, possibly made up of multiple physical entries. The record numbers for the new entries are returned in an array; the caller can assign their own record numbers to new entries by presetting the array. Any appropriate indexing and auditing automatically occurs for the new record.



**CAUTION:** Although the Updater can safely add entries to top-level files and to subfiles within those same new entries, there is one caution. If the subfile contains an **INPUT** transform that assumes the existence of the parent record, the developer should make two separate Updater calls:

- 1) Add the parents.
- 2) Add the children.

This API includes some elementary filing capabilities to permit the adding of required identifiers and key values at the time new records are created. It also includes elementary finding capabilities to facilitate the identification of top-level entries to which subentries are being added. For full filing and finding capabilities beyond the scope of adding new records, developers should use the Filer ([FILE^DIE](#)) or Finder ([FIND^DIC](#)). If you are filing data in existing records and you know the record numbers, use the Filer instead of the Updater.

#### Format

```
UPDATE^DIE([flags,]fda_root[,ien_root][,msg_root])
```

#### Input Parameters

flags:

(Optional) Flags to control processing. The possible values are:

- **E**—External values are processed. If this flag is set, the values in the **FDA** *must* be in the format input by the user. The Updater validates all values and converts them to VA FileMan internal format. Invalid values cancel the entire transaction.  
If the flag is *not* set, values *must* be in VA FileMan internal format and *must* be valid.
- **K**—If a file has a primary key, the primary **Key** fields, *not* the **.01** field, are used for lookup for **Finding** and **LAYGO Finding** nodes.
- **S**—The Updater **Saves** the **FDA** instead of **KILLing** it at the end.
- **U**—Do *not* check key integrity.



**CAUTION:** If this flag is used, the UPDATE^DIE call can result in records that contain null key fields or records with duplicate keys. It is the developer's responsibility to ensure that the database is *not* left in a state in which the integrity of keys is violated.

`fda_root`: (Required) The name of the root of a VA FileMan data array, which describes the entries to add to the database. The Updater accepts the following in its **FDA**s:

- **Adding** nodes
- **Filing** nodes
- **Finding** nodes
- **LAYGO Finding** nodes



**REF:** For a description of the format of the array named by the **FDA** parameter, see the “[Details and Features](#)” section.

`ien_root`” (Optional) The name of the Internal Entry Number Array (or **IEN Array**). This should be a closed root. This array has two functions:

- [Requesting Record Numbers for New Entries](#)
- [Locating Feedback on What the Updater Did](#)

### **Requesting Record Numbers for New Entries**

The application can set nodes in the **IEN Array** to direct the Updater to use specific record numbers for specific new records. These nodes should have a single subscript equal to the sequence number in the **IENS** subscript of the **FDA** entry and a value equal to the desired record number.

For example, if the application sets the **ien\_root** parameter to **ORIEN**, and sets **ORIEN(1)=1701**, the Updater tries to assign record number 1701 to the new record denoted by the **+1** value in the **FDA** subscripts.

This feature also affects **LAYGO Finding** nodes. When these nodes result in adding a new record, the Updater checks the **IEN Array** to see if the application wants to place the new record at a specific record number. When **LAYGO Finding** nodes result in a successful lookup, the **IEN Array** node passed in by the application is changed to the record number of the record found.

If the application sets an entry in the **IEN Array** for a **Finding** node, the Updater ignores it (actually, it overwrites it when it finds the record number for that node).

This feature is meaningless for **Filing** nodes, since they have no sequence numbers.

Unlike the **fda\_root** parameter, the **ien\_root** parameter is optional, both partially and as a whole. The Updater picks the next available record numbers for any new records *not* listed by sequence number in the **IEN Array**. If the **IEN Array** is empty or if the **ien\_root** is *not* passed, the Updater picks all the new record numbers.

## Locating Feedback on What the Updater Did

As the Updater decodes and processes the sequence numbers, it gradually converts them into genuine record numbers (see [Output](#)). The **IEN Array** named by the **ien\_root** parameter is where this feedback is given. Those sequence numbers *not* already assigned by the application are filled in by the Updater (or sometimes replaced, in the case of **LAYGO Finding** nodes).

**msg\_root:** (Optional) The array that should receive any error messages. This *must* be a closed array reference and can be either local or global. For example, if **msg\_root** equals "OROUT(42)", any errors generated appear in OROUT(42,"DIERR").

If the **msg\_root** T is *not* passed, errors are returned descendent from ^TMP("DIERR",\$J).

## Output

**IEN Array:** As the Updater assigns record numbers to the records described in the **FDA**, it sets up nodes in the **IEN Array** to indicate how it decoded the sequence numbers.



**REF:** For more information on sequence numbers, see "[Details and Features.](#)"

This lets the application find out what was done with the various nodes in the **FDA**.

The meaning of **IEN Array** entries varies depending on the type of node the sequence number came from. For example, the significance of an **IEN Array** entry of ORIEN(3) = 1701 depends on which type of node in the **FDA** the sequence number 3 came from.

For **Adding** node sequence numbers, the value in the **IEN Array** indicates the record number of the new record. If the example came from an **Adding** node, such as **FDA**(19,"+3",.01) = "ZTMDQ", it means the new record was assigned the record number 1701.

For **Finding** node sequence numbers, the value indicates at which record number the value was found. If the example came from a **Finding** node, such as **FDA**(19,"?3",.01) = "ZTMDQ", it means a call to [\\$\\$FIND1^DIC](#) found record number 1701 based on a lookup value of "ZTMDQ".

For **LAYGO Finding** sequence numbers, an extra zero-node equal to ? or + identifies whether the entry was found (?) or added (+). If the example came from a **LAYGO Finding** node, such as **FDA**(19,"?+3",.01) = "ZTMDQ", an extra node of ORIEN(3,0) = "?" means ZTMDQ was found, whereas ORIEN(3,0) = "+" means it was added.

By the time the Updater finishes processing an **FDA**, every sequence number is listed with a value in the **IEN Array** (some set by the application as input for new record numbers and the rest set by the Updater).

If the **ien\_root** parameter was *not* passed, the **IEN Array** is *not* returned.

### 3.5.20.1 Examples

#### 3.5.20.1.1 Example 1

[Figure 172](#) illustrates the use of this call to create a new record in a top-level file. In this case, a new option is being added at a specified record number. Notice the triggered 9 on the 0-node and the triggered “U” node:

**Figure 172: UPDATE^DIE API—Example 1: Input and Output**

```
>S FDA(42,19,"+1,",.01)="ZZ FDA TEST NAME"  
>S FDA(42,19,"+1,",1)="ZZ Toad Test Menu Text"  
>S FDAIEN(1)=2067642283  
>D UPDATE^DIE("","FDA(42)","FDAIEN")  
>D ^%G  
Global ^DIC(19,2067642283  
      DIC(19,2067642283  
^DIC(19,2067642283,0) = ZZ FDA TEST NAME^ZZ Toad Test Menu Text^^^9  
^DIC(19,2067642283,"U") = ZZ FDA TEST MENU TEXT
```

#### 3.5.20.1.2 Example 2

[Figure 173](#) illustrates the use of UPDATE^DIE to create a new record in a Multiple field. A new subentry Person Class is created for a user, in this example IEN #82, in the NEW PERSON (#200) file:

**Figure 173: UPDATE^DIE API—Example 2: Input and Output**

```
>S USERIEN=82  
>S ZZ(1,200.05,"+2,"_USERIEN_",",.01)=144  
>S ZZ(1,200.05,"+2,"_USERIEN_",",2)=3070605  
>S ZZ(1,200.05,"+2,"_USERIEN_",",3)=3070615  
>D UPDATE^DIE("","ZZ(1)")  
>D ^%G  
Global ^VA(200,82,"USC1"  
^VA(200,82,"USC1",0)=^200.05P^1^1  
^VA(200,82,"USC1",1,0)=144^3070605^3070615  
^VA(200,82,"USC1","AD",3070605,1)=  
^VA(200,82,"USC1","B",144,1)=
```

### 3.5.20.1.3 Example 3

[Figure 174](#) is another example of adding a new subentry to a menu option. In this case, the menu is EVE and the new option that is to be added is “ZZSO SECURITY DEMO:”

**Figure 174: UPDATE^DIE API—Example 3: Input and Output**

```

; Demo Adding Sub-file Entry N DIERR,IEN,IENS,FDA,NOPT
; Get "EVE" menu IEN
;;;
S IEN=$$FIND1^DIC(19,"","X","EVE","B")
I $G(DIERR)'="" D Q
. W !,"LOOKUP FOR 'EVE' FAILED"
. D CLEAN^DILF
. Q
;
; Get the option to be added to EVE IEN
S NOPT=$$FIND1^DIC(19,"","X","ZZSO SECURITY DEMO","B")
I $G(DIERR)'="" D Q
. W !,"LOOKUP FOR 'ZZSO SECURITY DEMO' FAILED"
. D CLEAN^DILF
. Q
;
; Now add the option to EVE using UPDATE^DIE
; The '?' says to see if the .01 value already exists,if it does
; then just edit the existing entry.
; The '+' says if the .01 value doesn't already exists, then add it.
; The '1' is just a place holder number.
; The value for IEN is equal to DA(1).
; The value '?+1' is a place holder for DA.
S IENS="?+1"
S FDA(19.01,IENS_"","_IEN_"",",.01)=NOPT
S FDA(19.01,IENS_"","_IEN_"",",2)="ZZ"
D UPDATE^DIE("","FDA")
W:$G(DIERR)'="" !,"THE MENU ADDITION FAILED."
D CLEAN^DILF
Q

```

### 3.5.20.2 Error Codes Returned

[Table 57](#) lists the possible error codes returned with the UPDATE^DIE API:

**Table 57: UPDATE^DIE API—Error Codes Returned**

Error	Description
<a href="#">110</a>	The record is currently locked.
<a href="#">111</a>	The File Header Node is currently locked.
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">202</a>	An input parameter is missing or not valid.
<a href="#">205</a>	The File and IENS represent different subfile levels.
<a href="#">301</a>	The passed flags are unknown or inconsistent.
<a href="#">302</a>	Entry already exists.
<a href="#">304</a>	The IENS lacks a final comma.



<b>Error</b>	<b>Description</b>
<a href="#">307</a>	The IENS has an empty comma-piece.
<a href="#">308</a>	The IENS is syntactically incorrect.
<a href="#">310</a>	The IENS conflicts with the rest of the FDA.
<a href="#">311</a>	The new record lacks some required identifiers.
<a href="#">330</a>	The value is not valid.
<a href="#">351</a>	FDA Node has a bad IENS.
<a href="#">352</a>	The new record lacks a .01 field.
<a href="#">401</a>	The file does not exist.
<a href="#">402</a>	The global root is missing or not valid.
<a href="#">403</a>	The file lacks a header node.
<a href="#">405</a>	Entries in file cannot be edited.
<a href="#">406</a>	The file has no .01 field definition.
<a href="#">407</a>	A word-processing field is not a file.
<a href="#">408</a>	The file lacks a name.
<a href="#">501</a>	The file does not contain that field.
<a href="#">502</a>	The field has a corrupted definition.
<a href="#">510</a>	The data type cannot be determined.
<a href="#">520</a>	That kind of field cannot be processed by this utility.
<a href="#">601</a>	The entry does not exist.
<a href="#">602</a>	The entry is not available for editing.
<a href="#">603</a>	The entry lacks a required field.
<a href="#">630</a>	The field value is not valid.
<a href="#">701</a>	The value is not valid for that field.
<a href="#">703</a>	The value cannot be found in the file.
<a href="#">712</a>	The value in that field cannot be deleted.
<a href="#">730</a>	The value is not valid according to the DD definition.
<a href="#">740</a>	New values are invalid because they would create a duplicate key.
<a href="#">742</a>	Deletion was attempted on a key field.
<a href="#">744</a>	A key field was not assigned a value.
<a href="#">746</a>	The K flag was used, but no primary key fields were provided in the FDA for Finding and LAYGO Finding nodes.

The Updater can also return any error returned by:

- [\\$\\$FIND1^DIC](#)
- [FILE^DIE](#)

### 3.5.20.3 Details and Features

#### 3.5.20.3.1 Adding

**Adding** nodes let applications create new entries in a file. In the place of the actual **IENS** subscript for the new record in the **FDA** array, the application instead uses a unique value consisting of a + followed by a positive number.

The **+#** *Always* adds *without* regard to duplication.

Thus, for example, an **FDA** of “**FDA(42)**” might be accompanied by the following array:

```
FDA(42,19,"+1","",.01)="NAME OF OPTION"  
FDA(42,19,"+1","",1)="MENU TEXT OF NEW OPTION"  
FDA(42,19.01,"+2,+1","",.01)=45  
FDA(42,19.01,"+2,+1","",2)="TM"  
FDA(42,19.01,"+3,+1","",.01)=408
```

The **fd\_a\_root** value directs the Updater to the **FDA(42)** array, whose format instructs the Updater to add one new entry to the **OPTION** (#19) file and two new entries to the **MENU Multiple** of that entry.



**NOTE:** The sequence number for each new entry to be added to a file or subfile *must* be unique throughout the **FDA**.

#### 3.5.20.3.2 Adding—Identifiers and Keys

The **FDA** for a new record *must* include the **.01** field, all of the *required* identifiers, and all key fields. If any of these needed fields is missing, the entire **FDA** transaction fails; none of the entries is added if any one lacks required data.

#### 3.5.20.3.3 Filing

**Filing** nodes let the application file new data under existing entries. This may be necessary to complete a logical record addition. Any **FDA** node whose **IENS** subscript consists solely of record numbers and commas is considered a **Filing** node. If you know all of the record numbers (i.e., if all of the nodes in your **FDA** are **Filing** nodes), you should use the Filer ([FIND^DIC](#)) instead of the Updater to file the data.

For example, **FDA(42,19,"408,"",1)="NEW MENU TEXT"** instructs the Updater to update Field #1 of record 408, so no actual record creation takes place as a result of this node.

#### 3.5.20.3.4 Finding

**Finding** nodes let applications work with existing entries for which the application does *not* yet have a record number. Instead of **+#**, the application uses the notation **?#** to stand in for an unknown record number. The sequence number that follows the **?** *must* be unique throughout the **FDA**.

Every **FDA** of this type *must* include an **FDA** node for the **.01** field, or, if the **K** flag is passed, nodes for at least one field in the primary key. The value of this **FDA** node is used to perform a lookup on the file. It *must* match only one entry in that file; ambiguity or failure to find a match is an error condition. The record number found is then used for this **FDA** entry.

For example, the following **FDA** adds a new menu item to the ZTMMGR menu and changes the menu's text:

```
FDA(42,19,"?1",".01)="ZTMMGR"  
FDA(42,19,"?1","1)="New Menu Text"  
FDA(42,19.01,"+2,?1",".01)=45  
FDA(42,19.01,"+2,?1","2)="TM"
```

In this example, the Updater first uses the value ZTMMGR in a lookup to find the record number that replaces ?1. It then adds a new entry to Subfile #19.01 under that entry, and changes the menu text of the option to "New Menu Text". The first node shown is a **Finding** node that specifies the value of the .01 field to be used for lookup. The next node specifies a new value for Field #1, the menu's text. The last two nodes are **Adding** nodes that specify the values for Fields #01 and #2 of the new menu item.

When the **E** flag is used, the .01 **Finding** node can equal any valid input value for the Lookup. For example, to pick based on a set of codes where **WA** stands for WASHINGTON, when using the **E** flag, you can enter **WASH**.

However, when the **E** flag is *not* used, the .01 **Finding** node *must* equal an internal value, though the special lookup values—<Spacebar> and grave accent (`) concatenated with the IEN—still work. For example, a .01 **Finding** node equal to **WASH** would return an error in the above scenario if the **E** flag were *not* passed. To succeed, the .01 **Finding** node would need to equal **WA**, the internal value.

### 3.5.20.3.5 LAYGO Finding

**LAYGO Finding** nodes let the application refer to entries that may or may *not* already exist. If they do exist, the Updater finds and uses their record numbers. If *not*, the Updater adds the entries. The **IENS** notation used to stand in for these entries is ?+#. The # is a unique positive number that acts as a placeholder until an actual internal entry number can be produced by the Updater.

For example, this call expects to find the ZTMMGR option, but adds it if it is missing:

```
FDA(42,19,"?+1",".01)="ZTMMGR"  
FDA(42,19.01,"+2,?+1",".01)=45  
FDA(42,19.01,"+2,?+1","2)="TM"
```

The **IEN Array** node for this entry includes an extra zero node equal to ? or + to identify if the entry was found or added. For example, if the entry for the previous example was found, the **IEN Array** node for this **FDA** might look like this:

```
IEN(1)=388  
IEN(1,0)="?"  
IEN(2)=9
```

All **LAYGO Finding** nodes are processed in order after **Finding** nodes and before other kinds of nodes.

Like **Finding** nodes, .01 **LAYGO Finding** nodes *must* match the format of the overall call: external if the **E** flag has been passed, internal if *not*.



**REF:** For details, see the "[Finding](#)" section.

### 3.5.20.3.6 Sequence Numbers

A positive number that acts as a placeholder to identify a record until an actual internal entry number can be created or found by the Updater. This positive number *must* be unique throughout the **FDA** array. For example, if +1, is used in an **FDA**, you *cannot* also use ?1, or ?+1.

## 3.5.21 VAL^DIE(): Validator

The VAL^DIE API (aka Validator) takes the external form of user input and determines if that value is valid (i.e., if that value can be put into the VA FileMan database). In addition, the Validator converts the user-supplied value into the VA FileMan internal value when necessary. It is this internal value that is stored. If the Validator determines that the value passed is invalid, a caret (^) is returned.

WORD-PROCESSING and COMPUTED fields *cannot* be validated. The **.01** field of a Multiple *must* be input using:

FILE = subfile number and FIELD = **.01**.

Optionally, the Validator does the following:


- Returns the resolved external value of the data.
- Returns help text for invalid values.
- Loads the internal value into the VA FileMan Data Array (**FDA**) to prepare for a later Filer call ([FILE^DIE](#)).

### Format

```
VAL^DIE(file,iens,field[,flags],value,.result[,fda_root][,msg_root])
```

### Input Parameters

file:	(Required) File or subfile number.
iens:	(Required) Standard IENS indicating internal entry numbers.
field:	(Required) Field number for which data is being validated.
flags:	(Optional) Flags to control processing. The possible values are: <ul style="list-style-type: none"><li>• <b>E</b>—External value is returned in <b>RESULT(0)</b>.</li><li>• <b>F</b>—FDA node is set for valid data in array identified by <b>fda_root</b>.</li><li>• <b>H</b>—Help (single ?) is returned if <b>value</b> is <i>not</i> valid.</li><li>• <b>R</b>—Record identified by IENS is verified to exist and to be editable. Do <i>not</i> include <b>R</b> if there are placeholders in the IENS.</li><li>• <b>U</b>—Do <i>not</i> perform key validation. Without this flag, the data in <b>value</b> is checked to ensure that no duplicate keys are created and that key field values are <i>not</i> deleted.</li></ul>
value:	(Required) Value to be validated as input by a user. The <b>value</b> parameter can take several forms depending on the data type involved, such as a partial, unambiguous match for a pointer) and any of the supported ways to input dates (e.g., “ <b>TODAY</b> ” or “11/3/93”).

- .result:** (Required) Local variable that receives output from call:
- If the **value** input parameter is valid, the internal value is returned.
  - If the **value** input parameter is *not* valid, ^ is returned.
  - If **E** flag is present, external value is returned in **RESULT(0)**.
-  **NOTE:** This array is KILLED at the beginning of each Validator call.
- fda\_root:** (Optional; required if **F** flag present) Root of **FDA** into which internal value is loaded if **F** flag is present.
- msg\_root:** (Optional) Root into which the following arrays are put:
- Error
  - Help
  - Message
- If this parameter is *not* passed, these arrays are put into nodes descendent from ^TMP.

## Output

See Input Parameters **.result**, **fda\_root**, and **msg\_root**.

- **RESULT** = internal value or ^ if the passed VALUE is *not* valid.
- **RESULT(0)** = external value if the passed VALUE is valid and **E** flag is present.

### 3.5.21.1 Example

This example checks the validity of a value for a set of codes field. Note that the flags indicate that the external value should be returned and that a node in the **FDA** should be built. In this situation a **value** input parameter of **YES** would also have been acceptable and would have resulted in exactly the same output as shown in [Figure 175](#):

**Figure 175: VAL^DIE API—Example: Input and Output**

```
>S FILE=16200,FIELD=5,IENS="3,",FLAG="EHFR",VALUE="Y"
>D VAL^DIE(FILE,IENS,FIELD,FLAG,VALUE,.ANSWER,"MYFDA(1)")
>ZW ANSWER
ANSWER=Y
ANSWER(0)=YES
>ZW MYFDA(1)
MYFDA(1,16200,"3,",5)=Y
```

### 3.5.21.2 Error Codes Returned

In addition to codes indicating that the input parameters are incorrect and that the file, field, or entry does *not* exist, [Table 58](#) lists the possible primary error messages returned with the VAL^DIE API:

**Table 58: VAL^DIE API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">299</a>	Ambiguous value. (Variable Pointer data type only.)
<a href="#">405</a>	The file is uneditable.
<a href="#">520</a>	The field's data type or INPUT transform is inappropriate.
<a href="#">602</a>	The entry cannot be edited.
<a href="#">701</a>	Value is invalid.
<a href="#">710</a>	The field is uneditable.
<a href="#">712</a>	An inappropriate deletion of a field's value is being attempted.
<a href="#">740</a>	A duplicate key is produced by a field's new value.
<a href="#">742</a>	A value for a field in a key is being deleted.
<a href="#">1610</a>	Help was improperly requested.

### 3.5.21.3 Details and Features

#### 3.5.21.3.1 What is Validated

The Validator takes the following steps in validating the input data:

- Rejects a **value** input parameter starting with a question mark (?). Help should be requested using the [HELP^DIE](#) API.
- If the **R** flag is sent, it verifies that the entry is present and that editing is *not* blocked because the entry is being archived.
- If the field is uneditable, it rejects the input if there is already data in the field.
- If the passed value is null or @, signifying data deletion, it rejects the input if the:
  - Field is required.
  - Field is a key field.
  - Tests present in any “**DEL**” nodes for the field are *not* passed.

For Multiples, the deletion of the last subentry in the Multiple is rejected if the Multiple is required.

- Verifies that the value of the field is *not* DINUMed.
- Checks all keys in which the field participates to ensure the new value does *not* create any duplicate keys.

- Passes the value through the field's INPUT transform and executes any screens on POINTER, VARIABLE POINTER, or SET OF CODES fields. For POINTER and VARIABLE POINTER, values that do *not* yield at least a partial match are rejected (no LAYGO); ambiguous values are rejected (see "[Note for VARIABLE POINTERS](#)"). If these tests are passed, the input value is accepted and the internal value becomes the value resulting in the execution of the INPUT transform or the POINTER value resulting from the lookup.



**NOTE:** No file or field access security checks on either the file or field level are done.

### 3.5.21.3.2 Note for POINTERS

The internal entry number of the entry in the pointed-to file that corresponds to the input is returned. If the lookup value partially matches more than one entry in the pointed-to file, the call fails.

### 3.5.21.3.3 Note for VARIABLE POINTERS

For a DATA TYPE field value of VARIABLE POINTER, the **value** input parameter can include the VARIABLE POINTER's PREFIX, MESSAGE, or FILENAME followed by a period (.) before the lookup value. If no particular file is specified in this way, all of the pointed-to files are searched. If the lookup value is *not* found in any file searched or if more than one match is found in any files, the call fails (i.e., the **value** input parameter is *not* valid).

### 3.5.21.3.4 Note for SET OF CODES

For a DATA TYPE field value of SET OF CODES, the **value** input parameter is treated as case insensitive. If the **value** is ambiguous, the validation fails.

### 3.5.21.3.5 Returning External Values

If the **E** flag is sent, the Validator returns the external value of **value** in addition to its internal value. This is returned in **RESULT(0)**.

For DATA TYPE field values of

- FREE TEXT, NUMBER, and MUMPS—The external value is created by passing **value** through the INPUT transform (if any) and then the OUTPUT transform (if any).
- DATE/TIME—The external value is the standard VA FileMan external DATE/TIME format.
- POINTERS and VARIABLE POINTERS—The external value is the **.01** of the entry in the pointed-to file.
- SET OF CODES—The external value is the "translation" of the code.

### 3.5.21.3.6 Validate and File

If you want to validate a set of data and then file the valid data, make a call to the [FILE^DIE](#) (the Filer) API with an **E** flag passed in the first parameter. The nodes in the **FDA** identified by the second parameter should be set to the external, unvalidated value used as input to the Validator. Based on this flag, the Filer calls the Validator for each field and only files the valid, internal values. Error messages are returned for the fields that could *not* be filed.



**NOTE:** You *cannot* mix internal and external values in the **FDA** when calling the Filer.

### 3.5.22 VALS^DIE(): Fields Validator




The VALS^DIE API (aka Fields Validator) validates data for a group of fields and converts valid data to VA FileMan internal format. It is intended for use with a set of fields that comprise a logical record; fields from more than one file can be validated by a single call. By default, the integrity of any keys affected by the new values is checked.

The Fields Validator performs the same checks performed by the [VAL^DIE](#) API (see for details).

#### Format

```
VALS^DIE([flags], fda_ext_root, fda_int_root[, msg_root])
```

#### Input Parameters

- flags: (Optional) Flags to control processing. The possible values are:
- **K**—If the file has a Primary Key, this flag indicates that the Primary Key fields, *not* the **.01** field, are to be used for lookup in the **Finding** and **LAYGO/Finding** nodes of the **FDA**. Without this flag, VALS^DIE assumes that you want to file the fields in the Primary Key, rather than use them for lookup, and performs the uniqueness check. This flag is equivalent to the **K** flag in the Updater ([UPDATE^DIE](#)).
  - **R**—Records identified by IENSs in the **FDA\_EXT** are verified to exist and to be editable. (Same as **R** flag for [VAL^DIE](#).)
  - **U**—Do *not* perform key validation. Without this flag, the data in the **FDA** is checked to ensure that no duplicate keys are created and that key field values are *not* deleted.
- fda\_ext\_root: (Required) The root of a standard **FDA**. This array should contain the external values that you want to validate. This is the input array.
-  **REF:** For details of the structure of the **FDA**, see the “[Introduction](#)” section in the “[Database Server \(DBS\) API](#)” section.
- fda\_int\_root: (Required) The root of a standard **FDA**. This **FDA** is the output array, and upon return is set equal to the internal values of each validated field. If a field fails validation, its value is set to a caret (^).
-  **NOTE:** If a field is valid, the corresponding node in the output array is set to the internal value, *not* a caret (^), even if that field violates key integrity.
-  **REF:** For details of the structure of the **FDA**, see the “[Introduction](#)” section in the “[Database Server \(DBS\) API](#)” section.
- msg\_root: (Optional) The root of an array (local or global) into which error messages are returned. If this parameter is not included, error messages are returned in the default array: ^TMP(“DIERR”, \$J).



## Output



**REF:** For an explanation of how internal values are returned to the client application, see the description of the **fdi\_int\_root**.

If an error occurs in any of the validations, the **DIERR** variable is set and appropriate error messages are returned.

### 3.5.22.1 Examples

#### 3.5.22.1.1 Example 1

This simple example ([Figure 176](#)) validates and converts the values for two fields:

**Figure 176: VALS^DIE API—Example 1: Input and Output**

```
>S MYFDA("EXT",16997,"1",1)="SOME TEXT"
>S MYFDA("EXT",16997,"1",2)="JAN 1, 1996"
>D VALS^DIE("","MYFDA("EXT")","MYFDA("INT")")
>W $G(DIERR)
>ZW MYFDA("INT")
MYFDA("INT",16997,"1",1)=SOME TEXT
MYFDA("INT",16997,"1",2)=2960101
```

### 3.5.22.1.2 Example 2

This example ([Figure 177](#)) reports that one of the values does *not* pass validation. Note that the value for the invalid field equals ^ in MYFDAINT.

**Figure 177: VALS^DIE API—Example 2: Input and Output**

```
>S MYFDA("EXT",16997,"1","",1)="SOME TEXT"

>S MYFDA("EXT",16997,"1","",2)="JAN 1, 6"

>D VALS^DIE("", "MYFDA(""EXT"")", "MYFDA(""INT"")")

>W DIERR
1^1
>D ^%G

Global ^TMP("DIERR", $J
      TMP("DIERR", $J
^TMP("DIERR", 610279233, 1) = 701
^TMP("DIERR", 610279233, 1, "PARAM", 0) = 4
^TMP("DIERR", 610279233, 1, "PARAM", 3) = JAN 1, 6
^TMP("DIERR", 610279233, 1, "PARAM", "FIELD") = 2
^TMP("DIERR", 610279233, 1, "PARAM", "FILE") = 16997
^TMP("DIERR", 610279233, 1, "PARAM", "IENS") = 1,
^TMP("DIERR", 610279233, 1, "TEXT", 1) = The value `JAN 1,
6' for field REVERSE DATE FIELD IN KEY in file ZZD
KEYTEST is not valid.
^TMP("DIERR", 610279233, "E", 701, 1) =
Global ^

>ZW MYFDA("INT")
MYFDA("INT", 16997, "1", "", 1)=SOME TEXT
MYFDA("INT", 16997, "1", "", 2)=^
```

### 3.5.22.1.3 Example 3

In this example ([Figure 178](#)), the values pass field validation, but an error is returned because they fail the requested key integrity check.

**Figure 178: VALS^DIE API—Example 3: Input and Output**

```
>K MYFDA
>S MYFDA("EXT",16997,"1",1)="TEXT INTO SECOND"
>S MYFDA("EXT",16997,"1",2)="MAR 4, 1996"
>D VALS^DIE("U","MYFDA(""EXT"")","MYFDA(""INT"")")
>W %G(DIERR)
1^1
>D ^%G

Global ^TMP("DIERR", $J
      TMP("DIERR", $J
^TMP("DIERR", 610279233, 1) = 740
^TMP("DIERR", 610279233, 1, "PARAM", 0) = 3
^TMP("DIERR", 610279233, 1, "PARAM", "FILE") = 16997
^TMP("DIERR", 610279233, 1, "PARAM", "IENS") = 13,
^TMP("DIERR", 610279233, 1, "PARAM", "KEY") = 34
^TMP("DIERR", 610279233, 1, "TEXT", 1) = New values are invalid
because they create a duplicate Key 'C' for the ZSD KEYTEST file.
^TMP("DIERR", 610279233, "E", 740, 1) =
Global ^

>ZW MYFDA("INT")
MYFDA("INT", 16997, "1", 1) = TEXT INTO SECOND
MYFDA("INT", 16997, "1", 2) = 2960304
```

### 3.5.22.2 Error Codes Returned

In addition to codes indicating that the input parameters are incorrect and that the file, field, or entry does not exist, [Table 59](#) lists the possible primary error messages returned with the VALS^DIE API:

**Table 59: VALS^DIE API—Error Codes Returned**

Code	Description
<a href="#">120</a>	Error occurred during execution of a FileMan hook.
<a href="#">299</a>	Ambiguous value. (Variable Pointer data type only.)
<a href="#">405</a>	The file is uneditable.
<a href="#">520</a>	The field's data type or INPUT transform is inappropriate.
<a href="#">602</a>	The entry cannot be edited.
<a href="#">701</a>	Value is invalid.
<a href="#">710</a>	The field is uneditable.
<a href="#">712</a>	An inappropriate deletion of a field's value is being attempted.
<a href="#">740</a>	A duplicate key is produced by a field's new value.

Code	Description
<a href="#">742</a>	A value for a field in a key is being deleted.
<a href="#">744</a>	Not all fields in a key have a value.
<a href="#">1610</a>	Help was improperly requested.

### 3.5.22.3 Details and Features

#### 3.5.22.3.1 Key Integrity Validation

Unless the **U** flag is passed, the internal values produced by the validation of the values passed in the **FDA\_EXT** are checked to make sure that no key's integrity is violated.

## 3.5.23 WP^DIE(): Word-Processing Filer

The WP^DIE API files a single WORD-PROCESSING field.

### Format

```
WP^DIE(file,iens,field[,flags],wp_root[,msg_root])
```

### Input Parameters

- file: (Required) File or subfile number.
- iens: (Required) Standard IENS indicating internal entry numbers.
- field: (Required) Field number of the WORD-PROCESSING field into which data is being filed.
- flags: (Optional) Flags to control processing. The possible values are:
- **A**—Append new word-processing text to the current word-processing data. If this flag is *not* sent, the current contents of the WORD-PROCESSING field are completely erased before the new word-processing data is filed.
  - **K**—Lock the entry or subentry before changing the word-processing data.
- wp\_root: (Required) The root of the array that contains the word-processing data to be filed. The data *must* be in nodes descendent from this root. The subscripts of the nodes below the **wp\_root** *must* be positive numbers. The subscripts do *not* have to be integers, and there can be gaps in the sequence. The word-processing text *must* be in these nodes or in the **0**-node descendent from these nodes. To delete the WORD-PROCESSING field, set **wp\_root** equal to **@**.
- msg\_root: (Optional) Root into which errors are put. If this parameter is *not* passed, these arrays are put into nodes descendent from **^TMP**.

### Output

The typical result of this call is the updating of the database with new word-processing data. If the call fails, an error message is returned either in **^TMP** or, if it is passed, descendent from **msg\_root**.

### 3.5.23.1 Example

The following call files the data into Field #4 of (fictitious) File #16200 for record number 606. The entry is locked before filing and the new data is added to any word-processing data that is already there.

**Figure 179: WP^DIE API—Example: Input**

```
>D WP^DIE(16200,"606","",4,"KA","^TMP($J,""WP"")")
```

In this example, the word-processing text *must* be located at:

**Figure 180: WP^DIE API—Example: Word-Processing Text Location 1**

```
^TMP($J,"WP",1,0) =Line 1  
^TMP($J,"WP",2,0) =Line 2  
...etc.
```

Or:

**Figure 181: WP^DIE API—Example: Word-Processing Text Location 2**

```
^TMP($J,"WP",1) =Line 1  
^TMP($J,"WP",2) =Line 2  
...etc.
```

### 3.5.23.2 Error Codes Returned

In addition to errors indicating that input parameters are missing or incorrect and that the file, field, or entry does *not* exist, [Table 60](#) lists the possible error codes returned with the WP^DIE API:

**Table 60: WP^DIE API—Error Codes Returned**

Code	Description
<a href="#">110</a>	Lock could not be obtained because the entry was locked.
<a href="#">305</a>	There is no data in the array identified by WP_ROOT.
<a href="#">726</a>	The specified field is not a word-processing field.

### 3.5.24 CLEAN^DILF: Array and Variable Cleanup

The CLEAN^DILF API KILLS the standard message arrays and variables that are produced by VA FileMan.

#### Format

```
CLEAN^DILF
```

#### Input Parameters

None.

#### Output

The CLEAN^DILF AP KILLS the following arrays:

- ^TMP(“DIERR”, \$J)
- ^TMP(“DIHELP”, \$J)
- ^TMP(“DIMSG”, \$J)

The CLEAN^DILF AP KILLS the following variables:

- DIERR
- DIHELP
- DIMSG
- DUOUT
- DIRUT
- DIROUT
- DTOUT

#### 3.5.24.1 Error Codes Returned

None.

### 3.5.25 \$\$CREF^DILF(): Root Converter (Open to Closed Format)

The \$\$CREF^DILF extrinsic function converts the traditional open-root format to the closed-root format used by subscript indirection. It converts an ending comma to a close parenthesis. If the last character is an open parenthesis, the last character is dropped.

#### Format

```
$$CREF^DILF(open_root)
```

#### Input Parameters

open\_root: (Required) An open root that is a global root ending in either an open parenthesis or a comma.

### 3.5.25.1 Example

Figure 182: \$\$CREF^DILF API—Example: Input and Output

```
>W $$CREF^DILF(“^DIZ(999000,”)
^DIZ(999000)
```

### 3.5.26 DA^DILF(): Convert IENS to DA() Array Structure

The DA^DILF API converts an IENS into an array with the structure of a DA() array.

#### Format

```
DA^DILF(iens, .da)
```

#### Input Parameters

- iens: (Required) A string with record and subrecord numbers in IENS format.
- .da: (Required) The name of the array that receives the record numbers.



**NOTE:** This array is cleaned out (KILLeD) before the record numbers are loaded.

#### Output

An array with the record numbers from the IENS; the array is structured like the traditional VA FileMan DA() array.

### 3.5.26.1 Example

Figure 183: DA^DILF API—Example: Input and Output

```
>S IENS="4,1,2,532,"
>D DA^DILF(IENS, .MYDA)
>ZW MYDA
MYDA=4
MYDA(1)=1
MYDA(2)=2
MYDA(3)=532
```

### 3.5.26.2 Error Codes Returned

None.

### 3.5.27 DT^DILF(): Date Converter

The DT^DILF API converts a user-supplied value into VA FileMan's internal date format and (optionally) into the standard VA FileMan external, readable date format.

#### Format

```
DT^DILF([flags,]in_date, .result[,limit][,msg_root])
```

#### Input Parameters

- flags: (Optional) Flags to control processing of user input and the type of output returned. Generally, **flags** is the same as **%DT** input variable to [^%DT](#) entry point, with the following exceptions:
- **A** is *not* allowed.
  - The meaning of **E** is different (see below).
- The possible values are:
- **E**—External, readable date returned in zero-node of **result**.
  - **F**—Future dates are assumed.
  - **N**—Numeric-only input is *not* allowed.
  - **P**—Past dates are assumed.
  - **R**—Required time input.
  - **S**—Seconds are returned.
  - **T**—Time input is allowed but *not* required.
  - **X**—EXact date (with month and day) is required.
- in\_date: (Required) Date input as entered by the user in any of the formats known to VA FileMan. Also, help based on the **flags** passed can be requested with a question mark (?).
- .result: (Required) Local array that receives the internal value of the DATE/TIME and, if the **E** flag is sent, the readable value of the date. If input is *not* a valid date, **-1** is returned.
- limit: (Optional) A value equal to a DATE/TIME in VA FileMan internal format or **NOW**. The **in\_date** parameter is accepted only if it is:
- Greater than or equal to **limit** if it is positive.
  - Less than or equal to **limit** if it is negative.
- This is equivalent to the **%DT(0)** variable in the [^%DT](#) call.
- msg\_root: (Optional) Root into which the following arrays are put:
- Error
  - Help
  - Message



## Output

Output is returned in the local array passed by reference in the RESULT parameter, shown below:

**RESULT:** Date in internal VA FileMan format. If input is invalid or if help is requested with a question mark (?), -1 is returned.

**RESULT(0):** If requested, date in external, readable format. When appropriate, error messages and help text are returned in the standard manner in ^TMP or in msg\_root (if it is specified).

### 3.5.27.1 Examples

#### 3.5.27.1.1 Example 1

[Figure 184](#) is an example of one of the many kinds of user inputs that can be processed by this call. Use of the E flag ensures that the readable form of the data is returned in the 0-node as follows:

**Figure 184: DT^DILF API—Example 1: Input and Output**

```
>D DT^DILF("E","T+10",.ANSWER)

>ZW ANSWER
ANSWER=2931219
ANSWER(0)=DEC 19, 1993
```

#### 3.5.27.1.2 Example 2

[Figure 185](#) is an example of a request for help when time is allowed as input:

**Figure 185: DT^DILF API—Example 2: Input and Output**

```
>D DT^DILF("T","?",.ANSWER,"","MYHELP")

>ZW ANSWER
ANSWER=-1

>ZW MYHELP
MYHELP("DIHELP")=10
MYHELP("DIHELP",1)=Examples of Valid Dates:
MYHELP("DIHELP",2)= JAN 20 1957 or JAN 57 or 1/20/57 or 012057
MYHELP("DIHELP",3)= T (for TODAY), T+1 (for TOMORROW), T+2, T+7, etc.
MYHELP("DIHELP",4)=T-1 (for YESTERDAY), T-3W (for 3 WEEKS AGO), etc.
MYHELP("DIHELP",5)=If the year is omitted, the computer uses the CURRENT YEAR.
MYHELP("DIHELP",6)=You may omit the precise day, as: JAN, 1957.
MYHELP("DIHELP",7)=
MYHELP("DIHELP",8)=If the date is omitted, the current date is assumed.
MYHELP("DIHELP",9)=Follow the date with a time, such as JAN 20@10, T@10AM, 10:30,
etc.
MYHELP("DIHELP",10)=You may enter NOON, MIDNIGHT, or NOW to indicate the time.
```

### 3.5.27.2 Error Codes Returned

In addition to errors indicating that the input parameters are incorrect or missing, [Table 61](#) lists the possible error codes returned with the DT^DILF API:

Table 61: DT^DILF API—Error Codes Returned

Code	Description
<a href="#">330</a>	Date/time is not acceptable.

### 3.5.27.3 Details and Features

#### 3.5.27.3.1 Acceptable User Input

The DT^DILF API processes a wide range of formats for dates and times. [Example 2](#) shows the response to an **in\_date** of ? summarizes the acceptable formats. Remember that the allowable values are controlled by the **flags** sent and by the **limit** parameter.

#### 3.5.27.3.2 Internal Format

The primary use of the DT^DILF API is to transform the DATE/TIME passed in the **in\_date** parameter into the format used by VA FileMan to store values in DATA TYPE fields with a value of DATE/TIME. That format is:

*YYYDDMM.HHMMSS*

Where *YYY* is the number of years since **1700**.

When the **E** flag is sent to request that the readable form of the data be returned, the format is always:

*MON dd,yyyy@ hh:mm:ss*

## 3.5.28 FDA^DILF(): FDA Loader

The FDA^DILF API can be used to load data into the **FDA**. It accepts either the traditional **DA()** array or the **iens** input parameter for specifying the entry. No validation of the **value** input parameter is done.

### Format

1. FDA^DILF(file,iens,field[,flags],value,fda\_root[,msg\_root])
2. FDA^DILF(file,.da,field[,flags],value,fda\_root[,msg\_root])

### Input Parameters

- file: (Required) File or subfile number.
- .da: (Required for format 2) **DA()** array containing entry and subentry numbers.
- iens: (Required for format 1) Standard **IENS** indicating internal entry numbers.
- field: (Required) Field number for which data is being loaded into the **FDA**.
- flags: (Optional) Flag to control processing:

**R**—Record identified by **iens** or **.da** is verified to exist. Do *not* use the **R flag** if the **IENS** or **DA()** array contain placeholder codes instead of actual record numbers.

value: (Required, can be null) Value to which the **FDA** node is set. Depending on how the **FDA** is used, this could be the internal or external value. For word-processing fields, this is the root of the array that contains the word-processing data. Internal and external values *cannot* be mixed in a single **FDA**.

fda\_root: (Required) The root of the **FDA** in which the new node is loaded.

msg\_root: (Optional) Root into which the following arrays are put:

- Error
- Help
- Message

If this parameter is *not* passed, these arrays are put into nodes descendent from **^TMP**.

## Output

Successful completion of this call results in the creation of a node descendent from the root passed in **fda\_root**. The format of the node is:

**Figure 186: FDA^DILF API—Node Format**

```
FDA_ROOT(FILE,"IENS",FIELD)=VALUE
```



**REF:** For more information on the format of the **FDA**, see the [“Introduction”](#) in the [“Database Server \(DBS\) API”](#) section.

By default, error messages are returned in **^TMP**. If **msg\_root** is passed, messages are returned there.

### 3.5.28.1 Example

The example in [Figure 187](#) loads the **FDA** for the first sub-subentry in the second subentry of entry number 4 for Field #4 in (fictitious) subfile #16200.32 with a value of “NEW DATA” [the **FDA** is descendent from **^TMP(“MYDATA”, \$J)**]:

**Figure 187: FDA^DILF API—Example: Input and Output**

```
>S FILE=16200.32,IENS="1,2,4,",FIELD=4,VALUE="NEW DATA",ROOT="^TMP("MYDATA", $J)"
>D FDA^DILF(FILE,IENS,FIELD,"",VALUE,ROOT)
>D ^%G
Global ^TMP("MYDATA", $J
      TMP("MYDATA", $J
^TMP("MYDATA",000101456,16200.32,"1,2,4,",4) = NEW DATA
```

### 3.5.28.2 Error Codes Returned

[Table 62](#) lists the possible error codes returned with the FDA^DILF API:

**Table 62: FDA^DILF API—Error Codes Returned**

Code	Description
<a href="#">202</a>	One of the input parameters is not properly specified.
<a href="#">401</a>	The file does not exist.
<a href="#">501</a>	The field does not exist.
<a href="#">601</a>	The entry does not exist.

### 3.5.29 \$\$HTML^DILF(): HTML Encoder/Decoder

The \$\$HTML^DILF extrinsic function has two capabilities:

- Encodes a string that can contain embedded caret (^) characters according to the rules of HTML so that the ^ characters are replaced with the following string:

**&#94;**

As a side effect, & characters are encoded as the following string:

**&amp;**

Other encodings typical of HTML are *not* performed by this function, since its focus is on encoding the ^ character used as the delimiter in VA FileMan databases.

- Decodes an encoded string, restoring its ^ and & characters.

#### Format

```
$$HTML^DILF(string[,action])
```

#### Input Parameters

**string:** (Required) The string to be either encoded or decoded. Encoding a string that contains no ^ or & characters has no effect on the string. Nor does decoding one that lacks ^ and & substrings.

**action:** (Optional) Set this parameter to the following:

- **1**—Encode the input string.
- **-1**—Decode the input string.

Defaults to **1**.

#### Output

The function evaluates to the encoded or decoded string. If encoding the string makes it overflow the string length limit, it returns error [207](#). Decoding never makes it overflow.

### 3.5.29.1 Error Codes Returned

[Table 63](#) lists the possible error codes returned with the \$\$HTML^DILF API:

Table 63: \$\$HTML^DILF—Error Codes Returned

Code	Description
<a href="#">207</a>	The value is too long to encode into HTML.

### 3.5.30 \$\$IENS^DILF(): Return IENS from a DA() Array Structure

The \$\$IENS^DILF extrinsic function returns the IENS when passed an array in the traditional DA() structure.

#### Format

```
$$IENS^DILF( .da )
```

#### Input Parameters

.da: (Required) An array with the structure of the traditional VA FileMan DA() array [i.e., DA=lowest subfile record number, DA(1)=next highest subfile record number, etc.].

#### Output

A string of record numbers in the IENS format [i.e., “DA,DA(1),...DA(n),”].



**NOTE:** The string always ends with a comma (.). If the array passed by reference is empty, a 0 is returned.

#### 3.5.30.1 Example

Figure 188: \$\$IENS^DILF API—Example: Input and Output

```
>S NMSPDA=4,NMSPDA(1)=1,NMSPDA(2)=2,NMSPDA(3)=532
>W $$IENS^DILF(.NMSPDA)
4,1,2,532,
```

### 3.5.30.2 Error Codes Returned

None.

### 3.5.31 LOCK^DILF(): Lock Global Reference

The LOCK^DILF API locks a global reference using VA FileMan’s Lock time out value (DILOCKTM).

#### Format

```
LOCK^DILF(closed_root)
```

#### Input Parameter

closed\_root: (Required) A closed root, which is a global root ending in a close parenthesis.

## Output

**\$Truth** value:

- **1**—Lock obtained.
- **0**—Lock failed.

### 3.5.31.1 Example

Figure 189: LOCK^DILF API—Example: Input and Output

```
>D LOCK^DILF("^MYFILE(123,1,0)")
>W $T
1
>W DILOCKTM
3
```

## 3.5.32 \$\$OREF^DILF(): Root Converter (Closed to Open Format)

The \$\$OREF^DILF extrinsic function converts a closed root to an open root. It converts an ending close parenthesis to a comma.

### Format

```
$$OREF^DILF(closed_root)
```

### Input Parameter

closed\_root: (Required) A closed root, which is a global root ending in a close parenthesis.

### 3.5.32.1 Example

Figure 190: \$\$OREF^DILF API—Example: Input and Output

```
>W $$OREF^DILF("^DIZ(999000)")
^DIZ(999000,
```

## 3.5.33 \$\$VALUE1^DILF(): FDA Value Retriever (Single)

The \$\$VALUE1^DILF extrinsic function returns the value associated with a particular file and field in a standard **FDA**. Only a single value is returned. If there is more than one node in the **FDA** array for the same field, the first value encountered by this function is returned. Use the [VALUES^DILF\(\): FDA Values Retriever](#) API if you want more than one value returned.

### Format

```
$$VALUE1^DILF(file,field,fda_root)
```

### Input Parameters

file: (Required) File or subfile number.

field: (Required) Field number for which data is being requested.

fda\_root: (Required) The root of the **FDA** from which data is being requested.

## Output

This function returns the value for the specified file and field that is stored in the **FDA** identified by **fda\_root**:

- If the field is a WORD-PROCESSING field, only the root at which word-processing data is stored is returned. No IENS information is returned.
- If more than one value is associated with a particular field (e.g., in a subfile), only a single value is returned.
- If there is no node in the **FDA** for a particular field, a caret (^) is returned.
- If the node has a null value, null is returned.

### 3.5.33.1 Example

Figure 191: \$\$VALUE1^DILF API—Example: Input and Output

```
>ZW MYFDA
MYFDA("DATA",16200,"33","",4)=FREE TEXT DATA
MYFDA("DATA",16200.04,"1,33","",1)=16
MYFDA("DATA",16200.04,"2,33","",1)=45

>W $$VALUE1^DILF(16200,4,"MYFDA("DATA")")
FREE TEXT DATA
```

### 3.5.33.2 Error Codes Returned

None.

## 3.5.34 VALUES^DILF(): FDA Values Retriever

The VALUES^DILF API returns values from an **FDA** for a specified field. The IENS associated with a particular value is also returned. Use the [\\$\\$VALUE1^DILF\(\): FDA Value Retriever \(Single\)](#) API if you want the single value associated with a particular file and field in a standard **FDA**.

### Format

```
VALUES^DILF(file,field,fda_root,.result)
```

### Input Parameters

- file: (Required) File or subfile number.
- field: (Required) Field number for which data is being requested.
- fda\_root: (Required) The root of the **FDA** from which data is being requested.
- .result: (Required) Local array that receives output from the call. The array is **KILLED** at the beginning of each call.



**REF:** For the structure of the array, see the “[Output](#)” section.

## Output



**REF:** See the [.result](#) input parameter.

The output from the call is returned in the array identified by **result**. Its structure is:

**RESULT:** Number of values found for the specified field. If no node exists in the **FDA** for the field, **RESULT=0**.

**RESULT(seq#):** Value for a particular instance of the field. **Seq#** is an integer starting with **1** that identifies the particular value.

**RESULT(seq#,"IENS"):** The **IENS** of the entry or subentry with the value in **RESULT(seq#)**.

### 3.5.34.1 Example

Figure 192: VALUES^DILF API—Example: Input and Output

```
>ZW MYFDA
MYFDA("DATA",16200,"33","",4)=FREE TEXT DATA
MYFDA("DATA",16200.04,"1,33","",1)=16
MYFDA("DATA",16200.04,"2,33","",1)=45

>D VALUES^DILF(16200.04,1,"MYFDA("DATA")",.MYVALUES)

>ZW MYVALUES
MYVALUES=2
MYVALUES(1)=16
MYVALUES(1,"IENS")=1,33,
MYVALUES(2)=45
MYVALUES(2,"IENS")=2,33,
```

### 3.5.34.2 Error Codes Returned

None.

## 3.5.35 \$\$EXTERNAL^DILFD(): Converts Internal Value to External Format

The \$\$EXTERNAL^DILFD extrinsic function converts any internal value to its external format. It does the following:

- Decodes codes.
- Makes VA FileMan dates readable.
- Follows pointer or variable pointer chains to resolve their values.

OUTPUT transforms are applied to their fields.



**REF:** For more information about how VA FileMan handles OUTPUT transforms and pointers, see the “[Details and Features](#)” section.

### Format

```
$$EXTERNAL^DILFD(file,field[,flags],internal[,msg_root])
```



## Input Parameters

- file: (Required) The number of the file or subfile that contains the field that describes the internal value passed.
- field: (Required) The number of the field that describes the internal value passed.
- flags: (Optional) To control processing.

A single-character code that explains how to handle OUTPUT transforms found along pointer chains. The default describes how fields *not* found along a pointer chain are always handled, regardless of whether a flag is passed.



**REF:** For definition and explanation of pointer chains, see the “[Details and Features](#)” section.

The default, if no flag is passed, is the way this function generally handles OUTPUT transforms. If a field has an OUTPUT transform, the transform is applied to the internal value of the field and VA FileMan does *not* process the value further. This means it is the responsibility of the OUTPUT transform to:

- Resolve codes.
- Transform dates.
- Follow POINTER or VARIABLE POINTER chains to their destination.

The default handling of POINTER chains, therefore, is to follow the chain either until:

- The last field is found, at which point the field is transformed according to its data type.

Or:

- A field with an OUTPUT transform is found, at which point VA FileMan applies the OUTPUT transform to the field where it is found and quits.

The possible values are:

- **F**—If the **F**irst field in a POINTER chain has an OUTPUT transform, apply the transform to that first field and quit. Ignore any other OUTPUT transforms found along the POINTER chain. With the exception of this function, VA FileMan regularly handles OUTPUT transforms this way.
- **L**—If the **L**ast field in a POINTER chain has an OUTPUT transform, apply the transform to that last field and quit. Ignore any other OUTPUT transforms found along the POINTER chain.
- **U**—Use the first OUTPUT transform found on the last field in the POINTER chain. Following the POINTER chain, watch for OUTPUT transforms. When one is found, remember it, but keep following the POINTER chain. When the last field in the chain is reached, apply the remembered transform to that last field.

internal: (Required) The internal value that is to be converted to its external format.

msg\_root: (Optional) The array that should receive any error messages. This *must* be a closed array reference and can be either local or global. For example, if

**msg\_root** equals "OROUT(42)", any errors generated appear in OROUT(42,"DIERR").

If the **msg\_root** is *not* passed, errors are returned descendent from ^TMP("DIERR",\$J).

## Output

This function evaluates to an external format value, as defined by a field in a file in the database. In the event of an error, this function outputs the empty string instead.

### 3.5.35.1 Examples

#### 3.5.35.1.1 Example 1

Figure 193: \$\$EXTERNAL^DILFD API—Example 1: Input and Output

```
>W $$EXTERNAL^DILFD(19,4,"","A")
action
```

#### 3.5.35.1.2 Example 2

Figure 194: \$\$EXTERNAL^DILFD API—Example 2: Input and Output

```
>W $$EXTERNAL^DILFD(4.302,.01,"",2940209.0918)
FEB 09, 1994@09:18
```

#### 3.5.35.1.3 Example 3

Figure 195: \$\$EXTERNAL^DILFD API—Example 3: Input and Output

```
>W $$EXTERNAL^DILFD(3.7,.01,"",DUZ)
FMPATIENT,27
```

#### 3.5.35.1.4 Example 4

Figure 196: \$\$EXTERNAL^DILFD API—Example 4: Input and Output

```
>W $$EXTERNAL^DILFD(3298428.1,.01,"",1)
11111 1 11111
```

#### 3.5.35.1.5 Example 5

Figure 197: \$\$EXTERNAL^DILFD API—Example 5: Input and Output

```
>W $$EXTERNAL^DILFD(3298428.1,.01,"F",1)
11111 1 11111
```

#### 3.5.35.1.6 Example 6

Figure 198: \$\$EXTERNAL^DILFD API—Example 6: Input and Output

```
>W $$EXTERNAL^DILFD(3298428.1,.01,"L",1)
22222 TOAD 22222
```

### 3.5.35.1.7 Example 7

Figure 199: \$\$EXTERNAL^DILFD API—Example 7: Input and Output

```
>W $$EXTERNAL^DILFD(3298428.1,.01,"U",1)
11111 TOAD 11111
```

### 3.5.35.1.8 Example 8

Figure 200: \$\$EXTERNAL^DILFD API—Example 8: Input and Output

```
>W $$EXTERNAL^DILFD(3298428.1,.01,"GGG",1) W DIERR D ^%G
1^1
Global ^TMP("DIERR"
      TMP("DIERR"
^TMP("DIERR",731987397,1) = 301
^TMP("DIERR",731987397,1,"PARAM",0) = 1
^TMP("DIERR",731987397,1,"PARAM",1) = GGG
^TMP("DIERR",731987397,1,"TEXT",1) = The passed flag(s) 'GGG' are unknown or
inconsistent.
^TMP("DIERR",731987397,"E",301,1) =
```

## 3.5.35.2 Error Codes Returned

[Table 64](#) lists the possible error codes returned with the \$\$EXTERNAL^DILFD API

Table 64: \$\$EXTERNAL^DILFD API—Error Codes Returned

Code	Description
<a href="#">202</a>	The input parameter is missing or invalid.
<a href="#">301</a>	The passed flag(s) are unknown or inconsistent.
<a href="#">348</a>	The passed value points to a file that does not exist or lacks a Header Node.
<a href="#">401</a>	File # does not exist.
<a href="#">403</a>	File # lacks a Header Node.
<a href="#">404</a>	The Header node of the file lacks a file number.
<a href="#">501</a>	File # does not contain a field.
<a href="#">510</a>	The data type cannot be determined.
<a href="#">537</a>	Corrupted pointer definition.
<a href="#">603</a>	Entry lacks the required Field #.
<a href="#">648</a>	The value points to a file that does not exist or lacks a Header Node.

### 3.5.35.3 Details and Features

#### 3.5.35.3.1 Data Types

The internal value of a field is the way it is stored in the database. The external value is the way a user expects the field to look. (See also “[OUTPUT Transforms](#).”) VA FileMan *must* perform the transformation whenever such a value is displayed. The data types that undergo this process are listed in [Table 65](#):

**Table 65: \$\$EXTERNAL^DILFD API—VA FileMan Data Types**

Data Type	Description
DATE/TIME	The internal value is a numeric code, while the external is readable text. For example, the internal value of: 2940214.085938 has an external value of: FEB 14,1994@ 08:59:57
NUMERIC	The internal and external values are identical.
SET OF CODES	The full external value is decoded from abbreviated internal value. Each SET OF CODES field defines which codes are allowed and what they mean. For example, the internal value of <b>F</b> can have the external value of <b>FEMALE</b> for a certain field.
FREE TEXT	The internal and external values are identical.
WORD-PROCESSING	\$\$EXTERNAL^DILFD does <i>not</i> handle this data type.
COMPUTED	This data type does <i>not</i> have an internal value, so \$\$EXTERNAL^DILFD does <i>not</i> handle this data type.
POINTER TO A FILE	The internal value of this field is the internal entry number of one record in the pointed-to file. The external format of a pointer value is the external format of the <b>.01</b> field of the record identified by the pointer's internal value. The definition of a pointer <i>must</i> always identify the pointed-to file. For example, if <b>1</b> is the internal value of a pointer to the STATE (#5) file, then the external value is ALABAMA, because the <b>.01</b> of the STATE (#5) file is defined as FREE TEXT (needing no transform) and the <b>.01</b> field of record #1 in the STATE (#5) file is ALABAMA.
VARIABLE POINTER	Unlike the DATA TYPE field with a value of POINTER, the internal value of a VARIABLE POINTER identifies the pointed-to file. Like the POINTER, the VARIABLE POINTER's external format is the external value of the <b>.01</b> field of the pointed-to record. The <b>Prefix.Value</b> notation many users are familiar with is <i>not</i> the external format of a VARIABLE POINTER; that is merely a user interface convention. For example, the internal value: 1;DIC(5, has the external format of: ALABAMA (It is the VARIABLE POINTER equivalent of the previous example.)
MUMPS	The internal and external values are identical.

### 3.5.35.3.2 OUTPUT Transforms

OUTPUT transforms assume full responsibility for transforming the internal value to its external format. So, transforms on sets of codes work with values like **F**, *not* FEMALE; those on pointers deal with 1, *not* ALABAMA; etc. This includes following [POINTER Chains](#) to their conclusions.

### 3.5.35.3.3 POINTER Chains

A POINTER chain is a list of one or more POINTER fields that point to one another in sequence, the final POINTER of which points to a file with a non- POINTER **.01** field. Thus, for example, if the **.01** field of File A points to the STATE (#5) file, that is a POINTER chain with one link. If File B points to File A, that makes a POINTER chain with two links. Chains can be made up of any mix of POINTERS and VARIABLE POINTERS. Every field in the chain except the first one *must* be a **.01** field, since POINTERS point to files, *not* fields; the first POINTER field may or may *not* be a **.01** field.

When VA FileMan converts a POINTER or VARIABLE POINTER to its external value, it *must* follow the links to the final field and convert that field to its external value. An OUTPUT transform on a POINTER field, therefore, *must* do the same. The flags available for this function allow developers to try out different ways of handling OUTPUT transforms on POINTER fields. These flags only alter this function's behavior, however. The rest of VA FileMan continues to treat OUTPUT transforms on POINTER chains as described under the **F** flag (under "[Input Parameters](#)").

## 3.5.36 \$\$FLDNUM^DILFD(): Field Number Retriever

The \$\$FLDNUM^DILFD extrinsic function returns a field number when passed a file number and a field name.

### Format

```
$$FLDNUM^DILFD(file,fieldname)
```

### Input Parameters

file: (Required) The file number of the field's file or subfile.

fieldname: (Required) The full name of the field for which you want the number.

### Output

The field number of the requested field is returned by this extrinsic function. If the field name does *not* exist or if there is more than one field with that name, a zero (**0**) is returned.

### 3.5.36.1 Example

Figure 201: \$\$FLDNUM^DILFD API—Example: Input and Output

```
>W $$FLDNUM^DILFD(200,"DUZ(0)")  
3
```

### 3.5.36.2 Error Codes Returned

[Table 66](#) lists the possible error codes returned with the \$\$FLDNUM^DILF API:

**Table 66: \$\$FLDNUM^DILFD API—Error Codes Returned**

Code	Description
<a href="#">401</a>	The file does not exist.
<a href="#">501</a>	The file does not contain the field.
<a href="#">505</a>	More than one field has the name.

### 3.5.37 PRD^DILFD(): Package Revision Data Initializer

The PRD^DILFD API sets the PACKAGE REVISION DATA attribute for a file. The file data dictionary *must* exist in order to successfully set this attribute.

#### Format

```
PRD^DILFD(file,data)
```

#### Input Parameters

file: (Required) File or subfile number.

data: (Required) Free text information, determined by the developer.

#### Output

A successful call sets the data into the appropriate data dictionary location.

#### 3.5.37.1 Example

The call in [Figure 202](#) sets the PACKAGE REVISION DATA as follows:

**Figure 202: PRD^DILFD API—Example: Input and Output**

```
>D PRD^DILFD(999088,"REVISION #5")  
  
>W $$GET1^DID(999088,"","","PACKAGE REVISION DATA")  
REVISION #5
```

#### 3.5.37.2 Error Codes Returned

None.

### 3.5.38 RECALL^DILFD(): Recall Record Number

The RECALL^DILFD API saves a record number for later retrieval using **Spacebar Recall**. While Classic VA FileMan has automatically performed this procedure for applications in the past, the VA FileMan DBS lookup calls *cannot* do so. The decision to perform this procedure can only be made by code that knows its context, which knows whether the selection taking place results from a user's selection or from some silent activity. In addition, VA FileMan often is inactive when a user selection occurs (e.g., when a user picks a single entry from a listbox managed by the application). For these reasons, the maintenance of the **Spacebar Recall** feature is increasingly the responsibility of the applications.

#### Format

```
RECALL^DILFD(file,iens,user)
```

#### Input Parameters

- file: (Required) The file or subfile number.
- iens: (Required) The IENS that identifies the record selected.
- user: (Required) The user number (i.e., DUZ) of the user who made the selection.

#### 3.5.38.1 Example

Figure 203: RECALL^DILFD API—Example: Input and Output

```
>D RECALL^DILFD(19,"1","9) W $G(DIERR) D ^%G

Global ^DISV(9,"^DIC(19,"
      DISV(9,"^DIC(19,"
^DISV(9,"^DIC(19,") = 1
```

#### 3.5.38.2 Error Codes Returned

[Table 67](#) lists the possible error codes returned with the RECALL^DILFD API:

Table 67: RECALL^DILFD API—Error Codes Returned

Code	Description
<a href="#">202</a>	An input parameter is missing or invalid.
<a href="#">205</a>	The FILE and IENS represent different subfile levels.
<a href="#">401</a>	File # does not exist.
<a href="#">402</a>	The global root is missing or not valid.


### 3.5.39 \$\$ROOT^DILFD(): File Root Resolver

The \$\$ROOT^DILFD intrinsic function resolves the file root when passed file or subfile numbers. At the top-level of the file \$\$ROOT^DILFD returns the global name. When passing a subfile number, \$\$ROOT^DILFD uses the IENS to build the root string.

#### Format

```
$$ROOT^DILFD(file[,iens][,flags][,error_flag])
```

#### Input Parameters

- file:** (Required) File number or subfile number.
- iens:** (Optional) If the **file** parameter equals a file number, the Lister ignores the **iens** parameter. If the **file** parameter equals a subfile number, the Lister needs the **iens** parameter to help identify which subfile to list. In other words, files can be specified with the **file** parameter alone, but subfiles require both the **file** and **iens** parameters.
- When the **iens** parameter is used, it *must* equal an IENS that identifies the parent record of the exact subfile to list. Since this parameter identifies the subfile under that record, and *not* the subrecord itself, the first comma-piece of the parameter should be empty. If the first comma-piece of the **iens** parameter is *not* empty, that first comma-piece is ignored.
-  **REF:** For more information on the IENS, see the discussion in the “[IENS: Identify Entries and Subentries](#)” in the “[Database Server \(DBS\) API](#)” section.
- For example, to specify the Menu Item subfile under option number 67, you *must* pass FILE=19.01 (the subfile number for the Menu subfile) and IENS=“,67,” (showing that record number 67 holds the Menu subfile you want to list).
- Defaults to empty string.
- flags:** (Optional) If set to **1 (true)**, returns a closed root. The default is to return an open root.
- error\_flag:** (Optional) If set to **1 (true)**, processes an error message if an error is encountered.

#### 3.5.39.1 Examples

##### 3.5.39.1.1 Example 1

Figure 204: \$\$ROOT^DILFD API—Example 1: Input and Output

```
>S DIC=$$ROOT^DILFD(999000.07, "1,38,")
>W DIC
^DIZ(999000,38,2,
```



### 3.5.39.1.2 Example 2

Figure 205: \$\$ROOT^DILFD API—Example 2: Input and Output

```
>S DIC=$$ROOT^DILFD(999000)

>W DIC
^DIZ(999000,
```

### 3.5.39.1.3 Example 3

Figure 206; \$\$ROOT^DILFD API—Example 3: Input and Output

```
>S CROOT=$$ROOT^DILFD(999000,"",1)

>W CROOT
^DIZ(999000)
```

## 3.5.39.2 Error Codes Returned

[Table 68](#) lists the possible error codes returned with the \$\$ROOT^DILFD API:

Table 68: \$\$ROOT^DILFD API—Error Codes Returned

Code	Description
<a href="#">200</a>	Invalid parameter
<a href="#">205</a>	The File and IENS represent different subfile levels.

## 3.5.40 \$\$VFIELD^DILFD(): Field Verifier

The \$\$VFIELD^DILFD extrinsic function verifies that a field in a specified file exists.

### Format

```
$$VFIELD^DILFD(file,field)
```

### Input Parameters

file: (Required) The number of the file or subfile in which the field to be checked exists.

field: (Required) The number of the field to be checked.

### Output

This Boolean function returns the following:

- **1**—If the field exists in the specified file.
- **0**—If the field does *not* exist in the specified file.

### 3.5.40.1 Example

Figure 207: \$\$VFIELD^DILFD API—Example: Input and Output

```
>W $$VFIELD^DILFD(200,99999)
0
```

### 3.5.40.2 Error Codes Returned

None.

## 3.5.41 \$\$VFILE^DILFD(): File Verifier

The \$\$VFILE^DILFD extrinsic function verifies that a file exists.

### Format

```
$$VFILE^DILFD(file)
```

### Input Parameters

file: (Required) The number of the file or subfile that you want to check.

### Output

This Boolean extrinsic function returns the following:

- **1**—If the file exists.
- **0**—If the file does *not* exist.

### 3.5.41.1 Example

Figure 208: \$\$VFILE^DILFD API—Example: Input and Output

```
>W $$VFILE^DILFD(200)
1
```

### 3.5.41.2 Error Codes Returned

None.

### 3.5.42 \$\$GET1^DIQ(): Data Retriever (Single Field)

The \$\$GET1^DIQ extrinsic function retrieves data from a single field in a file.

Data can be retrieved from any field, including COMPUTED or WORD-PROCESSING fields, and fields specified using relational syntax. A basic call does *not* require that any local variables be present and the symbol table is *not* changed by this utility. However, computed expressions can require certain variables be present and can change the symbol table, because the data retriever does execute data dictionary nodes.

The text for WORD-PROCESSING fields is returned in a target array. If data exists for WORD-PROCESSING fields, this function returns the resolved **target\_root**; otherwise, null is returned.

#### Format

```
$$GET1^DIQ(file,iens,field[,flags],target_root[,msg_root])
```

#### Input Parameters

file:	(Required) A file number or subfile number.
iens:	(Required) Standard Internal Entry Number String (IENS) indicating internal entry numbers.
field:	(Required) Any of the following: <ul style="list-style-type: none"><li>• Field number</li><li>• Field name</li><li>• On-the-fly computed expression for the <b>file</b></li></ul>
flags:	(Optional) Flags to control processing. The possible values are: <ul style="list-style-type: none"><li>• <b>I</b>—Internal format is returned. (The default is external.)</li><li>• <b>Z</b>—Zero node included for WORD-PROCESSING fields on target array.</li><li>• <b>A#</b>—Audit Trail is used to retrieve the value of “FIELD” at a particular point in time. # is a date/time in VA FileMan internal format (e.g., 3021015.8). The value retrieved is the (audited) value of the field as of that date/time.</li></ul>
target_root:	(Required for WORD-PROCESSING fields only) The root of an array into which word-processing text is copied.
msg_root:	(Optional) Closed root into which the error message arrays are put. If this parameter is <i>not</i> passed, the arrays are put into nodes descendent from ^TMP.

#### 3.5.42.1 Examples

##### 3.5.42.1.1 Example 1

[Figure 209](#) is an example of retrieving the value from the .01 field of record #1 in (fictitious) File #999000:

**Figure 209: \$\$GET1^DIQ API—Example 1: Input and Output**

```
>W $$GET1^DIQ(999000,"1",".01")
FMPATIENT,TWENTY
```

### 3.5.42.1.2 Example 2

[Figure 210](#) is an example of retrieving the internally-formatted value from the SEX field of Record #1 in (fictitious) File #999000:

**Figure 210: \$\$GET1^DIQ API—Example 2: Input and Output**

```
>S X=$$GET1^DIQ(999000,"1","","SEX","I")
>W X
M
```

### 3.5.42.1.3 Example 3

Use the SUBTYPE pointer field in the DEVICE (#3.5) file to navigate to the TERMINAL TYPE (#3.2) file and retrieve the DESCRIPTION field as follows:

**Figure 211: \$\$GET1^DIQ API—Example 3: Input and Output**

```
>S X=$$GET1^DIQ(3.5,"55","","SUBTYPE:DESCRIPTION")
>W X
WYSE 85
```

### 3.5.42.1.4 Example 4

[Figure 212](#) is an example of retrieving the contents of a WORD-PROCESSING field and storing the text in the target array, **WP**:

**Figure 212: \$\$GET1^DIQ API—Example 4: Input and Output**

```
>S X=$$GET1^DIQ(999000,"1","","12","","WP")
>ZW
WP(1)=THIS WP LINE 1
WP(2)=WP LINE2
WP(3)=AND SO ON
X=WP
```

### 3.5.42.1.5 Example 5

Retrieve the contents of a WORD-PROCESSING field, storing the text in the target array, **WP**. The format parameter **Z** means the target array is formatted like the nodes of a VA FileMan WORD-PROCESSING field. If no data exists, **WP** is equal to null as shown in [Figure 213](#):

**Figure 213: \$\$GET1^DIQ API—Example 5: Input and Output**

```
>S WP=$$GET1^DIQ(999000,1,12,"Z","","WP") ZW WP
WP=WP
WP(1,0)=THIS WP LINE 1
WP(2,0)=WP LINE2
WP(3,0)=AND SO ON
```

### 3.5.42.1.6 Example 6

[Figure 214](#) is an example of retrieving data from a subfile. Here is a partial record entry, number 323, in ^DIZ(999000):

**Figure 214: \$\$GET1^DIQ API—Example 6: Input and Output**

```

^DIZ(999000,323...
.
.
^DIZ(999000,323,4,2,1,0) = ^999000.163^1^1
^DIZ(999000,323,4,2,1,1,0) = XXX2M3F.01^XXX2M3F1^XXX2M3F2
^DIZ(999000,323,4,2,1,"B","XXX2M3F.01",1) =
^DIZ(999000,323,4,"B","XXX1",1) =
^DIZ(999000,323,4,"B","XXX2",2) =

>S IENS="1,2,323,"
>W $$GET1^DIQ(999000.163,IENS,2)
XXX2M3F2

```

### 3.5.42.1.7 Example 7

[Figure 215](#) retrieves the value of the .01 field of record #1 in (fictitious) File #999000 as of 1 January, 2000. Suppose that auditing has been turned on for that field, and that early in 2000, an incorrect spelling of "FMPATIENCE,TWENTY" had been corrected:

**Figure 215: \$\$GET1^DIQ API—Example 7: Input and Output**

```

>W $$GET1^DIQ(999000,"1",.01,"A3000000")
FMPATIENCE,TWENTY

```

### 3.5.42.2 Error Codes Returned

[Table 69](#) lists the possible error codes returned with the \$\$GET1^DIQ API:

**Table 69: \$\$GET1^DIQ API—Error Codes Returned**

Code	Description
<a href="#">200</a>	There is an error in one of the variables passed.
<a href="#">202</a>	Missing or invalid input parameter.
<a href="#">301</a>	Flags passed are unknown or incorrect.
<a href="#">309</a>	Either the root of the Multiple or the necessary entry numbers are missing.
<a href="#">348</a>	The passed value points to a file that does not exist or lacks a Header Node.
<a href="#">401</a>	The specified file or subfile does not exist.
<a href="#">403</a>	The file lacks a Header Node.
<a href="#">404</a>	The file Header Node lacks a file #.
<a href="#">501</a>	The field name or number does not exist.
<a href="#">505</a>	The field name passed is ambiguous.
<a href="#">510</a>	The data type for the specified field cannot be determined.

Code	Description
<a href="#">520</a>	An incorrect kind of field is being processed.
<a href="#">537</a>	Field has a corrupted pointer definition.
<a href="#">601</a>	The entry does not exist.
<a href="#">602</a>	The entry is not available for editing.
<a href="#">603</a>	A specific entry in a specific file lacks a value for a required field.
<a href="#">648</a>	The value points to a file that does not exist or lacks a Header Node.

### 3.5.43 GETS^DIQ(): Data Retriever (Multiple Fields)

The GETS^DIQ API retrieves one or more fields of data from a record or sub-records and places the values in a target array.

#### Format

```
GETS^DIQ(file,iens,field[,flags],target_root[,msg_root])
```

#### Input Parameters

- file: (Required) File or subfile number.
- iens: (Required) Standard IENS indicating internal entry numbers.
- field: (Required) Can be one of the following:
- A single field number.
  - A list of field numbers, separated by semicolons.
  - A range of field numbers, in the form *M:N*; where *M* and *N* are the end points of the inclusive range. All field numbers within this range are retrieved.
  - Asterisk (\*) For all fields at the top-level (no sub-Multiple record).
  - Double asterisk (\*\*) For all fields including all fields and data in sub-Multiple fields.
  - Field number of a Multiple followed by an \* to indicate all fields and records in the sub-Multiple for that field.
- flags: (Optional) Flags to control processing. The possible values are:
- **E**—Returns **E**xternal values in nodes ending with **E**.
  - **I**—Returns **I**nternal values in nodes ending with **I**; otherwise, external is returned.
  - **N**—Does not return **N**ull values.
  - **R**—**R**esolves field numbers to field names in target array subscripts.
  - **Z**—**Z**WORD-PROCESSING fields include **Z**ero nodes.

- **A#**—Audit Trail is used to retrieve the value of “**FIELD**” at a particular point in time.

# is a date/time in VA FileMan internal format (e.g., 3021015.08). The values retrieved are the (audited) values of the fields as of that date/time.

target\_root: (Required) The name of a closed root reference.  
 msg\_root: (Optional) The name of a closed root reference that is used to pass error messages.

## Output

target\_root: The output array is in the **FDA** format:

**TARGET\_ROOT(FILE,IENS,FIELD)=DATA**

WORD-PROCESSING (WP) fields have data descendent from the field nodes in the output array.

### 3.5.43.1 Examples

#### 3.5.43.1.1 Example 1

[Figure 216](#) retrieves the values of all fields for a record.

**Figure 216: GETS^DIQ API—Example 1: Input and Output**

```
>D GETS^DIQ(999000,"1","**","","ARRAY")

>ZW
ARRAY(999000,"1",",.01)=TEST1
ARRAY(999000,"1",",1)=OCT 01, 1992
ARRAY(999000,"1",",2)=YES
ARRAY(999000,"1",",3)=1
ARRAY(999000,"1",",4)=DTM-PC
ARRAY(999000,"1",",5)=SUPPORTED
ARRAY(999000,"1",",6)=S Y="SET Y=TO THIS"
ARRAY(999000,"1",",8)=AUDIT,Z
ARRAY(999000,"1",",9)=ACCESS,Z
ARRAY(999000,"1",",10)=GRP,Z
ARRAY(999000,"1",",11)=DESCRIP,Z
ARRAY(999000,"1",",12)=ARRAY(999000,"1",",12)
ARRAY(999000,"1",",12,1)=THIS WP LINE 1
ARRAY(999000,"1",",12,2)=WP LINE2
ARRAY(999000,"1",",12,3)=AND SO ON
ARRAY(999000,"1",",13)=LASTNAME,FIRST
ARRAY(999000.07,"1,1",",.01)=TEST1 ONE
ARRAY(999000.07,"1,1",",1)=
ARRAY(999000.07,"2,1",",.01)=TEST1 TWO
ARRAY(999000.07,"2,1",",1)=
ARRAY(999000.07,"3,1",",.01)=TEST1 THREE
ARRAY(999000.07,"3,1",",1)=
ARRAY(999000.07,"4,1",",.01)=TEST1 FOUR
ARRAY(999000.07,"4,1",",1)=MUMPS
```

### 3.5.43.1.2 Example 2

[Figure 217](#) retrieves the values of all fields for a record, excluding Multiples.

**Figure 217: GETS^DIQ API—Example 2: Input and Output**

```
>D GETS^DIQ(999000,"1","","*", "", "ARRAY1")

>ZW
ARRAY1(999000,"1", ".01")=TEST1
ARRAY1(999000,"1", ",1)=OCT 01, 1992
ARRAY1(999000,"1", ",2)=YES
ARRAY1(999000,"1", ",3)=1
ARRAY1(999000,"1", ",4)=DTM-PC
ARRAY1(999000,"1", ",5)=SUPPORTED
ARRAY1(999000,"1", ",6)=S Y="SET Y=TO THIS"
ARRAY1(999000,"1", ",8)=AUDIT,Z
ARRAY1(999000,"1", ",9)=ACCESS,Z
ARRAY1(999000,"1", ",10)=GRP,Z
ARRAY1(999000,"1", ",11)=DESCRIP,Z
ARRAY1(999000,"1", ",12)=ARRAY(999000,"1", ",12)
ARRAY1(999000,"1", ",12,1)=THIS WP LINE 1
ARRAY1(999000,"1", ",12,2)=WP LINE2
ARRAY1(999000,"1", ",12,3)=AND SO ON
ARRAY1(999000,"1", ",13)=LASTNAME,FIRST
```

### 3.5.43.1.3 Example 3

[Figure 218](#) retrieves both internal and external values of three specific fields for a record.

**Figure 218: GETS^DIQ API—Example 3: Input and Output**

```
>D GETS^DIQ(999000,"1","",".01;3;5", "IE", "ARRAY3")

>ZW
ARRAY3(999000,"1", ".01, "E")=TEST1
ARRAY3(999000,"1", ".01, "I")=TEST1
ARRAY3(999000,"1", ",3, "E")=1
ARRAY3(999000,"1", ",3, "I")=1
ARRAY3(999000,"1", ",5, "E")=SUPPORTED
ARRAY3(999000,"1", ",5, "I")=
```



### 3.5.43.1.4 Example 4

[Figure 219](#) retrieves both internal and external values for a range of fields in a record.

**Figure 219: GETS^DIQ API—Example 4: Input and Output**

```
>D GETS^DIQ(999000,"1",".01:6","IE","ARRAY4")

>ZW
ARRAY4(999000,"1",".01","E")=TEST1
ARRAY4(999000,"1",".01","I")=TEST1
ARRAY4(999000,"1","1","E")=OCT 01, 1992
ARRAY4(999000,"1","1","I")=2921001
ARRAY4(999000,"1","2","E")=NO
ARRAY4(999000,"1","2","I")=0
ARRAY4(999000,"1","3","E")=66
ARRAY4(999000,"1","3","I")=66
ARRAY4(999000,"1","4","E")=DTM-PC
ARRAY4(999000,"1","4","I")=9
ARRAY4(999000,"1","5","E")=SUPPORTED
ARRAY4(999000,"1","5","I")=
ARRAY4(999000,"1","6","E")=S Y="SET Y=TO THIS"
ARRAY4(999000,"1","6","I")=S Y="SET Y=TO THIS"
```

### 3.5.43.1.5 Example 5

[Figure 220](#) retrieves the values of five specific fields, including all of the values of a Multiple field.

**Figure 220: GETS^DIQ API—Example 5: Input and Output**

```
>D GETS^DIQ(999000,"1",".01;3;7*;11;13","","ARRAY5")

>ZW
ARRAY5(999000,"1",".01)=TEST1
ARRAY5(999000,"1","3)=1
ARRAY5(999000,"1","11)=DESCRIP,Z
ARRAY5(999000,"1","13)=LASTNAME,FIRST
ARRAY5(999000.07,"1,1",".01)=TEST1 ONE
ARRAY5(999000.07,"1,1","1)=
ARRAY5(999000.07,"2,1",".01)=TEST1 TWO
ARRAY5(999000.07,"2,1","1)=
ARRAY5(999000.07,"3,1",".01)=TEST1 THREE
ARRAY5(999000.07,"3,1","1)=
ARRAY5(999000.07,"4,1",".01)=TEST1 FOUR
ARRAY5(999000.07,"4,1","1)=MUMPS OS
```

## 3.5.43.2 Error Codes Returned

[Table 70](#) lists the possible error codes returned with the GETS^DIQ API API:

**Table 70: GETS^DIQ API—Error Codes Returned**

Code	Description
<a href="#">200</a>	There is an error in one of the variables passed.
<a href="#">202</a>	Missing or invalid input parameter.
<a href="#">301</a>	Flags passed are unknown or incorrect.
<a href="#">309</a>	Either the root of the Multiple or the necessary entry numbers are missing.

<b>Code</b>	<b>Description</b>
<a href="#">348</a>	The passed value points to a file that does not exist or lacks a Header Node.
<a href="#">401</a>	The specified file or subfile does not exist.
<a href="#">403</a>	The file lacks a Header Node.
<a href="#">404</a>	The file Header Node lacks a file #.
<a href="#">501</a>	The field name or number does not exist.
<a href="#">505</a>	The field name passed is ambiguous.
<a href="#">510</a>	The data type for the specified field cannot be determined.
<a href="#">520</a>	An incorrect kind of field is being processed.
<a href="#">537</a>	Field has a corrupted pointer definition.
<a href="#">601</a>	The entry does not exist.
<a href="#">602</a>	The entry is not available for editing.
<a href="#">603</a>	A specific entry in a specific file lacks a value for a required field.
<a href="#">648</a>	The value points to a file that does not exist or lacks a Header Node.

# II. ScreenMan

## 4 ScreenMan Forms

### 4.1 Introduction

The basic steps to prepare and present screens to the user are:

1. Design the physical layout of the screens and determine data editing rules.
2. Use the [ScreenMan Form Editor](#) to create the form.
3. Test the form.
4. Invoke the form from an application.

The [ScreenMan Form Editor](#) provides sophisticated tools for creating new forms and editing existing ones. The [ScreenMan Form Editor](#) facilitates the composition process from the initial design through editing and completion. It allows you to place blocks and fields wherever you wish on the screen, and later to select and drag them to new positions.

In addition to allowing you to experiment with the “look” of the screen, the [ScreenMan Form Editor](#) eases the process of positioning:

- Popup pages
- Blocks
- Captions
- Edit windows



**REF:** See also:

- “[ScreenMan Form Editor](#)” section.
- “[ScreenMan API](#)” section, which describes the ScreenMan APIs you can use to load a form and to use within a form.
- *ScreenMan Tutorial for Developers Manual*, located on the VDL at: <http://www4.va.gov/vdl/application.asp?appid=5>.

## 4.2 Form Layout: Forms and Pages

### 4.2.1 Form Structure

A form is a series of screens that are presented to the user. A form contains one or more pages, a page contains one or more blocks, and a block contains one or more fields.

Structurally, the form is an entry in the FORM (#.403) file. The FORM (#.403) file contains a PAGE Multiple, and the PAGE Multiple contains a BLOCK Multiple. The **.01** field of the BLOCK Multiple is a pointer to the BLOCK (#.404) file. The BLOCK (#.404) file contains a Multiple for fields.

Because of this structure, blocks in the BLOCK (#.404) file are reusable (i.e., the same block can be placed on more than one page and on more than one form).

Each block in the BLOCK (#.404) file that contains VA FileMan fields has a [DD Number](#) property. Each block can contain fields from only one file or subfile, as determined by this **DD Number**.

## 4.2.2 Linking Pages of a Form

When a form is first invoked and the user is presented with the first page, conceptually, the user is at the top-level of the form. When the user goes to the next or previous pages, the user remains at the top-level. Only at this level can the user exit or quit the form or save changes made during the editing session.

When the user opens up a subpage, however, the user has descended a level. At this level and at lower levels, the user can only close the current page, or issue the **Refresh** command to repaint the screen; the user *cannot* exit or quit the form or save any changes.

Pages on a form can be linked together in a variety of ways. The following lists the places where links can be defined:

- Pages at the same level:
  - The [Next Page](#) property of a page.
  - The [Previous Page](#) property of a page.
  - The **DDSBR** variable in the [Branching Logic](#) property of a field or in [Pre Action](#) and [Post Action](#) page properties.
- Pages at different levels:
  - The [Parent Field](#) property of a page.
  - The [Subpage Link](#) property of a field.
  - The [DDSSTACK](#) variable in the [Branching Logic](#) property of a field.

Both the [Next Page](#) and [Previous Page](#) properties link pages at the same level. The user can go to the next and previous pages by pressing <PF1><ARROW DOWN> and <PF1><ARROW UP>, respectively. Pages linked via the **Next Page** and **Previous Page** links *must* be regular pages; they *cannot* be “popup” pages. Use the [DDSBR](#) variable to take the user to another page under conditions you specify.

Both the [Parent Field](#) and [Subpage Link](#) properties allow you to take the user to a subpage at a lower level when the user presses the **Enter** key at a field on the parent page. The subpage can be either a regular or a “popup” page. A “popup” page is usually preferable, since it gives users a better indication that they have descended a level and *must* close the subpage to return to the previous level. After the user closes the subpage, ScreenMan automatically returns to the previous level (i.e., to the parent page from where the branch occurred).

The difference between the **Parent Field** property and the **Subpage Link** property is where the link is defined:

- **Parent Field**—Defined with the subpage and indicates the field from which the branch should occur.
- **Subpage Link**—Defined with the field and indicates the subpage to which the branch should occur.

In a sense, the difference between these two properties is the direction of the “pointer:”

- **Parent Field**—Points from the subpage to the field.
- **Subpage Link**—Points from the field to the subpage.


Where you choose to define the link is a matter of personal preference. However, the disadvantage of defining the link in the **Subpage Link** property is that the block on which the field is defined may *not* be reusable on other forms, since the link points to a specific page on the form.

You *must* use either the **Parent Field** or the **Subpage Link** property to link a Multiple field on a form to a subpage that contains the fields within the Multiple.

Use the **DDSSTACK** variable to link a field to a subpage. It behaves just like the **Parent Field** and **Subpage Link** properties, but because it is set in M code in the Branching Logic property of a field, **DDSSTACK** lets you branch conditionally.

[Figure 221](#) illustrates the various page links:

**Figure 221: ScreenMan Forms—DDSSTACK Variable: Sample Page Links**



## 4.3 Features

### 4.3.1 Displaying Multiples in Repeating Blocks

You can display more than one subrecord in a Multiple simultaneously on the screen.



**REF:** See the “Multiples” section in the *VA FileMan User Manual*.

You do this by defining a **repeating block**, a block that has a [Replication](#) property value greater than **1**. The **Replication** number defines the number of times the fields on the block appear on the screen. Fields can occupy multiple lines, and are repeated together. The [DD Number](#) property of the block corresponds to the subfile number of the Multiple.

You should reserve one column to the left of the repeating block for ScreenMan to display the plus sign (+) indicator before the first and last lines of the list.

[Figure 222](#) shows two subfields of a Multiple displayed in a repeating block:

**Figure 222: ScreenMan Forms—Sample of Two Subfields of a Multiple Displayed in a Repeating Block**

```

                                     A TEST FORM

NAME: FMPATIENT, ONE
DATE: DEC 1, 1994

      NAME MULT 1                      SET OF CODES
      -----
+SECOND SUBRECORD                      FEBRUARY
THIRD SUBRECORD                         MARCH
FOURTH SUBRECORD                       APRIL
FIFTH SUBRECORD                        MAY
+SIXTH SUBRECORD                       JUNE

-----
Exit      Save      Refresh

Enter a command or '^' followed by a caption to jump to a specific field.

COMMAND:                                     Press H for help Insert
```

The subfields are NAME MULT1 and SET OF CODES. The repeating block has a **Replication** value of 5; therefore, up to five subrecords can be displayed simultaneously. The coordinate of the repeating block corresponds to the position of the first line in the list.

The column headings are defined as caption-only fields on another block that is *non-repeating*.

The last line in the scrolling list is blank. This is where the user can add a subrecord by entering a new name or jump to a particular entry in the list by entering the name of an existing subrecord. By default, this blank line is positioned in the same column as the first editable field in the repeating block.

[Table 71](#) lists the variables that are available in the pre- and post-actions of fields on the repeating block, as well as in the Executable Caption code:

**Table 71: ScreenMan Forms—Variables Available in Repeating Blocks**

Local Variable	Description
<b>DDSSN</b>	The sequence number in the list of the current subrecord.
<b>DDSLN</b>	The line number in the repeating block on which the cursor is currently resting.

The block properties in [Table 72](#) apply only to repeating blocks:

**Table 72: ScreenMan Forms—Block Properties that Apply only to Repeating Blocks**

Repeating Block Property	Description
Replication	The number of times the fields defined in this block should be replicated. This number <i>must</i> be greater than <b>1</b> .
Index	(Optional) The name of the index that should be used to pick up the subrecords in the Multiple. The subrecords will initially be sorted in the order defined by this index. The default Index is <b>B</b> . If the Multiple has no <b>B</b> index, or to display the subentries in record number order, enter the following: <b>!!EN</b>
Initial Position	(Optional) This is where the cursor should rest when the user first navigates to the repeating block. Possible values are: <ul style="list-style-type: none"> <li>• <b>FIRST</b></li> <li>• <b>LAST</b></li> <li>• <b>NEW</b>—Where <b>NEW</b> indicates that the cursor should initially rest on the blank line at the end of the list.</li> </ul> The default Initial Position is <b>FIRST</b> .
Disallow LAYGO	(Optional) If set to <b>YES</b> , this prohibits the user from entering new subrecords into the Multiple.
Field for Selection	(Optional) This is the field order of the field that defines the column position of the blank line at the end of the list. The default is the first editable field in the block. This is also the field before which ScreenMan prints the plus sign (+) to indicate there are more entries above or below the displayed list.

### 4.3.2 Form-Only Fields

Form-only fields are fields that are defined only on the form. They allow you to request from the user data that is *not* linked to a VA FileMan field. You might use a form-only field to control the flow of data input. For example, when the user presses the **Enter** key at a form-only field, you might branch to a “popup” page (window) or branch only if the user enters a certain value. You might also use a form-only field to:

1. Request data from the user.
2. Store the response in a local or global variable.
3. Process the response after the user exits the form.

When you define a form-only field, you specify parameters that look like the VA FileMan Reader ([^DIR](#)) parameters. In addition, you can define **Save Code**, code that is executed when the user issues the **Save** command. You might use the **Save Code** to store the value entered by the user in local or global variables.

[Table 73](#) describes the field properties that pertain only to Form-Only fields.



**REF:** For more detailed information about the Reader parameters, see the "[^DIR: Response Reader](#)" section in the "[Classic VA FileMan API](#)" section.

**Table 73: ScreenMan Forms—Properties of Form-Only Fields**

Form Only Field Property	Description
Read Type	This property defines the type of the form-only field. Valid values are: <ul style="list-style-type: none"> <li>• <b>D</b>—DATE</li> <li>• <b>F</b>—FREE TEXT</li> <li>• <b>L</b>—LIST OR RANGE</li> <li>• <b>N</b>—NUMERIC</li> <li>• <b>P</b>—POINTER</li> <li>• <b>S</b>—SET OF CODES</li> <li>• <b>Y</b>—YES OR NO</li> <li>• <b>DD</b>—DATA DICTIONARY</li> </ul>
Parameters	This property corresponds to the parameters that can be used in the first ^-piece of the <b>DIR(0)</b> input variable to <a href="#">^DIR</a> . The <b>O</b> parameter has no effect, since the <a href="#">Required</a> property can be used to make a field required.
Qualifiers	This property corresponds to the second ^- piece of the <b>DIR(0)</b> input variable to <a href="#">^DIR</a> .
Help (WP)	The lines in this word-processing field correspond to the nodes in the <b>DIR("?",#)</b> input array to <a href="#">^DIR</a> .
INPUT Transform	This property corresponds to the third ^-piece of the <b>DIR(0)</b> input variable to <a href="#">^DIR</a> .
Screen	This is M code that sets the variable <b>DIR("S")</b> .
Save Code	This is M code that is executed when the user issues a <b>Save</b> command and ScreenMan has detected a change to the value of the form-only field.



### 4.3.3 Relational Navigation: Forward Pointers

On a page of a form, you can place a block that contains fields from a file other than the Primary file of the form. If the file is reached via a forward pointer, you *must* define a [Pointer Link](#) for that block. The syntax of the **Pointer Link** property is similar to VA FileMan’s relational syntax. When you define the **Pointer Link**, your point of reference is the Primary file of the form.

In [Figure 223](#), the Primary file of the form is the (fictitious) ORDER (#16202) file. There are two blocks on the page. Block A contains fields from the (fictitious) ORDER (#16202) file, and Block B contains fields from the (fictitious) CUSTOMER (#16201) file. CUSTOMER NAME in the (fictitious) ORDER (#16202) file points to the (fictitious) CUSTOMER (#16201) file.

**Figure 223: ScreenMan Forms—Relational Navigation: Forward Pointers**

```
BLOCK A, CONTAINS FIELDS FROM THE ORDER FILE, #16202

ORDER ID: A24680
CUSTOMER NAME: FMPATIENT, ONE

This field points to the (fictitious) CUSTOMER file.

ORDER DATE: SEP 1, 1994
ORDER AMOUNT: 12.31

BLOCK B, CONTAINS FIELDS FROM THE ORDER FILE, #16201

NAME: FMPATIENT, ONE
STREET: 123 FIRST STREET
CITY: ANYTOWN
STATE: CALIFORNIA
ZIP: 99999

Exit      Save      Refresh

Enter a command or ^^ followed by a caption to jump to a specific field.

COMMAND:                                     Press <PF1>H for help  Insert
```

If CUSTOMER NAME is Field #1, the **Pointer Link** property for Block B can be set to either “CUSTOMER NAME” or 1. The following sections describe in more detail the syntax for the **Pointer Link** property:

- [Syntax for Pointer Link—Navigating Via DD Fields](#)
- [Syntax for Pointer Link—Navigating Via Form Only Fields](#)


### 4.3.3.1 Syntax for Pointer Link—Navigating Via DD Fields

In the valid formats listed in [Table 74](#):

- “**Pfield**” is a pointer-type field.
- Both “**Pfield**” and “**Field**” can be either field names or field numbers.
- “**Mult\_field**” is the name or number of a Multiple field.
- “**File**” is the name or number of a file.

A file or field name can be enclosed in quotation marks.

**Table 74: ScreenMan Forms—Valid Formats for DD Fields**

Format	Explanation
Pfield	The Primary file of the form has a <b>Pfield</b> field that points to the file associated with the block. That pointer field determines the record to display in the pointed-to block.
Pfield_1:Pfield_2: ... :Pfield_n	The pointed-to block is reached after relational jumps across many files. Here, <b>Pfield_1</b> in the Primary file points to File #2 that contains a <b>Pfield_2</b> that points to File #3, etc. Finally, <b>Pfield_n</b> points to the file associated with the block being defined.
Field;Opt_spec	<p>The value of <b>Field</b> in the Primary file should be used to do a lookup into the file associated with the block.</p> <p>You can control how the lookup is done by using any of the following optional specifiers (Opt_spec):</p> <ul style="list-style-type: none"> <li>• <b>;I</b>—Use the Internal form of the field value for the lookup.</li> <li>• <b>;L</b>—Allow LAYGO.</li> <li>• <b>;IX(xref list)</b>—Use specific Indexes in the lookup. For example, <b>;IX(B^C)</b> specifies that the <b>B</b> and <b>C</b> index should be used. If the specifier is <i>not</i> used, all indexes starting with the <b>B</b> index are used in the lookup.</li> </ul>
Field;Opt_spec:File:Pfield_1: Pfield_2: ... :Pfield_n	<p>The pointed-to block is reached after relational jumps across many files. The first jump is accomplished with a lookup into File.</p> <p> <b>REF:</b> See <a href="#">Opt_spec</a>.</p>
Mult_field_1:Mult_field_2: ... :Mult_field_n:Pfield	The pointed-to block is reached after descending into subfiles of the Primary file and finally a relational jump via a pointer field within a subfile.

### 4.3.3.2 Syntax for Pointer Link—Navigating Via Form Only Fields

Form-only fields can also be used to relationally link blocks.

In the formats in [Table 75](#):

- The characters “**FO**” indicate that a form-only field is being identified.
- “**Pform\_only**” is a pointer-type form-only field.
- “**Form\_only**” is a form-only field that is *not* a pointer.

Form\_only and Pform\_only are three-piece comma-delimited strings that uniquely identify form-only fields on the form. They have the following format:


Field\_id,Block\_id,Page\_id

Where:

- Field\_id = Field Order number; or Caption of the field; or Unique Name of the field
- Block\_id = Block Order number; or Block Name
- Page\_id = Page Number; or Page Name (required only if Block Order number is used to identify the block)

**Table 75: ScreenMan Forms—Valid Formats for Form Only Fields**

Format	Explanation
FO(Pform_only)	The pointer-type form-only field is a pointer to the file associated with the block being defined. The contents of the form-only field determines the record to display in the pointed-to file.
FO(Pform_only):Pfield_1: ... Pfield_n	The pointed-to file is reached after relational jumps across many files. Here, the pointer-type form-only field points to File #1 that contains a <b>Pfield_1</b> that points to File #2, etc. Finally, <b>Pfield_n</b> points to the file associated with the block being defined.
FO(Form_only);Opt_spec	The value of the form-only field is used to do a lookup into the file associated with the block. You can control how the lookup is done by using any of the following optional specifiers (Opt_spec): <ul style="list-style-type: none"> <li>• <b>;I</b>—Use the Internal form of the field value for the lookup.</li> <li>• <b>;L</b>—Allow LAYGO.</li> <li>• <b>;IX(xref list)</b>—Use specific Indexes in the lookup. For example, <b>;IX(B^C)</b> specifies that the <b>B</b> and <b>C</b> index should be used. If this specifier is <i>not</i> used, all indexes starting with the <b>B</b> index are used in the lookup.</li> </ul>
FO(Form_only);Opt_spec:File: Pfield_1: ... Pfield_n	The pointed-to file is reached after relational jumps across many files. The first jump is accomplished with a lookup.

Format	Explanation
	 REF: See <a href="#">Opt_spec</a> .

### 4.3.4 Relational Navigation: Backward Pointers

Records reached via backward pointers appear to the user much like subrecords within a Multiple. To display the records in the pointing file, you can define a repeating block that has a **DD Number** property equal to the file number of the pointing file and an Index property equal to the name of the whole file cross-reference of the pointer field.



**REF:** For more information on how to define repeating blocks, see the “[Displaying Multiples in Repeating Blocks](#)” section.

### 4.3.5 Computed Fields

ScreenMan computed fields, like form-only fields, are fields that are defined only on the form. You *cannot* place computed fields from VA FileMan files on a form, because the M code for those fields often directly references data in files, which is outside the context of ScreenMan’s transaction.

When you define a ScreenMan computed field, you enter a computed expression. The computed expression has the following format:

M code that sets the local variable **Y**

For example:

**Figure 224: ScreenMan Forms—Computed Fields: Example of Format**

```
>S:$D(FLAG) Y=$P(MYVAR,"",2)_" " "$P(MYVAR,"")
```

The computed expression can reference any of the following used elsewhere on the form:

- Data dictionary fields
- Form-only fields
- Computed fields

If the user changes the value of a field used in a computed expression, ScreenMan automatically recalculates and repaints the computed field.

The expression atom that identifies other form elements has a syntax that uses curly braces ({} ) as described in [Table 76](#).

#### 4.3.5.1 Referencing Data Dictionary Fields

In the formats in [Table 76](#):

- “**Field**” is the name or number of a data dictionary field.
- “**Pfield**” is the name or number of a pointer-type data dictionary field.
- “**File**” is the name or number of a file.

**Table 76: ScreenMan Forms—Syntax for Computed Expression Atom that References a DD Field**

Format	Explanation
{Field;Opt_spec}	The value of <b>Field</b> is retrieved. An Opt_spec (optional specifier) can be used to retrieve the internal, rather than the external form: <b>;I</b> —Retrieve the Internal form of the <b>Field</b> value.
{Pfield:Field;Opt_spec}	<b>Pfield</b> is a pointer to a file. The value of <b>Field</b> in that file is retrieved. The Opt_spec value of <b>;I</b> can be used as described immediately above to retrieve the internal, rather than the external form.
{Field_1;Opt_spec1: File:Field_2;Opt_spec}	<b>Field_1</b> is <i>not</i> a pointer field. The value of <b>Field_1</b> is used to do a lookup into <b>File</b> . <b>Field_2</b> from that file is retrieved. An Opt_spec value of <b>;I</b> can be used to retrieve the internal rather than the external form. In addition, you can control how the lookup is done by using any of the following optional specifiers for Opt_spec1: <ul style="list-style-type: none"> <li><b>;I</b>—Use the Internal form of the field value for the lookup.</li> <li><b>;IX(xref list)</b>—Use specific <b>Indexes</b> in the lookup. For example, <b>;IX(B^C)</b> specifies that the <b>B</b> and <b>C</b> index should be used. If this specifier is <i>not</i> used, all indexes starting with the <b>B</b> index are used in the lookup.</li> </ul>

#### 4.3.5.2 Referencing Form-Only and Computed Fields

A computed expression atom can also reference form-only fields and computed fields used on the form.

In the formats listed in [Table 77](#):

- The syntax is similar to that for referencing data dictionary fields, except that “**FO(Form\_only)**” is used instead of “**Field.**”
- “**Form\_only**” is a three-piece comma-delimited string that identifies a form-only or computed field.



**REF:** For a description of the format of “**Form\_only**,” see the description of “[Syntax for Pointer Link—Navigating Via Form Only Fields.](#)”

**Table 77: ScreenMan Forms—Syntax for Computed Expression Atom that References a Form Only Field**

Format	Explanation
{FO(Form_only);Opt_spec}	<p>The value of <b>Form_only</b> is retrieved.</p> <p>An Opt_spec (optional specifier) can be used to retrieve the internal, rather than the external form.</p> <p><b>;I</b>—Retrieve the Internal form of the <b>Form_only</b> field.</p>
{FO(Pform_only: Field;Opt_spec)}	<p><b>Pfield_order</b> is a pointer-type form-only field that points to a file. The value of <b>Field</b> in that file is retrieved.</p> <p>The Opt_spec value of <b>;I</b> can be used as described above to retrieve the internal, rather than the external form.</p>
{FO(Form_only);Opt_spec1 :File:Field_2;Opt_spec}	<p><b>Form_only</b> is a form-only field that is <i>not</i> a pointer-type form-only field. The value of <b>Field_order</b> is used to do a lookup into <b>File</b>. <b>Field_2</b> from that file is retrieved.</p> <p>An Opt_spec value of <b>;I</b> can be used to retrieve the internal, rather than the external form.</p> <p>In addition, you can control how the lookup is done by using any of the following optional specifiers for Opt_spec1:</p> <ul style="list-style-type: none"> <li>• <b>;I</b>—Use the Internal form of the field value for the lookup.</li> <li>• <b>;IX(xref list)</b>—Use specific Indexes in the lookup. For example, <b>;IX(B^C)</b> specifies that the <b>B</b> and <b>C</b> index should be used. If this specifier is <i>not</i> used, all indexes starting with the <b>B</b> index are used in the lookup.</li> </ul>

**4.3.5.2.1 Example**

**Figure 225: ScreenMan Forms—Referencing Form-Only and Computed Fields: Example**

```

S Y="The value is: "_{NUMERIC}
S:$D(var)#2 Y="The value is: "_{NUMERIC}
S Y={LAST NAME}_", "_{FIRST NAME}
S Y={NAME}_ " "_{NAME:SSN}
S Y={FO(PRICE)}*1.085
S Y={FO(NAME):NEW PERSON:SSN}

```

### 4.3.6 DDSBR Variable

ScreenMan allows you to branch the user to a field under conditions you specify. You can do this by defining M code in the following properties:

- [Branching Logic](#)
- [Pre Action](#)
- [Post Action](#)
- [Post Action on Change](#) (at the field level)
- [Data Validation](#) (at the form level)

The M code can set the local variable **DDSBR** to a value that defines the location of the field to which you wish to take the user.

**DDSBR** has the following format:

```
DDSBR=Field id^Block id^Page id
```

Where:

- Field id = Field Order number; or Caption of the field; or Unique Name of the field
- Block id = Block Order number; or Block Name
- Page id = Page Number; or Page Name

For example:

**Figure 226: ScreenMan Forms—DDSBR Variable: Example**

```
S:X="Y" DDSBR="FIELD 1^BLOCK 1^PAGE 2"
```

This would take the user to the field with unique name or caption “FIELD 1” on the block named “BLOCK 1” on the page named “PAGE 2”, if the internal value of the field equals **Y**.

ScreenMan assumes values for any of the ^-pieces of **DDSBR** that are empty, as listed in [Table 78](#):

**Table 78: ScreenMan Forms—Assumptions when Pieces of DDSBR are Null**

If DDSBR is Set to:	ScreenMan Assumes:
Field id	Current block and current page.
Field id^Block id	Current page.
Field id^^Page id	Current block.
^Block id	Field with lowest Field Order, current page.
^Block id^Page id	Field with lowest Field Order.
^^Page id	Field with lowest Field Order, Block with lowest Block Order.

To branch the user to the command line, **DDSBR** takes the following format:

**Figure 227: ScreenMan Forms—DDSBR Variable: Example of Format to Branch the User to the Command Line**

```
>S DDSBR="COM"
```

### 4.3.7 DDSSTACK Variable

The **DDSSTACK** variable can be set only in the [Branching Logic](#) property of a field. It can be used to branch users to another page when they press **Enter** at the field. After the user closes the page defined in **DDSSTACK**, ScreenMan takes the user to the parent page, to the field immediately following the field from which the branch occurred.

Set **DDSSTACK** equal to a [Page Number](#) or [Page Name](#). For example:

**Figure 228: ScreenMan Forms—DDSSTACK Variable: Example of Setting Variable to a Page Number**

```
S:X="Y" DDSSTACK="Page 1.1"
```

This would take the user to Page 1.1 if the internal value of the field is **Y** and the user presses **Enter** at the field. When Page 1.1 is closed, the user returns to the parent page, to the field immediately following the field that contained the [Branching Logic](#).



**NOTE:** ScreenMan provides another way to achieve this kind of “branch and return” behavior. You can link a field to a subpage by defining a [Subpage Link](#) for the field or by defining a [Parent Field](#) for the subpage. The **Subpage Link** and **Parent Field** methods, however, do *not* allow branching conditionally.

### 4.3.8 Data Filing (When Is It Performed?)

With some important exceptions, the database is unaffected during a ScreenMan editing session. Changes are filed only at the user’s request.

However, there are two situations in which changes to the database are made immediately:

- When an entry is deleted from a file or subfile.
- When an entry is added to a file or subfile.

When the user attempts to delete an entry, ScreenMan issues a warning that deletions are immediate and permanent. Even if the user quits the form without saving the changes, the entry is *not* restored to the database.

Similarly, when the user adds an entry to a file or subfile, that entry is immediately added to the database. The entry is added with values for the **.01** field and all required identifiers. After the entry is added, however, changes made to the data for that entry are part of ScreenMan’s transaction and are filed only at the user’s request. Also, in contrast to deletions of entries, if the user subsequently quits the form *without* saving changes, entries added during the editing session are deleted.

Because of this, you should consider cross-references that can cause an overall state change when the user adds an entry and when ScreenMan subsequently deletes the entry. Triggers, bulletins, and MUMPS-type cross-references can cause irreversible events to occur. Therefore, when you design cross-references for the **.01** field and the required identifiers for entries the user can add or delete during an editing session, it is best to ensure that the **KILL** logic can undo the effects of the **SET** logic.



### 4.3.9 Word Processing Field Data Indication

WORD-PROCESSING fields display a plus sign (+) in the data section when there is existing data.

## 4.4 Form Property Reference

### 4.4.1 Form Properties

[Table 79](#) lists the Form properties:

**Table 79: ScreenMan Forms—Form Properties**

Property	Description
Form Name	(Required) The <b>Form Name</b> property is the <b>.01</b> field of the FORM (#.403) file. <b>Form Names</b> should be namespaced.
Title	The <b>Title</b> property can be used by the form designer to help identify a form. It is cross-referenced and need <i>not</i> be unique. ScreenMan does <i>not</i> automatically display the <b>Title</b> to the user, but the form designer can choose to create a caption-only field that displays the <b>Title</b> to the user.
Pre Action Post Action	The <b>Pre Action</b> property is M code that is executed when the form is first invoked; before any of the pages are loaded and displayed. The <b>Post Action</b> property is M code that is executed <i>before</i> ScreenMan returns to the calling application.
Data Validation	The <b>Data Validation</b> property is M code that is executed when the user attempts to save changes to the form. If the code sets <b>DDSERROR</b> , the user is unable to save changes. If the code sets <b>DDSBR</b> , the user is taken to the specified field.  In addition to the <a href="#">\$\$GET^DDSVAL</a> , <a href="#">PUT^DDSVAL</a> , <a href="#">\$\$GET^DDSVLF</a> , <a href="#">PUT^DDSVLF</a> , and <a href="#">HLP^DDSUTL</a> APIs, you can use the <a href="#">MSG^DDSUTL</a> API to print on a separate screen messages to the user about the validity of the data.
Post Save	The <b>Post Save</b> property is M code that is executed when the user saves changes. It is executed only if all data is valid, and after all data has been filed.
Record Selection Page	If you define a <b>Record Selection Page</b> property, the user can select another entry in the file, and, if LAYGO is allowed, add another entry into the file <i>without</i> exiting the form. The <b>Record Selection Page</b> should be a popup page, and the first field on that page is a pointer-type form-only field. The file specified in the <a href="#">Qualifiers</a> property of the form-only field should be the Primary file of the form. The <b>Record Selection Page</b> property should be set equal to the <a href="#">Page Number</a> of the <b>Record Selection Page</b> .  The user can open the <b>Record Selection Page</b> by pressing <PF1>L. After the user selects a record and closes the <b>Record Selection Page</b> , the data for the selected record is displayed.  The Screenman <b>Record Selection Page</b> can now be a full Screenman page using a computed Multiple pointer, so that the user can select an entry by scrolling up or down. This new feature lets forms contain embedded lookups.  You can set this up automatically, at the time you are creating a form,


Property	Description
	<p>answering <b>Yes</b> at the following prompt:</p> <p style="padding-left: 40px;">Do you want your form to begin with a display of all entries, for selection?</p> <p>The initial position can be set to be the user's last selection, rather than first, last, or new.</p>

## 4.4.2 Page Properties

[Table 80](#) lists the Page properties:

**Table 80: ScreenMan Forms—Page Properties**

Property	Description
Page Number	(Required) The <b>Page Number</b> uniquely identifies a page on a form. You can use this number to refer to the page in ScreenMan functions and utilities. ScreenMan does <i>not</i> display <b>Page Numbers</b> to the user.
Page Name	(Required) Like the <b>Page Number</b> , you can use the <b>Page Name</b> to refer to a page in ScreenMan functions and utilities. ScreenMan displays the <b>Page Name</b> to the user if, during an attempt to file data, ScreenMan finds required fields with null values. ScreenMan uses the <a href="#">Caption</a> of the field and the <b>Page Name</b> to inform the user of the location of the required field.
Page Coordinate Lower Right Coordinate	<p>(Required) The <b>Page Coordinate</b> property defines the location of the top left corner of the page on the screen. The format of a coordinate is: Row,Column</p> <p>Regular pages normally have a <b>Page Coordinate</b> of “1,1”. They do <i>not</i> have a <b>Lower Right Coordinate</b>.</p> <p>The <b>Page Coordinate</b> of “popup” pages defines the position of the top left corner of the border of the “popup” page. “Popup” pages <i>must</i> have a <b>Lower Right Coordinate</b>, which defines the position of the bottom right corner of the border of the “popup” page.</p> <p>All blocks on the page are positioned relative to the page on which they are defined. If a page is moved (i.e., if the <b>Page Coordinate</b> is changed) all blocks and all fields on that page move with it.</p> <p>The Form Editor described below greatly simplifies the process of assigning coordinates to “popup” pages. It allows you to drag and drop an entire “popup” page and to drag and drop the lower right corner to resize the “popup” page. It therefore eliminates the need for you to manually enter <b>Page Coordinate</b> values.</p>
Header Block	<p>A page can have one <b>Header Block</b> that contains uneditable information. ScreenMan always positions the <b>Header Block</b> at coordinate “1,1” relative to the page.</p> <p>There is no need to place <b>Header Blocks</b> on a page. Display blocks with a coordinate of “1,1” provide the same functionality as <b>Header Blocks</b>.</p>
Is This a “Pop-Up” Page?	If this page is a “popup” page, rather than a regular page, set this property to <b>YES</b> .
Next Page	The Next Page and Previous Page properties are set to Page Numbers. The user can go to the next and previous pages by pressing

Property	Description
Previous Page	<p>&lt;PF1&gt;&lt;ARROW DOWN&gt; and &lt;PF1&gt;&lt;ARROW UP&gt;, respectively. The user can also ^-jump to fields on other pages that are linked to the current page via the next and previous page links.</p> <p> <b>REF:</b> For more information about using these properties to link pages, see the <a href="#">“Linking Pages of a Form”</a> section.</p> <p>ScreenMan also uses the <b>Next Page</b> property during filing. Starting with the first page displayed to the user, ScreenMan:</p> <ol style="list-style-type: none"> <li>1. Follows the <b>Next Page</b> links.</li> <li>2. Loads those pages <i>not</i> already loaded.</li> <li>3. Checks that all required fields on those pages have values.</li> <li>4. If any of the required fields have null values, no filing occurs; otherwise, ScreenMan files the data along with any defaults.</li> </ol>
Parent Field	<p>This property can be used to link a subpage to a field on the parent page. <b>Parent Field</b> has the following format:</p> <pre>Field id,Block id,Page id</pre> <p>Where:</p> <ul style="list-style-type: none"> <li>• Field id = Field Order number; or Caption of the field; or Unique Name of the field</li> <li>• Block id = Block Order number; or Block Name</li> <li>• Page id = Page Number; or Page Name</li> </ul> <p>For example:</p> <pre>ZZFIELD 1,ZZBLOCK 1,ZZPAGE 1</pre> <p>Identifies the field with <a href="#">Caption</a> or <a href="#">Unique Name</a> “ZZFIELD 1,” on the block named “ZZBLOCK 1,” on the page named “ZZPAGE 1”.</p>
Pre Action Post Action	<p>ScreenMan executes the M code in the <b>Pre Action</b> property when the user reaches the page.</p> <p>ScreenMan executes the M code in the <b>Post Action</b> property when the user leaves the page.</p>

### 4.4.3 Block Properties


Block properties are stored in two locations:



- [Block Properties Stored in the FORM File](#)
- [Block Properties Stored in the BLOCK File](#)

#### 4.4.3.1 Block Properties Stored in the FORM File

[Table 81](#) lists the Block properties stored in the FORM (#.403) file. Since these properties are stored in the FORM (#.403) file, they apply only as it is used on a particular form.

**Table 81: ScreenMan Forms—Block Properties: FORM File**

Property	Description
Block Name	(Required) This is the <b>.01</b> field of the BLOCK Multiple of the PAGE Multiple of the FORM (#.403) file. This field is a pointer to the BLOCK (#.404) file.
Block Order	(Required) The <b>Block Order</b> determines the order in which users traverse fields on a page when they press <PF1><PF4> to go to the next block, or press the <b>Enter</b> key to move from the last field on one block to the first field on the next. When the user first reaches a page, ScreenMan places the user on the block with the lowest <b>Block Order</b> number.
Type of Block	<p>(Required) The <b>Type of Block</b> property can be either:</p> <ul style="list-style-type: none"> <li>• <b>DISPLAY</b>—DISPLAY blocks allow fields to be displayed but <i>not</i> changed by the user. Fields in a DISPLAY block are read-only.</li> <li>• <b>EDIT</b>—EDIT blocks allow fields to be changed by the user. Adding an EDIT block to a form enables the editing of any data dictionary fields placed on the EDIT-type block.</li> </ul> <p>When you first add a block to a form, you enter the properties for the block, including the type of block it is. You can also edit the properties of the block later.</p> <p> <b>REF:</b> For more information, see the <i>ScreenMan Tutorial for Developers Manual</i>, particularly Lessons 1-2 (DISPLAY blocks) and 1-7 (EDIT blocks). This manual is available on the VDL at: <a href="http://www4.va.gov/vdl/application.asp?appid=5">http://www4.va.gov/vdl/application.asp?appid=5</a></p>
Block Coordinate	<p>(Required) This property defines the location of the block. The format of a coordinate is:</p> <p style="padding-left: 40px;">Row,Column</p> <p>A <b>Block Coordinate</b> is defined relative to the page on which the block is defined. A Block Coordinate of “1,1”, for example, corresponds to the top left corner of the page. If a page is moved to a new position (i.e., if it is given a new coordinate), all blocks on the page move with it.</p>
Pointer Link	This property is used if the fields displayed in this block are reached through a relational jump from the primary file of the form. The <b>Pointer Link</b> is a relational expression that describes this jump.

Property	Description
	 <b>REF:</b> For more information, see the “Relational Navigation” section in the <i>VA FileMan Advanced User Manual</i> .
Pre Action Post Action	<p>The <b>Pre Action</b> property is M code that is executed whenever the user reaches this block.</p> <p>The <b>Post Action</b> property is M code that is executed whenever the user navigates away from this block.</p> <p>Since these two properties are stored in the FORM (#.403) file, they apply to the block only as it is used on this form.</p>
<a href="#">Replication</a> <a href="#">Index</a> <a href="#">Initial Position</a> <a href="#">Disallow LAYGO</a> <a href="#">Field for Selection</a>	<p>These properties pertain only to repeating blocks.</p>  <b>REF:</b> For more information about these properties, see the “ <a href="#">Displaying Multiples in Repeating Blocks</a> ” section.

#### 4.4.3.2 Block Properties Stored in the BLOCK File

[Table 82](#) lists the Block properties stored in the BLOCK (#.404) file. Since these properties are stored in the BLOCK (#.404) file, they are part of the definition of the block itself. These properties apply to the block wherever it is used.

**Table 82: ScreenMan Forms—Block Properties: BLOCK File**


Property	Description
Name	(Required) This is the <b>.01</b> field of the BLOCK(#.404) file . The block <b>Name</b> should be namespaced.
DD Number	This is the data dictionary (DD) number of the file or subfile that contains the fields that are placed on this block. A block can contain fields from only one file or subfile.
Disable Navigation	<p>If you set this property to <b>YES</b>, navigation within the block is disabled:</p> <ul style="list-style-type: none"> <li>Users <i>cannot</i> ^-jump to other fields.</li> <li>Users <i>cannot</i> ^-jump to the command line.</li> <li>The &lt;ARROW UP&gt;, &lt;ARROW DOWN&gt;, Tab, and PF4 keys traverse the fields in the same order when pressing the <b>Enter</b> key (i.e., in the order established by the <a href="#">Field Order</a> property of the fields).</li> <li>Users <i>cannot</i> use the &lt;PF1&gt;S, &lt;PF1&gt;E, &lt;PF1&gt;Q, and &lt;PF1&gt;C key sequences.</li> </ul> <p>If you set this property to <b>OUTOK</b>, navigation within the block is disabled, but the user can:</p> <ul style="list-style-type: none"> <li>^-jump to the command line.</li> <li>Use the &lt;PF1&gt;S, &lt;PF1&gt;E, &lt;PF1&gt;Q, and &lt;PF1&gt;C key sequences.</li> </ul>
Pre Action	The <b>Pre Action</b> property is M code that is executed whenever the user

Property	Description
Post Action	reaches this block. The <b>Post Action</b> property is M code that is executed whenever the user navigates away from this block. Since these two properties are stored in the BLOCK (#.404) file, they apply to the block as it is used on any page of any form.





#### 4.4.4 Field Properties

[Table 83](#) lists the Field properties:



**Table 83: ScreenMan Forms—Field Properties**

Property	Description
Field Type	(Required) Four different types of fields can be defined on a block: <ul style="list-style-type: none"> <li>• <b>Caption only</b>—Used to display text on the screen. They have no data portion associated with them.</li> <li>• <b>Data Dictionary</b>—Correspond to fields in a file. They have the following: <ul style="list-style-type: none"> <li>○ A data portion, which is the value of the field.</li> <li>○ An optional caption portion, which serves to identify the data on the screen for the user.</li> </ul> </li> <li>• <b>Form-only</b>—Defined only on the form and are <i>not</i> tied to a field in a VA FileMan file. <p> <b>REF:</b> For more information about this field type, see the <a href="#">“Form-Only Fields”</a> section.</p> </li> <li>• <b>Computed</b>—Like <b>Form-only</b> fields, <b>Computed</b> fields are defined only on the form. You <i>cannot</i> place <b>Computed</b> fields from VA FileMan files on a form. The computed expression is defined on the form and can be based on other fields on the form. Users <i>cannot</i> navigate to <b>Computed</b> fields.</li> </ul>
Field Order	(Required) The <b>Field Order</b> number determines the order in which users traverse the fields in the block as they press the <b>Enter</b> key. <b>Field Order</b> is the <b>.01</b> field of the Field Multiple of the BLOCK (#.404) file.
Field	(Required for <b>Data Dictionary</b> -type fields.) The <b>Field</b> property applies only to <a href="#">Data Dictionary</a> -type fields. It identifies a field in a VA FileMan file or subfile. The <a href="#">DD Number</a> of the block identifies the file or subfile that contains the field.
Unique Name	You can optionally give fields on a block a <b>Unique Name</b> . A <b>Unique Name</b> is <i>never</i> seen by the user. They can be used to identify fields in some of the ScreenMan utilities, such as <a href="#">PUT^DDSVAL</a> and <a href="#">\$\$GET^DDSVAL</a> , and in the computed expressions of computed fields. No two fields on a block can have the same <b>Unique Name</b> .
Caption Executable Caption Suppress Colon After	A <b>Caption</b> is uneditable text that appears on the screen. Captions of <a href="#">Data Dictionary</a> , <a href="#">Form-only</a> , and <a href="#">Computed</a> fields serve to identify for the user the data portion of the fields. Captions of these types of fields are <i>automatically</i> followed by a colon, unless the <b>Suppress Colon After Caption</b> property is set to <b>YES</b> . Captions of <a href="#">Caption-only</a> fields have no

Property	Description								
Caption	<p>associated data element and are <i>not automatically</i> followed by a colon. If you want the text of a caption to be determined whenever the page is painted, you can enter M code as an <b>Executable Caption</b>. The code should set the local variable <b>Y</b> equal to the text you want displayed. A field with an <b>Executable Caption</b> <i>must</i> have <b>!M</b> as a <b>Caption</b>.</p>								
<p>Default</p> <p>Executable Default</p>	<p>You can assign a Default to a <a href="#">Data Dictionary</a> or <a href="#">Form-only</a> type field on a form. ScreenMan presents the <b>Default</b> value to the user if the value of the field is null when the page on which the field is located is first displayed. Since ScreenMan validates the <b>Default</b>, it <i>must</i> be valid, unambiguous, and in external form; otherwise, it is <i>not</i> used.</p> <p>If the field is a Multiple field, you can assign one of the defaults listed in <a href="#">Table 84</a>:</p> <p style="text-align: center;"><b>Table 84: ScreenMan Forms—Valid Default Values for Multiple Fields</b></p> <table border="1" data-bbox="594 741 1336 947"> <thead> <tr> <th data-bbox="594 741 850 804">Default</th> <th data-bbox="850 741 1336 804">Subrecord Displayed</th> </tr> </thead> <tbody> <tr> <td data-bbox="594 804 850 852">FIRST</td> <td data-bbox="850 804 1336 852">The subrecord with the lowest IEN.</td> </tr> <tr> <td data-bbox="594 852 850 900">LAST</td> <td data-bbox="850 852 1336 900">The subrecord with the highest IEN.</td> </tr> <tr> <td data-bbox="594 900 850 947">Subrecord number</td> <td data-bbox="850 900 1336 947">The subrecord with the specified IEN.</td> </tr> </tbody> </table> <p>Here, the characters “<b>FIRST</b>” and “<b>LAST</b>” are keywords that ScreenMan interprets as the subrecords with the lowest and highest IENs, respectively.</p> <p>If the value of the default should be determined at the time the page is first presented to the user, you can enter M code as an <b>Executable Default</b>. The code should set the local variable <b>Y</b> equal to a valid, unambiguous value in external form. If the default in <b>Y</b> is invalid, it is <i>not</i> used. A field with an <b>Executable Default</b> <i>must</i> have <b>!M</b> as a <b>Default</b>.</p>	Default	Subrecord Displayed	FIRST	The subrecord with the lowest IEN.	LAST	The subrecord with the highest IEN.	Subrecord number	The subrecord with the specified IEN.
Default	Subrecord Displayed								
FIRST	The subrecord with the lowest IEN.								
LAST	The subrecord with the highest IEN.								
Subrecord number	The subrecord with the specified IEN.								
Data Length	<p>(Required for all field types, except <a href="#">Caption-only</a>.) <b>Data Length</b> defines the length of the edit window for the data portion of fields. Ideally, the <b>Data Length</b> should equal the maximum length of the external form of the data (i.e., the form displayed to the user).</p> <p>The <b>Data Length</b> of a WORD-PROCESSING field need only be <b>1</b>, since the contents of the field are <i>not</i> displayed in the edit window. A <b>Data Length</b> of <b>1</b> gives the cursor a place to rest when the user navigates to the field. When the user presses the <b>Enter</b> key at the field, control is passed to the user’s Preferred Editor, where the text can be displayed and, if allowed, edited.</p> <p>If you define a <b>Data Length</b> smaller than a field’s maximum size, ScreenMan still provides two ways for the user to see the entire value of the field:</p> <ul style="list-style-type: none"> <li>• Since the edit window is a “scrolling window,” text outside the confines of the edit window can scroll in, as text in the window scrolls out.</li> <li>• When the cursor is within an edit window, the user can press <b>&lt;PF1&gt; Z</b> to invoke the “zoom editor.” An area opens in the Command Area where up to <b>245</b> characters can be seen and edited at once.</li> </ul>								

Property	Description
	<p> <b>NOTE:</b> You <i>cannot</i> define an edit window that wraps around to a second line. In addition, the edit window <i>must not</i> extend into the rightmost column of the screen. This space <i>must</i> be left blank, so that the cursor has a place to rest beyond the last character of the data value. You <i>must</i>, therefore, never define a <b>Data Length</b> that causes the edit window to extend beyond the next to last column of the screen (i.e., column <b>79</b> on an <b>80</b>-column display).</p>
<p>Caption Data Coordinates</p>	<p>(Required if a field has a caption or data portion.) <b>Caption</b> and <b>Data Coordinates</b> define the location of fields on the screen and are relative to the coordinate of the block on which they are defined. The format of coordinate is: Row,Column The coordinate “<b>1,1</b>” for example, corresponds to the block’s top left corner (i.e., the first column on the first row of the block). The Form Editor simplifies the process of assigning coordinates to captions and data. It allows you to drag and drop fields on the screen, and thus, eliminates the need to explicitly assign values to the coordinate properties.</p> <p> <b>REF:</b> The Form Editor is described in detail in the “<a href="#">ScreenMan Form Editor</a>” section.</p>
<p>Right Justify</p>	<p>Set the Right Justify property to <b>YES</b> to display the data for the field to be right-justified.</p>
<p>Required</p>	<p>You can make any <i>non</i>-Multiple field on a form required. Making a field required on a form does <i>not</i> affect the definition of the field in the data dictionary. You need <i>not</i> make a field required that is already required by its data definition. The captions of required fields are underlined for easy identification.</p> <p> <b>REF:</b> For more information on how ScreenMan checks <b>Required</b> fields before filing, see the “<a href="#">Data Filing (When Is It Performed?)</a>” section.</p> <p>Before filing, ScreenMan checks that:</p> <ul style="list-style-type: none"> <li>• <b>Required</b> fields on all pages that can be accessed via the <a href="#">Next Page</a> and <a href="#">Previous Page</a> links have values, even if you have <i>not</i> accessed those pages during the editing session.</li> <li>• If you have accessed any subpages, required fields in those subpages <i>must</i> also have values.</li> </ul> <p>If any required field is empty, the user <i>cannot</i> file any data changes. When they attempt to file, ScreenMan displays a list of those fields that require values.</p> <p> <b>NOTE:</b> “Popup” pages <i>not</i> accessed during the editing session are <i>not</i> checked for <b>Required</b> fields.</p> <p>You can change the <b>Required</b> property on-the-fly while a form is running by making a call to <a href="#">REQ^DDSUTL</a>.</p>
<p>Display Group</p>	<p><b>Display Group</b> helps users resolve ambiguity when they attempt to ^-</p>



Property	Description
	<p>jump to a field that has a caption that is <i>not</i> unique. If more than one field has the same caption, when users try to ^-jump to a field with that caption, they are presented with a list of fields from which to choose. The text in the <b>Display Group</b> property is displayed in parentheses after the caption to help the user identify the correct field.</p> <p>For example, if two fields have the caption “NAME:”, but one of those fields has a <b>Display Group</b> “Next of Kin,” when users enter ^NAME, they are asked to choose between “NAME” and “NAME (Next of Kin)”.</p>
<p>Disable Editing Disallow LAYGO</p>	<p>If you set the <b>Disable Editing</b> property to <b>YES</b>, users <i>cannot</i> navigate to the field, unless the field is a WORD-PROCESSING field. If the field is defined as uneditable in the data dictionary (DD), users <i>cannot</i> navigate to it—even if the field’s value is null.</p> <p> <b>REF:</b> For information about uneditable WORD-PROCESSING fields, see the “Word-processing Fields” section in the <i>VA FileMan User Manual</i>.</p> <p>If you set the <b>Disable Editing</b> property to “<b>REACHABLE</b>,” users can navigate to the field, but they <i>cannot</i> change the value. For example, you might want to make an uneditable field reachable if you want to attach <a href="#">Branching Logic</a> to that field, to take the user to another page when they press the <b>Enter</b> key. You might also want to make an uneditable field reachable if the data value <i>cannot</i> fit in an edit window. Then the user can navigate to the field and see the entire contents of the field, either by scrolling the data in the edit window or by invoking the “zoom editor.”</p> <p>You can change the <b>Disable Editing</b> property on-the-fly while a form is running by making a call to <a href="#">UNED^DDSUTL</a>.</p> <p> <b>NOTE:</b> Fields on display blocks are always uneditable. On display blocks, users can navigate only to Multiple and WORD-PROCESSING fields.</p> <p>Disabling editing for Multiple fields has no meaning. However, you can prevent users from adding new entries into a Multiple by setting the <b>Disallow LAYGO</b> property to <b>YES</b>. Multiple fields on display blocks automatically prohibit LAYGO.</p>
<p>Data Validation</p>	<p>ScreenMan uses the definition of a field to automatically validate values input by the user. You can use the <b>Data Validation</b> property to validate the value even further. <b>Data Validation</b> is M code that is executed after the user enters a new value for a field and after the automatic validation that ScreenMan normally performs. If the code sets the <b>DDSERROR</b> variable, ScreenMan rejects the value. You might also want to ring the bell and make a call to <a href="#">HLP^DDSUTL</a> to display a message to the user that indicates the reason the value was rejected.</p>
<p>Subpage Link</p>	<p>A subpage can be linked to a parent page by the <b>Subpage Link</b> property. The <b>Subpage Link</b> <i>must</i> be equal to the <a href="#">Page Number</a> of the subpage.</p>

Property	Description																		
Branching Logic Pre Action Post Action Post Action on Change	<p>These properties contain M code that is executed at the times listed in <a href="#">Table 85</a>:</p> <p><b>Table 85: ScreenMan Forms—Descriptions of Field-Level Pre and Post Actions</b></p> <table border="1" data-bbox="594 411 1365 787"> <thead> <tr> <th>Property</th> <th>Executed</th> </tr> </thead> <tbody> <tr> <td>Branching Logic</td> <td>When the user presses the <b>Enter</b> at the field.</td> </tr> <tr> <td>Pre Action</td> <td>Right before the user lands on the field.</td> </tr> <tr> <td>Post Action</td> <td>When the user leaves the field.</td> </tr> <tr> <td>Post Action on Change</td> <td>When the user leaves the field, and only if the user changed the value of the field.</td> </tr> </tbody> </table> <p>The code in the <b>Branching Logic</b>, <b>Pre Action</b>, <b>Post Action</b>, <b>Post Action on Change</b>, and <b>Data Validation</b> at the field level can rely on the variables listed in <a href="#">Table 86</a>:</p> <p><b>Table 86: ScreenMan Forms—Variables Available in Field-Level Pre and Post Actions</b></p> <table border="1" data-bbox="594 1010 1365 1220"> <thead> <tr> <th>Local Variable</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><b>X</b></td> <td>The current internal value of the field.</td> </tr> <tr> <td><b>DDSEXT</b></td> <td>The current external value of the field.</td> </tr> <tr> <td><b>DDSOLD</b></td> <td>The previous internal value of the field.</td> </tr> </tbody> </table> <p>The <b>Post Action</b> and <b>Post Action on Change</b> are <i>not</i> executed when the user:</p> <ul style="list-style-type: none"> <li>• Times out at a field.</li> <li>• Enters a caret (^) to go to the Command Area.</li> <li>• Enters a ^-jumps to another field.</li> </ul>	Property	Executed	Branching Logic	When the user presses the <b>Enter</b> at the field.	Pre Action	Right before the user lands on the field.	Post Action	When the user leaves the field.	Post Action on Change	When the user leaves the field, and only if the user changed the value of the field.	Local Variable	Description	<b>X</b>	The current internal value of the field.	<b>DDSEXT</b>	The current external value of the field.	<b>DDSOLD</b>	The previous internal value of the field.
Property	Executed																		
Branching Logic	When the user presses the <b>Enter</b> at the field.																		
Pre Action	Right before the user lands on the field.																		
Post Action	When the user leaves the field.																		
Post Action on Change	When the user leaves the field, and only if the user changed the value of the field.																		
Local Variable	Description																		
<b>X</b>	The current internal value of the field.																		
<b>DDSEXT</b>	The current external value of the field.																		
<b>DDSOLD</b>	The previous internal value of the field.																		

## 4.5 ScreenMan Menu Options

The ScreenMan menu [DDS SCREEN MENU], which is locked with the XUSCREENMAN security key, is found on a submenu of the Other Options menu [DIOTHER], as shown in [Figure 229](#):

**Figure 229: ScreenMan Forms—ScreenMan Menu Options**

```
Select VA FileMan Option: OTHER OPTIONS
Select Other Options Option: SCREENMAN
Select ScreenMan Option: ?
  Answer with SCREENMAN OPTION NUMBER, or NAME
Choose from:
  1          EDIT/CREATE A FORM
  2          RUN A FORM
  3          DELETE A FORM
  4          PURGE UNUSED BLOCKS

Select SCREENMAN OPTION:
```

The following sections describe these four ScreenMan options.

### 4.5.1 Edit/Create a Form

Use the Edit/Create a Form option [DDS EDIT/CREATE A FORM] on the ScreenMan menu [DDS SCREEN MENU] to invoke the Form Editor, the screen-oriented utility for editing and building ScreenMan forms.



**REF:** The Form Editor is described in detail in the “[ScreenMan Form Editor](#)” section.

### 4.5.2 Run a Form

Instead of setting up input variables and making a call to [^DDS](#), you can use the Run A Form option [DDS RUN A FORM] on the ScreenMan menu [DDS SCREEN MENU] to run a form, as shown in [Figure 230](#):

**Figure 230: ScreenMan Forms—Run a Form Option**

```
Select SCREENMAN OPTION: RUN A FORM

MODIFY SCREEN TEMPLATE FOR WHAT FILE: ZZEZ SCREENDOC

Select FORM: ZZEZ DOC <Enter>  ZZEZ DOC

Enter number of first page: 1// <Enter>

Select ZZEZ SCREENDOC NAME: FMUSER,ONE <Enter>  M.          FM
```

You are asked to select a

- File
- Form
- Initial page
- Record

The Run A Form option [DDS RUN A FORM] *cannot* run a form used to edit a subfile directly.

### 4.5.3 Delete a Form

You can use the Delete A Form option [DDS DELETE A FORM] on the ScreenMan menu [DDS SCREEN MENU] to delete a form from the FORM (#.403) file, and any or all of the blocks used on that form from the BLOCK (#.404) file.

**Figure 231: ScreenMan Forms—Delete a Form Option**

```
Select SCREENMAN OPTION: DELETE A FORM
MODIFY SCREEN TEMPLATE FOR WHAT FILE: ZZEZ SCREENDOC
Select FORM to delete: ZZTEST DOC <Enter>  ZZTEST DOC
                        #55          02/16/91  User #14   File #16500
```

Once you have selected a file and form to delete, a short report is printed that lists all blocks used on the form, as illustrated in [Figure 232](#):

**Figure 232: ScreenMan Forms—Delete a Form Option: Report of All Blocks Used on the Form**

```
BLOCKS USED ON FORM "ZZTEST DOC" (IEN #55)
Internal
Entry Number   Block Name                Used on
                Other Forms?   Deletable?
-----
178            ZZTEST DOC HDR1         NO           YES
179            ZZTEST DOC1             NO           YES
180            ZZTEST DOC2             NO           YES
181            ZZTEST DOC3             NO           YES
182            ZZTEST DOC HDR3         NO           YES
```

The first column lists the internal entry numbers of the blocks used on the form, and the second column lists the names of the blocks. The last two columns indicate whether the blocks are used on other forms and whether you can delete those blocks from the BLOCK (#.404) file. Only those blocks that are *not* used on other forms can be deleted.

You are then asked whether you want to delete the blocks used on the form from the BLOCK (#.404) file, as shown in [Figure 233](#):

**Figure 233: ScreenMan Forms—Delete a Form Option: Delete Blocks**

```
Delete all deletable blocks used on form ZZTEST DOC
from the BLOCK file (Y/N)? YES// ?

Enter 'Y' to delete blocks used on form
ZZTEST DOC from the BLOCK file.
(Only blocks not used on other forms can be deleted.)

Enter 'N' to delete the form but not the blocks.

Delete all deletable blocks used on form ZZTEST DOC
from the BLOCK file (Y/N)? YES// <Enter>
```

If you answer **NO**, the form is deleted from the FORM (#.403) file, but none of the blocks used on the form are deleted. If you choose *not* to delete a block, and that block is *not* used on any form, the only way to delete the block is to run the [Purge Unused Blocks](#) option [DDS PURGE UNUSED BLOCKS].

If you answer **YES**, you are asked whether you want to delete those blocks *without* confirmation.

**Figure 234: ScreenMan Forms—Delete a Form Option: Delete Blocks with or without Confirmation**

```
Delete blocks without prompting (Y/N)? NO// ?  
  
Enter 'Y' to delete blocks from the BLOCK file  
without confirmation.  
  
Enter 'N' to confirm each delete.  
  
Delete blocks without prompting (Y/N)? NO//
```

If you answer **YES**, all blocks used on the form that are *not* used on any form are deleted.

If you answer **NO**, you are prompted before any block is deleted. This gives you a chance to delete only specific blocks.

**Figure 235: ScreenMan Forms—Delete a Form Option: Deleting Blocks without Confirmation**

```
Continue (Y/N)? NO// YES  
  
Deleting form ZZTEST DOC (IEN #55) ...  
  
ZZTEST DOC HDR1          Delete (Y/N)? NO// YES  
ZZTEST DOC1              Delete (Y/N)? NO// YES  
ZZTEST DOC2              Delete (Y/N)? NO// YES  
ZZTEST DOC3              Delete (Y/N)? NO// YES  
ZZTEST DOC HDR3          Delete (Y/N)? NO// YES  
  
DONE!
```

## 4.5.4 Purge Unused Blocks

You can use the Purge Unused Blocks option [DDS PURGE UNUSED BLOCKS] on the ScreenMan menu [DDS SCREEN MENU] to delete any or all of the unused blocks from the BLOCK (#.404) file that are associated with a specific file.

**Figure 236: ScreenMan Forms—Purge Unused Blocks Option**

```
Select OPTION: OTHER OPTIONS  
Select OTHER OPTION: SCREENMAN  
Select SCREENMAN OPTION: PURGE UNUSED BLOCKS  
  
PURGE UNUSED BLOCKS FROM WHAT FILE: ZZEZ SCREENDOC
```

Once you have selected a file, a short report is printed that lists the blocks that are *not* used on any forms:

**Figure 237: ScreenMan Forms—Purge Unused Blocks Option: Report of Unused Blocks on any Forms**

```
UNUSED BLOCKS ASSOCIATED WITH FILE ZZEZ SCREENDOC (#16500)

Internal
Entry Number   Block Name
-----
72             ZZZEE EDIT3
178            ZZTEST DOC1
179            ZZTEST DOC2
180            ZZTEST DOC3
181            ZZTEST DOC HDR3
```

You are then asked whether to delete the blocks without confirmation:

**Figure 238: ScreenMan Forms—Purge Unused Blocks Option: Delete Blocks with or without Confirmation**

```
Delete all unused blocks without prompting (Y/N)? NO// <Enter>
```

If you answer **YES**, all unused block are deleted.

If you answer **NO**, you are prompted before any block is deleted. This gives you a chance to delete only specific blocks.

**Figure 239: ScreenMan Forms—Purge Unused Blocks Option: Delete Blocks without Confirmation**

```
Continue (Y/N)? NO// YES

ZZZEE EDIT3           Delete (Y/N)? NO// YES
ZZTEST DOC1          Delete (Y/N)? NO// YES
ZZTEST DOC2          Delete (Y/N)? NO// YES
ZZTEST DOC3          Delete (Y/N)? NO// YES
ZZTEST DOC HDR3      Delete (Y/N)? NO// YES

DONE!
```

## 4.6 Callable Routines

ScreenMan provides a number of callable routines. Many of these routines can be called from the various form properties that execute M code. These callable routines are described in the [“ScreenMan API”](#) section.

## 4.7 Programmer Mode Utilities

### 4.7.1 ^DDGF: Invoke the Form Editor from Programmer Mode

Use the ^DDGF API to invoke the Form Editor from programmer mode.



**NOTE:** You can also reach the Form Editor through the VA FileMan menu [DIUSER] options. On the VA FileMan menu [DIUSER], select Other Options [DIOTHER], ScreenMan [DDS SCREEN MENU], and Edit/Create a Form [DDS EDIT/CREATE A FORM].



REF: The Form Editor is described in detail in the “[ScreenMan Form Editor](#)” section.

## 4.7.2 CLONE^DDS: Make a Copy of a Form

Use the CLONE^DDS API to make a copy of a form. All blocks used on the form are copied and a new form that uses the new blocks is created.

In [Figure 240](#), CLONE^DDS is used to make a copy of the XUEDIT CHARACTERISTICS form of the NEW PERSON (#200) file:

**Figure 240: ScreenMan Forms—CLONE^DDS: Sample Dialogue to Copy a Form**

```
>D CLONE^DDS

CLONE FORM FROM WHAT FILE: NEW PERSON

Select FORM to clone: ??

Choose from:
  XUEDIT CHARACTERISTICS      #1      12/06/90      File #200
  XUEXISTING USER             #2      12/12/90      File #200

Select FORM to clone: XUEDIT CHARACTERISTICS <Enter> XUEDIT CHARACTERISTICS
                                     #1      12/06/90      File #200
```

Once you have selected a form to clone, a report that lists the blocks used on the form is printed, as shown in [Figure 241](#):

**Figure 241: ScreenMan Forms—CLONE^DDS: Report Showing Blocks Used on a Form**

```
BLOCKS USED ON FORM "XUEDIT CHARACTERISTICS" (IEN #1)

Internal
Entry Number  Block Name
-----
1             XUEDIT CHARACTERISTICS HDR
2             XUEDIT CHARACTERISTICS

Enter RETURN to continue or '^' to exit: <Enter>
```

You *must* assign names to the new form and blocks you are creating. If the original form and blocks are namespaced (i.e., start with the same set of characters), you can choose to give the new form and blocks the same name, but with the namespace replaced with another set of characters. Then, when you are asked to enter new names, names that have the namespace replaced with the set of characters are displayed as defaults, as shown in [Figure 242](#):

**Figure 242: ScreenMan Forms—CLONE^DD: Assigning New Form and Block Names**

```
The new form and blocks must be given unique names.

Give the new form and blocks the same names as the original,
but a different namespace? YES// <Enter>

Original namespace: XU
New namespace: ZZ

Enter names for the new form and blocks.

Original form name: XUEDIT CHARACTERISTICS
New form name: ZZEDIT CHARACTERISTICS

Original block name: XUEDIT CHARACTERISTICS HDR
New block name: ZZEDIT CHARACTERISTICS HDR

Original block name: XUEDIT CHARACTERISTICS
New block name: ZZEDIT CHARACTERISTICS
```

After you have given names to the new form and blocks, you are ready to clone the form as shown in [Figure 243](#):

**Figure 243: ScreenMan Forms—CLONE^DDS: Cloning a Form**

```
Ready to clone form? YES
Creating new blocks ...

  ZZEDIT CHARACTERISTICS HDR      #71
  ZZEDIT CHARACTERISTICS          #72

Creating new form ...
  ZZEDIT CHARACTERISTICS          #36

Repointing to new blocks ...
Reindexing new form ...

DONE!
>
```



**NOTE:** Be sure to check the properties of the cloned form and blocks for namespaced variables, block references, etc., that need to be modified manually.



### 4.7.3 PRINT^DDS: Print a Form

Use the PRINT^DDS API to print a form. PRINT^DDS prints the properties of the form and the properties of all the blocks used on that form, as shown in [Figure 244](#):

Figure 244: ScreenMan Forms—PRINT^DDS: Printing a Form

```
>D PRINT^DDS

Select FORM: ZZSAMPLE <Enter> (Nov 16, 1994) User #3 File 16201

Start each page of the form on a new page? Yes// NO
DEVICE: HOME// ;;9999 <Enter> DECSERVER

FORM LISTING - ZZSAMPLE (#38)
FILE: ZZTEST (#16201) NOV 16, 1994 13:29 PAGE 1
-----
PRIMARY FILE: 16201 READ ACCESS: @
DATE CREATED: NOV 16, 1994@08:24 WRITE ACCESS: @
DATE LAST USED: NOV 16, 1994@08:25 CREATOR: 3

Page Page
Number Properties
-----
1 Page 1

PAGE COORDINATE: 1,1

Block Block
Order Properties (Form File)
-----
1 ZZSAMPLE (#104)

TYPE OF BLOCK: EDIT
BLOCK COORDINATE: 1,1

Block Properties (Block File)
-----
DATA DICTIONARY NUMBER: 16201

Field Field
Order Properties
-----
1 FIELD TYPE: DATA DICTIONARY FIELD
CAPTION: NAME
FIELD: .01
CAPTION COORDINATE: 1,1
DATA COORDINATE: 1,7
DATA LENGTH: 30

2 FIELD TYPE: DATA DICTIONARY FIELD
CAPTION: SET
FIELD: 1
CAPTION COORDINATE: 2,2
DATA COORDINATE: 2,7
DATA LENGTH: 10
```

#### 4.7.4 RESET^DDS: Reset Terminal, Variables, and Remove Temp Data

If during a call to [^DDS](#) you get a hard error, you can **DO RESET^DDS** to:

- Reset the terminal characteristics.
- Unlock any locked records.
- Clean up some variables in the local symbol table.
- Remove the temporary data ScreenMan stores in **^TMP**.

Since RESET^DDS does *not* clean up all local variables, you should **DO P^DI** afterwards to clean up any variables that RESET^DDS missed.

You can also use RESET^DDS if you get a hard error while using the Form Editor.

## 5 ScreenMan Form Editor

### 5.1 Introduction

The ScreenMan Form Editor is a screen-oriented tool for creating and editing ScreenMan forms. It allows you to select and drag form elements and edit their properties through a ScreenMan interface. It can run on character-based terminals (e.g., DEC VT-100 and Qume QVT-102), if properly defined through the Device Handler.

As you use the Form Editor, it is helpful to display or have printouts of the data dictionaries of the files containing the fields you are placing on ScreenMan forms. You need to know such things as the data dictionary numbers of files and subfiles and the maximum length of the external form of data.



**REF:** See also:

- “[ScreenMan Forms](#)” section.
- “[ScreenMan API](#)” section, which describes the ScreenMan APIs you can use to load a form and to use from within a form.
- The *ScreenMan Tutorial for Developers Manual*, located on the VDL at: <http://www4.va.gov/vdl/application.asp?appid=5>.

### 5.2 Invoking the Form Editor

To invoke the Form Editor, perform the following steps from the VA FileMan menu [DIUSER]:

1. At the “Select VA FileMan Option:” prompt, enter the **Other Options** option [DIOTHER].
2. At the “Select Other Options Option:” prompt, enter the **ScreenMan** menu [DDS SCREEN MENU].



**NOTE:** The ScreenMan menu [DDS SCREEN MENU] is locked with the XUSCREENMAN security key.

3. At the “Select ScreenMan Option:” prompt enter the EDIT/CREATE A FORM option [DDS EDIT/CREATE A FORM], as shown in [Figure 245](#):

**Figure 245: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Invoking the Form Editor**

```
Select VA FileMan Option: OTHER OPTIONS
Select Other Options Option: SCREENMAN
Select ScreenMan Option: ?
  Answer with SCREENMAN OPTION NUMBER, or NAME
Choose from:
  1          EDIT/CREATE A FORM
  2          RUN A FORM
  3          DELETE A FORM
  4          PURGE UNUSED BLOCKS

Select SCREENMAN OPTION: EDIT/CREATE A FORM
```

4. You are asked to select a file:

**Figure 246: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Selecting a File**

```
EDIT/CREATE FORM FOR WHAT FILE:
```

5. And a form:

**Figure 247: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Selecting a Form**

```
Select FORM:
```

At the “Select FORM:” prompt, you can either:

- Select an existing form to edit.
- Create a new form by entering a new form name.

If you create a new form ([Figure 248](#)), the Form Editor *automatically* creates one page on that form. The new page is given a:

- Page Number of **1**.
- Page Name of “Page **1**”.
- Page Coordinate of “**1,1**”.

**Figure 248: ScreenMan Form Editor—EDIT/CREATE A FORM Option: Creating a New Form**

```
<Enter Form Fields here>

File: OPTION (#19)                                     R1,C1
Form: ZZTEST (#86)
Page: 1 (Page 1)

<PF1>Q=Quit <PF1>E=Exit <PF1>S=Save <PF1>V=Block Viewer <PF1>H=Help
```



**NOTE:** You can also use the programmer mode utility [^DDGF](#) to invoke the Form Editor.

## 5.3 Command Summary

This section describes the following Form Editor functionality:

- [Navigating on the Main Screen and Block Viewer Screen](#)
- [Quick Page Navigation](#)
- [Moving Screen Elements](#)
- [Adding, Selecting, and Editing](#)

### 5.3.1 Navigating on the Main Screen and Block Viewer Screen

**Table 87: ScreenMan Form Editor—Navigating: Cursor Navigation to the Main Screen and the Block Viewer Screen**

To Move the Cursor	Press
Up one line	<ARROWUP>
Down one line	<ARROWDOWN>
Right one column	<ARROWRIGHT>
Left one column	<ARROWLEFT>
One field to the right	<Tab>
One field to the left	Q
Five columns to the right	S
Five columns to the left	A
Top of screen	<PF1><ARROWUP>
Bottom of screen	<PF1><ARROWDOWN>
Right edge of screen	<PF1><ARROWRIGHT>
Left edge of screen	<PF1><ARROWLEFT>

**To switch between the Main screen and the Block Viewer screen:**

Press <PF1>V.

### 5.3.2 Quick Page Navigation

**Table 88: ScreenMan Form Editor—Navigating: Key Sequences for Quick Page Navigation**

To	Press
Go to the next page	<PF1><PF1><ARROWDOWN>
Go to the previous page	<PF1><PF1><ARROWUP>
Go into a subpage associated with a field	Select the field with <b>Spacebar</b> or <b>Enter</b> keys and press <PF1>D

**To select a screen element (field caption, field data, or block name):**

1. Position the cursor over the element.
2. Press **Spacebar** or **Enter**.
3. Press **Spacebar** or **Enter** again to deselect the element.

### To reorder all fields on a block:

1. Select the block on the Block Viewer Screen.
2. Press <PF1>O.

## 5.3.3 Moving Screen Elements

Table 89: ScreenMan Form Editor—Key Sequences to Move Screen Elements

To Drag a Selected Element	Press
Up one line	<ARROWUP>
Down one line	<ARROWDOWN>
Right one column	<ARROWRIGHT>
Left one column	<ARROWLEFT>
Five columns to the right	<Tab> or S
Five columns to the left	Q or A
Top of screen	<PF1><ARROWUP>
Bottom of screen	<PF1><ARROWDOWN>
Right edge of screen	<PF1><ARROWRIGHT>
Left edge of screen	<PF1><ARROWLEFT>

## 5.3.4 Adding, Selecting, and Editing

Table 90: ScreenMan Form Editor—Key Sequences to Add, Select, and Edit

To	Press
Select or create a new form	<PF1>M or <PF2>M
Select another page	<PF1>P
Add a new page	<PF2>P
Add a new block	<PF2>B
Add a new field	<PF2>F
Edit properties of current form	<PF4>M
Edit properties of current page	<PF4>P

### To invoke the ScreenMan form to edit field or block properties:

1. Select the field or block.
2. Press PF4.

### To edit the caption of a field on the Main Screen:

1. Position the cursor over the caption.
2. Press **PF3**.
3. Press the **Enter** key when finished editing.

### To edit the data length of a field on the Main Screen:

1. Position the cursor over the underline that represents the data.
2. Press **PF3**.
3. Press **<ARROWRIGHT>** and **<ARROWLEFT>** to change the length.
4. Press the **Enter** key when finished.

## 5.4 Form Editor's Main Screen

[Figure 249](#) is an example of the Form Editor's Main Screen.

The **top** portion of the Main Screen is the **Work Area**. Here you see field captions, as well as underscores representing data fields, for fields that are defined on the blocks of the current page. Each of these items is called a **screen element**. This area of the screen is the one that you control when you display information to the user on a form.

**Figure 249: ScreenMan Form Editor—Main Screen**

```
NAME : _____
STREET ADDRESS : _____
CITY : _____
STATE : ____
ZIP CODE : _____

-----
File: ZZFILE NAME (# nnnn)                               Rn, Cn
Form: ZZFORM NAME
Page: n (ZZName of Page)

<PF1>Q=Quit   <PF1>E=Exit   <PF1>S=Save   <PF1>V=Block Viewer   <PF1>H=Help
```

The **bottom** portion of the screen contains status information, such as:

- Name and number of the file to which the form is attached.
- Name of the form.
- Number and name of the page you are currently editing.
- “**Rn,Cn**” at the lower right of the screen indicates the current row and column position of the cursor.

When a user runs a form, this portion of the screen is occupied by ScreenMan's command area.

## 5.4.1 Exiting, Quitting, Saving, and Obtaining Help

You can exit from the Form Editor's Main Screen in one of two ways:

- Press <PF1>E to exit and save any changes you made to the following:
  - Field captions
  - Data lengths of fields
  - Block names
  - Page, block, and field coordinates.

These are the properties that are visible on the Form Editor screens.

- Press <PF1>Q to quit and discard the changes you made to those properties.

You can also save changes without leaving the Form Editor by pressing <PF1>S.

Pressing <PF1>H accesses the Form Editor's online help screens.

**Table 91: ScreenMan Form Editor—General Key Sequences to: Exit, Quit, Save, and Obtain Help**

To	Press
Exit and save changes	<PF1>E
Quit without saving changes	<PF1>Q
Save without exiting	<PF1>S
Bring up help screens	<PF1>H
Move to Block Viewer screen	<PF1>V

## 5.5 Block Viewer Screen

To view the blocks on the current page, press <PF1>V to go to the Block Viewer Screen. The Block Viewer Screen displays the names of the blocks defined on the current page. For example, if the current page contains blocks called ZZBLOCK NAME 1 and ZZBLOCK NAME 2, the Block Viewer Screen looks like [Figure 250](#):

**Figure 250: ScreenMan Form Editor—Block Viewer Screen**

ZZBLOCK NAME 1		
ZZBLOCK NAME 2		
File: ZZFILE NAME (# nnnn)	BLOCK VIEWER	R1,C1
Form: ZZFORM NAME		
Page: n (ZZPage Name)		
<PF1>V=Main Screen    <PF1>H=Help		

Like the captions and data fields displayed on the [Main Screen](#), the block names on the Block Viewer Screen are screen elements.





**NOTE:** The words “**BLOCK VIEWER**” appear in the bottom portion of the Block Viewer Screen.

**To return to the Main Screen:**

Press <PF1>V.

## 5.6 Navigating on the Form Editor Screens

To move the cursor on the [Main Screen](#) and the [Block Viewer Screen](#), you can use the key sequences listed in [Table 92](#).



**NOTE:** You can move the cursor only within the boundaries of the current page, as determined by the page coordinate.

**Table 92: ScreenMan Form Editor—Navigating: Cursor Movement and Keyboard Combination**

To Move the Cursor	Press
Up one line.	<ARROWUP>
Down one line.	<ARROWDOWN>
Right one column.	<ARROWRIGHT>
Left one column.	<ARROWLEFT>
One field to the right.	<Tab> or S
One field to the left.	Q or A
Five columns to the right.	S
Five columns to the left.	A
Top of screen.	<PF1><ARROWUP>
Bottom of screen.	<PF1><ARROWDOWN>
Right edge of screen.	<PF1><ARROWRIGHT>
Left edge of screen.	<PF1><ARROWLEFT>

## 5.7 Going to Another Page

In the Form Editor, you work with one page at a time. The page with which you are currently working is indicated in the status area at the bottom portion of the screen. To go to another page, press <PF1>P. The Form Editor asks you to select another page on the form:

**Figure 251: ScreenMan Form Editor—Going to Another Page**

Select PAGE:

Here you can enter ? (a single question mark) to get a list of the pages defined on the form. The page you select becomes the current page and the Form Editor displays the fields on that page in the Work Area of the [Main Screen](#).

Shortcut keys listed in [Table 93](#) also allow you to quickly change the current page:

**Table 93: ScreenMan Form Editor—Changing Current Page: Shortcut Keys**

Shortcut Key Sequence	Description
<PF1><PF1><ARROWDOWN>	If the current page has a <a href="#">Next Page</a> defined, you can press this key sequenced to go to the next page.
<PF1><PF1><ARROWUP>	If the current page has a <a href="#">Previous Page</a> defined, you can press this key sequence to go to the previous page.
<PF1>D	If one of the fields on the current page has a subpage associated with it, you can go to that subpage by first selecting the field (press <b>Spacebar</b> or <b>Enter</b> over the caption of that field) and then press this key sequence.
<PF1>C	To close a subpage and return to the page underneath, press this key sequence.

## 5.8 Adding Pages, Blocks, and Fields

- [Adding Pages \(<PF2>P\)](#)
- [Adding Blocks <PF2>B](#)
- [Adding Fields <PF2>F](#)

### 5.8.1 Adding Pages (<PF2>P)

To add a new page to the form, press <PF2>P. The Form Editor asks you to enter the page number of the new page:

**Figure 252: ScreenMan Form Editor—Adding a Page**

NEW PAGE NUMBER:

Here you *must* enter a page number that has *not* yet been used on the form. Press <PF1>Q to close this “popup” page and abort adding a new page. Once you have selected a new page number, the Form Editor asks:

**Figure 253: ScreenMan Form Editor—Adding a Page Confirmation**

Are you adding Page *n*  
as a new page on this form?

If you answer **YES**, the Form Editor invokes a ScreenMan form in which you can edit the properties of the new page.



**REF:** See the “[Editing Page Properties](#)” section.

## 5.8.2 Adding Blocks <PF2>B

To add a new block to the current page, move the cursor to the location on the page where you want the upper left corner of the block positioned, and press <PF2>B. The Form Editor asks you for the name of the block you want to add to the current page:

**Figure 254: ScreenMan Form Editor—Adding a Block**

```
Select NEW BLOCK NAME:
```

Here, you can either select an existing block from the BLOCK (#.404) file, or enter the name of a new block. If you enter the name of a new block (e.g., ZZTEST BLOCK 1), the Form Editor asks you whether you wish to add the block to the BLOCK (#.404) file:

**Figure 255: ScreenMan Form Editor—Adding a Block Confirmation**

```
ARE YOU ADDING `ZZTEST BLOCK 1' AS A NEW BLOCK (THE 36TH)?
```

And, whether you want to add the block to the current page of the form:

**Figure 256: ScreenMan Form Editor—Adding a Block to a Page**

```
Are you adding ZZTEST BLOCK 1 as a new block on this page?
```

If you answer **YES** to these questions, the Form Editor invokes a ScreenMan form where you can edit the properties of the new block.



REF: See the “[Editing Block Properties](#)” section.

### 5.8.2.1 Header Blocks

For backward compatibility, the Form Editor displays and allows you to edit the properties of Header Blocks already defined on the form. It does *not*, however, provide a way to add Header Blocks to a form, since Display-type blocks provide the same functionality as Header Blocks. Instead of creating a Header Block on a page, you can create a Display-type block with a coordinate of “1,1” relative to the page.

## 5.8.3 Adding Fields <PF2>F

To add fields to a block on the current page of the form, you *must* be on the Form Editor’s [Main Screen](#). If you are currently on the [Block Viewer Screen](#), press <PF1>V to return to the Form Editor [Main Screen](#). Before you can add fields, at least one block *must* be defined on the current page.

To add a field, move the cursor to the desired location of the new field and press <PF2>F. The Form Editor presents the dialogue in [Figure 257](#):

**Figure 257: ScreenMan Form Editor—Adding Fields**

```
Select BLOCK:  
FIELD ORDER:  
FIELD TYPE:
```

To close this “popup” page and abort adding a new field, press <PF1>Q.

You can change any of the default answers the Form Editor provides. The Form Editor asks you to select a block on which to add the new field. You can select only those blocks that are defined on the current page. The Form Editor also asks you for the [Field Order](#) number and the [Field Type](#) of the new field.

Once you have filled in all the information in this “popup” page, press <PF1>E. The Form Editor adds the new field to the block, and invokes a form where you can edit the properties of the field just created.



**REF:** See the “[Editing Field Properties](#)” section.

## 5.9 Selecting and Moving Screen Elements

### 5.9.1 Selecting Screen Elements

The items you see on the Form Editor’s [Main Screen](#) and [Block Viewer Screen](#) are called **screen elements**. They include field captions and data fields shown on the [Main Screen](#), and block names shown on the [Block Viewer Screen](#):

- To select a screen element, press **Spacebar** or **Enter** over the element.
- To deselect an element, press **Spacebar** or **Enter** again.

### 5.9.2 Moving Screen Elements

To move a screen element, such as a field or block to a new location:

1. Position the cursor over the element.
2. Select it with **Spacebar** or **Enter** keys.
3. Use the key sequences in [Table 94](#) to move the element.

**Table 94: ScreenMan Form Editor—General Key Sequences to: Move Screen Elements**

To Drag an Element	Press this Key Sequence
Up one line	<ARROWUP>
Down one line	<ARROWDOWN>
Right one column	<ARROWRIGHT>
Left one column	<ARROWLEFT>
Five columns to the right	<Tab> or S
Five columns to the left	Q or A
Top of screen	<PF1><ARROWUP>
Bottom of screen	<PF1><ARROWDOWN>
Right edge of screen	<PF1><ARROWRIGHT>
Left edge of screen	<PF1><ARROWLEFT>

You can drag a field only within the boundaries of the block on which it is defined, and you can drag a block only within the boundaries of the page on which it is defined.



**NOTE:** No matter where you move a field, it remains associated with the block on which it was originally defined.

If you select the caption of a field, both the caption and data portion of the field, if one exists, are selected and can be dragged as a single unit. If you select the data portion of a field, only the data portion is selected and can be dragged independently of the caption.

If you drag a block name to a new location on the [Block Viewer Screen](#), all fields on that block move to a new location.

The [Block Coordinate](#) of a block defines the upper left boundary of the block. The block boundary extends from that coordinate to the lower right edge of the Display/Edit Area.

Similarly, the [Page Coordinate](#) of a page defines the upper left boundary of the page. If the page is a regular page, the page boundary extends from that coordinate to the lower right edge of the Display/Edit Area. If the page is a “popup” page, the [Lower Right Coordinate](#) of the page defines the lower right boundary of the page.

## 5.10 Editing Properties

### 5.10.1 Editing Field Properties

To edit the properties of a field:

1. Select the field with **Spacebar** or **Enter** keys.
2. Press **PF4**.
3. The Form Editor invokes a ScreenMan form where the properties of the field can be edited.

The specific form that is invoked depends on the type of the selected field. For example, the form for editing **Data Dictionary** fields looks like [Figure 258](#):

**Figure 258: ScreenMan Form Editor—Editing Field Properties**

```

----- Data Dictionary Field Properties -----
FIELD ORDER:                                FIELD:
ORDER PARAMETERS...                          SUPPRESS COLON AFTER CAPTION?
UNIQUE NAME:

CAPTION:
DEFAULT:
EXECUTABLE CAPTION:
EXECUTABLE DEFAULT:

BRANCHING LOGIC:
PRE ACTION:
POST ACTION:
POST ACTION ON CHANGE:

```

When you enter a value at the “FIELD:” prompt for **Data Dictionary** fields, the Form Editor automatically defines the **Caption** as the field’s label:

- Multiple field—If the field is a Multiple field, the Form Editor adds the word “**Select**” before the field’s label.
- WORD-PROCESSING field—If the field is a WORD-PROCESSING field, the Form Editor adds the characters “**(WP)**” after the field’s label.

At the “CAPTION:” prompt, you can:

- Accept the Form Editor’s default.
- Enter a new caption.
- Enter one of the captions listed in [Table 95](#):

**Table 95: ScreenMan Form Editor—Shortcuts at the CAPTION Prompt**

To Define the Caption as	Enter at the CAPTION Prompt
Field label	!L
Field title	!T
Unique name of field	!U
Duplicated string	!DUP(string,number of occurrences) For example, !DUP("-",79)

The “OTHER PARAMETERS:” prompt is followed by an ellipsis (...) to indicate that this field leads to a new page. To view that page:

1. Navigate to the Other Parameters field.
2. Press the **Enter** key.
3. A “popup” window appears where you can edit additional properties of the field.

**Figure 259: ScreenMan Form Editor—Other Parameters**

```

----- Data Dictionary Field Properties -----
----- Other Parameters -----
      REQUIRED: _____          DISPLAY GROUP: _____
  DISABLE EDITING: _____      RIGHT JUSTIFY: _____
    SUB PAGE LINK: _____

      DATA LENGTH: _____
  CAPTION COORDINATE: _____
    DATA COORDINATE: _____

    DATA VALIDATION: _____
  
```

To close the Other Parameters “popup” window, press <PF1>C. To return to the Form Editor’s [Main Screen](#), press <PF1>E to exit and save your changes, or press <PF1>Q to quit the form without saving your changes.

### 5.10.1.1 Editing Field Captions and Data Length

As described in the “[Editing Field Properties](#)” section, you can press **PF4** to invoke a ScreenMan form to edit the [Caption](#) and [Data Length](#) of fields. You can also edit these properties directly from the Form Editor’s [Main Screen](#).

To change the **Caption** of a field:

1. Position the cursor over the caption.
2. Press **PF3**.
3. Edit the caption with the same editing keys available in ScreenMan’s Field Editor.
4. Press **Enter** when you are finished editing the caption.

To change the **Data Length** of a field:

1. Position the cursor over the data portion of the field.
2. Press **PF3**.
3. Increase and decrease the **Data Length** by pressing <**ARROWRIGHT**> and <**ARROWLEFT**>. An indicator (**L=n**) at the lower right portion of the [Main Screen](#) indicates the current **Data Length**.
4. Press the **Enter** key when you are finished editing the **Data Length**.

### 5.10.1.2 Reordering All Fields on a Block

After creating and arranging all the fields on a block, you can quickly make the [Field Order](#) of all the fields equivalent to the tab order by doing the following:

1. Go to the [Block Viewer Screen](#) (<**PF1**>**V**).
2. Select the block (**Spacebar** or **Enter** over the block name).
3. Press <**PF1**>**O**.

Remember that the **Field Order** is the order in which the elements on the block are traversed when the user presses **Enter**. The <**PF1**>**O** key sequence reassigns **Field Order** numbers to all the elements on the block, so that the **Enter** key takes the user from field to field in the same order as the **Tab** key (left to right, top to bottom).



**NOTE:** If you refer to fields by [Field Order](#) in places, such as [Branching Logic](#), [Pre Action](#), and [Post Action](#), reordering the fields on the block could cause that code to refer to the wrong fields. You *must* then modify the code to either reflect the new **Field Order** numbers, or refer to those fields by [Caption](#) or [Unique Name](#) instead.

## 5.10.2 Editing Block Properties

To edit the properties of a block on the current page:

1. Press <**PF1**>**V** to go to the [Block Viewer Screen](#).
2. Select the block name with **Spacebar** or **Enter** keys.
3. Press **PF4**.
4. The Form Editor invokes a ScreenMan form where the properties of the block can be edited.

The form for editing block properties looks like [Figure 260](#):

**Figure 260: ScreenMan Form Editor—Editing Block Properties**

```
----- Block Properties Stored in FORM File -----
|
|      BLOCK NAME:                                BLOCK ORDER:
|      TYPE OF BLOCK:                            OTHER PARAMETERS...
|      POINTER LINK:
|
|      PRE ACTION:
|      POST ACTION:
|
|----- Block Properties Stored in BLOCK File -----
|
|      NAME:                                     DESCRIPTION (WP):
|      DD NUMBER:                               DISABLE NAVIGATION:
|
|      PRE ACTION:
|      POST ACTION:
|-----
```

The fields on the **top** portion of the preceding screen are fields from the FORM (#.403) file. Changes to the values of the fields in this area affect the block only as it is used on this particular form.

The fields on the **bottom** portion of the screen are fields from the BLOCK (#.404) file. Changes to the values of the fields in this area affect the properties of the block itself, and thus, affect any form that uses this block.

When you create a new block, make sure that the [DD Number](#) is correct. The Form Editor provides a default **DD Number** equal to the Primary file of the form. If you are creating a block that contains fields from a subfile, or from a file to which you are navigating, you *must* change the **DD Number**.



### 5.10.3 Editing Page Properties



**REF:** For information on how to move from page to page when editing a form, see the “[Going to Another Page](#)” section.

To edit the properties of the current page, press <PF4>P from the Form Editor’s [Main Screen](#). The form for editing page properties looks like [Figure 261](#):

**Figure 261: ScreenMan Form Editor—Editing Page Properties**

```
----- Page Properties -----
PAGE NUMBER:
PAGE NAME:
HEADER BLOCK:

PAGE COORDINATE:                IS THIS A POP UP PAGE?
                                LOWER RIGHT COORDINATE:

NEXT PAGE:
PREVIOUS PAGE:
PARENT FIELD:

DESCRIPTION (WP):
PRE ACTION:
POST ACTION:
```

If you want the page to be a “popup” page (window):

1. At the “IS THIS A POP UP PAGE?” prompt, enter **YES**.
2. Enter a value for “LOWER RIGHT COORDINATE”.



**NOTE:** VA FileMan 22.2 supports screens longer than 24 lines.

### 5.10.3.1 Editing “Popup” Page Coordinates

As described in Section [5.10.3](#), “[Editing Page Properties](#),” you can press <PF4>P to invoke a ScreenMan form to edit the properties of the current page. You can also change the coordinate of a “popup” page directly from the Form Editor’s [Main Screen](#), by selecting and dragging the border of the “popup” page.

[Figure 262](#) is an example of the Main Screen of the Form Editor where the current page is a “popup” page.

**Figure 262: ScreenMan Form Editor—Editing “Popup” Page Coordinates**

```
THIS IS A CAPTION ONLY FIELD

NAME: _____
SSN:  _____
SELECT PHONE: _____

-----
This is the pop-up page
-----

File: ZZFILE NAME (# nnnn)                                R1,C1
Form: ZZFORM NAME
Page: n (ZZName of Pop-Up Page)

<PF1>Q=Quit   <PF1>E=Exit   <PF1>S=Save   <PF1>V=Block Viewer   <PF1>H=Help
```

To move the entire “popup” page around on the [Main Screen](#), do the following:

1. Position the cursor anywhere on the top boundary of the “popup” page.
2. Press **Spacebar** or **Enter** to select it.
3. Use the navigational keys described in the “[Moving Screen Elements](#)” section to drag the entire “popup” page to a new location.
4. Press **Spacebar** or **Enter** again to lock the page in its new position.

To resize the “popup” page (i.e., to change the lower right coordinate of the page), do the following:

1. Position the cursor over the lower right corner of the page boundary.
2. Press **Spacebar** or **Enter** to select it.
3. Use the navigational keys to move the corner to a new location.
4. Press **Spacebar** or **Enter** again when the page is the correct size.

## 5.10.4 Editing Form Properties

To edit the properties of the form, press <PF4>M from the Form Editor's [Main Screen](#). The form for editing form properties looks like [Figure 263](#):

**Figure 263: ScreenMan Form Editor—Editing Form Properties**

```
----- Form Properties -----
NAME:
TITLE:

PRE ACTION:
POST ACTION:
DATA VALIDATION:
POST SAVE:

DESCRIPTION:                                RECORD SELECTION PAGE:

READ ACCESS:
WRITE ACCESS:
```

## 5.11 Choosing Another Form

You can select another form to edit or create a new form without leaving the Form Editor. Press <PF1>M or <PF2>M to select another file and form. You see the same prompts described in the section “Invoking the Form Editor”:

**Figure 264: ScreenMan Form Editor—Choosing Another Form**

```
EDIT/CREATE FORM FOR WHAT FILE:
```

And:

**Figure 265: ScreenMan Form Editor—Select Form**

```
Select FORM:
```

If you select a different form or create a new form, and changes to the previous form (e.g., ZZTEST) have *not* yet been saved, the Form Editor asks:

**Figure 266: ScreenMan Form Editor—Save Changes**

```
Save changes to form ZZTEST? YES//
```

This gives you the opportunity to save or discard your changes before moving on to the next form.

## 5.12 Deleting Screen Elements (Fields, Blocks, Pages, and Forms)

In general, to delete a **screen element**:

1. Select and edit the properties of the element.
2. Enter an at-sign (@) at the first field of the ScreenMan form.

### 5.12.1 Deleting Fields

To delete a **field**, select the field by pressing **Spacebar** or **Enter** over the caption of the field, press **PF4** to invoke the form to edit the properties of the field, and then enter an at-sign (@) at the “FIELD ORDER:” prompt.

### 5.12.2 Deleting Blocks

Similarly, to delete a **block**:

1. Select the block on the [Block Viewer Screen](#).
2. Press **PF4** to invoke the form to edit block properties.
3. Enter an at-sign (@) at the “BLOCK NAME:” prompt.
4. Answer **YES** to the warning that deletions are done immediately.
5. If the block is *not* used on any other forms, the Form Editor also asks whether you want to delete the block from the BLOCK (#.404) file.

If you choose *not* to delete the block from the BLOCK (#.404) file, you can subsequently delete the block only by running the ScreenMan Purge Unused Blocks option [DDS PURGE UNUSED BLOCKS].

### 5.12.3 Deleting Pages

To delete a **page**:

1. Make that page the current page.
2. Press <PF4>P to invoke the form to edit page properties.
3. Enter an at-sign (@) at the “PAGE NUMBER:” prompt.



**REF:** For information on how to move from page to page when editing a form, see the “[Going to Another Page](#)” section.

## 5.12.4 Deleting Forms

You *cannot* delete a **form** from the Form Editor. To delete a form:

1. Exit the Form Editor.
2. Perform the steps in [Figure 267](#) from the VA FileMan menu [DIUSER]:

**Figure 267: ScreenMan Form Editor—Choosing Another Form**

```
Select VA FileMan Option: OTHER OPTIONS
Select Other Options Option: SCREENMAN
Select ScreenMan Option: ?
Answer with SCREENMAN OPTION NUMBER, or NAME
Choose from:
  1          EDIT/CREATE A FORM
  2          RUN A FORM
  3          DELETE A FORM
  4          PURGE UNUSED BLOCKS

Select SCREENMAN OPTION: D <Enter> ELETE A FORM
```



**REF:** For more information on this menu option, see the “[ScreenMan Menu Options](#)” section in the “[ScreenMan Forms](#)” section.

## 6 ScreenMan API

### 6.1 Introduction

VA FileMan's ScreenMan utility provides a screen-oriented interface for editing and displaying data. The APIs described in this section provide entry points for loading a ScreenMan form and entry points you can use at various places within a ScreenMan form.



**REF:** See also:

- The “[ScreenMan Forms](#)” section.
- The “[ScreenMan Form Editor](#)” section.
- The *ScreenMan Tutorial for Developers Manual*, located on the VDL at: <http://www4.va.gov/vdl/application.asp?appid=5>.

### 6.2 ^DDS: Invoke ScreenMan

You can call the ^DDS API directly from an M routine to invoke the specified form.

The ^DDS API invokes a ScreenMan form attached to the specified file. ScreenMan automatically uses incremental locks to lock all records accessed during an editing session.

#### Input Variables

DDSFIL:	(Required) The number or global root of the Primary file of the form.
DR:	(Required) The name of the form (an entry in the FORM [#.403] file) enclosed in square brackets.
DA:	(Optional) The record number of the file entry to display or edit. If <b>DA</b> is null or undefined, the form <i>must</i> either contain no <a href="#">Data Dictionary</a> fields or have a <a href="#">Record Selection Page</a> , which is the first page ScreenMan presents to the user and is where the user can select a record from the file.



**REF:** See [Example 2](#) when a subfile is being accessed directly.

DDSPAGE:	(Optional) The <a href="#">Page Number</a> of the first page to display to the user. If <code>`\$G(DDSPAGE)</code> , a page with a <b>Page Number</b> equal to <b>1</b> <i>must</i> exist on the form and that is the first page ScreenMan presents to the user.
DDSPARM:	(Optional) A string of alphabetic characters that control ScreenMan's behavior are listed below: <ul style="list-style-type: none"><li>• <b>C</b>—Return the variable <b>DDSCHANG=1</b> if ScreenMan detects that the user saved a <b>Change</b> to the database.</li><li>• <b>E</b>—Return <b>Error</b> messages in <code>^TMP(“DIERR”, \$J)</code> and return <b>DIERR</b> if ScreenMan encounters problems when initially trying to load the form. If <b>DDSPARM</b> does <i>not</i> contain an <b>E</b>, ScreenMan prints messages directly on the screen, and returns the <b>DIMSG</b> variable equal to null.</li><li>• <b>S</b>—Return the variable <b>DDSSAVE=1</b> if the user pressed <code>&lt;PF1&gt;S</code> or <code>&lt;PF1&gt;E</code>, or entered an <b>Exit</b> or <b>Save</b> command from the command line, whether or <i>not</i> any changes were actually made on the form.</li></ul>

If ^DDS is used to display or edit data in a subfile directly, the following variables *must* be set in addition to the variables listed above:

DDSFIL(1): (Required) Contains the subfile number or the global root of the subfile.

DA(1) ... DA(n): (Required) The **DA** array, where:

- **DA** is the subrecord number at the deepest level.
- **DA(n)** is the record number at the top-level.

All the input variables are returned unchanged by the ^DDS call. KILL **DDSFIL(1)** when the call is complete to avoid conflict with subsequent ^DDS calls.

### Output Variables

DDSCHANG: **\$G(DDSCHANG)=1**, if the **DDSPARM** input variable to ^DDS contains a **C** and ScreenMan detects that the user saved a change to the database.

DDSSAVE: **\$G(DDSSAVE)=1**, if the **DDSPARM** input variable to ^DDS contains an **S** and the user pressed <PF1>E or <PF1>S, or issued the **Save** or **Exit** command from the command line.

DIMSG: **\$D(DIMSG)>0**, if the form could *not* be loaded, and the **DDSPARM** input variable to ^DDS does *not* contain an **E**.



**REF:** See the description of the [DDSPARM](#) input variable.

DTOUT: **\$D(DTOUT)>0**, if the user times out during the editing session.

## 6.2.1 DDS Variable

**\$D(DDS)** can be checked within programming hooks, such as Executable Help and INPUT Transforms to determine whether the hook is being executed from within a ScreenMan form. In that case, **\$D(DDS)** evaluates to **true**.

## 6.2.2 Examples

### 6.2.2.1 Example 1

Invoke the form EE FORM1 to edit the 15th entry in (fictitious) File #16500, as shown in [Figure 268](#):

**Figure 268: ^DDS API—Example 1: Input**

```
>S DDSFILE=16500,DA=15,DR="[EE FORM1]" D ^DDS
```

### 6.2.2.2 Example 2

As shown [Figure 269](#), invoke the form EE FORM2 to edit the 31st subentry in (fictitious) Subfile #16100.01, for the 9th entry in (fictitious) File #16100; Page Number 11 is the first page to present to the user; and have ScreenMan return **DDSCHANG** if it detects a change to the database when the user exits:

**Figure 269: ^DDS API—Example 2: Input**

```
>S DDSFILE=16100,DDSFILE(1)=16100.01
>S DA=31,DA(1)=9,DR="[EE FORM2]"
>S DDSPAGE=11,DDSPARM="C"
>D ^DDS
```

### 6.2.3 Error Codes Returned

[Table 96](#) lists the possible error codes returned with the ^DDS API.



**NOTE:** Error codes are returned only if the **DDSPARM** input variable to ^DDS contains an **E**.

**Table 96: ^DDS API—Error Codes Returned**

Code	Description
<a href="#">201</a>	The specified input variable is missing or invalid.
<a href="#">202</a>	One of the input variables is not properly specified.
<a href="#">405</a>	Entries in the file cannot be edited.
<a href="#">810</a>	At least one of the required ^%ZOSF nodes is missing.
<a href="#">840</a>	The Terminal Type file does not have an entry that matches IOST(0).
<a href="#">842</a>	At least one required piece of data in the Terminal Type file is null for the terminal type identified by IOST(0).
<a href="#">845</a>	A call to HOME^%ZIS returns \$G(POP)>0.
<a href="#">3021</a>	The specified form does not exist in the Form file, or DDSFILE is not the Primary File of the form.
<a href="#">3022</a>	The specified form contains no pages.
<a href="#">3023</a>	The form does not contain the specified page.



## 6.3 \$\$GET^DDSVAL(): Retrieve Data from a Data Dictionary Field

You can use the \$\$GET^DDSVAL extrinsic function only within a ScreenMan form, in all places where M code can be placed on the form.

The \$\$GET^DDSVAL extrinsic function retrieves data from a [Data Dictionary](#) field. If the user has edited the field on the ScreenMan form, or if the form designer has modified the field with a [PUT^DDSVAL](#) call, the function returns the new value, even if the user has *not* yet saved the change to the database. If the field has *not* been edited on the ScreenMan form, the function retrieves the data from the VA FileMan file/global.

For programming hooks at the field level (i.e., [Branching Logic](#), [Post Action](#), [Post Action On Change](#), and [Data Validation](#)), you can use \$\$GET^DDSVAL to obtain values of other fields, but you *cannot* use it to obtain the old and new values of the current field. For the field currently being edited, use the following variables instead:

- **DDSOLD**
- **X**
- **DDSEXT**

Text for a WORD-PROCESSING field is moved into a global array and \$\$GET^DDSVAL returns the closed root of that array. The array has the same format as a VA FileMan WORD-PROCESSING field.


COMPUTED fields in VA FileMan files *cannot* be retrieved. To retrieve the value of a COMPUTED field defined on the form, use the [\\$\\$GET^DDSVALF](#) function.

If, while a form is running, a call to \$\$GET^DDSVAL fails, ScreenMan prints an error message in the Command Area.

### Format

```
$$GET^DDSVAL(file,[.]record,field[,.error][,flags])
```

### Input Parameters

file:	(Required) The global root or number of the file or subfile. At the field level, the local variable <b>DIE</b> contains the current global root.
[.]record:	(Required) The internal entry number or an array of internal entry numbers. This parameter has the same form as the <b>DA</b> array. At the field level, the local array <b>DA</b> contains the current array of internal entry numbers.
field:	(Required) The field name or number or a relational expression that follows a forward pointer (e.g., POINTER:FIELD).
	 <b>REF:</b> The “ <a href="#">Relational Navigation: Forward Pointers</a> ” section in the “ <a href="#">ScreenMan Forms</a> ” section describes in detail the syntax accepted by ScreenMan to describe a relational jump via a <a href="#">Data Dictionary</a> field.
.error:	(Optional) <b>\$D(ERROR)&gt;1</b> , if the function call fails.

flags: (Optional) Controls whether the internal or external form is returned, as shown below (the **I** and **E** flags have no effect if the **field** parameter is a WORD-PROCESSING field):

- **I** (Default)—Return the **I**nternal form of the data.
- **E**—Return the **E**xternal form of the data.

## 6.3.1 Examples

### 6.3.1.1 Example 1

Retrieve the internal form of the **.01** field of the record currently being edited:

**Figure 270: \$\$GET^DDSVAL API—Example 1: Input**

```
S nmspNAME=$$GET^DDSVAL(DIE,.DA,.01)
```

### 6.3.1.2 Example 2

Retrieve the external form of Field #20, record #362, in (fictitious) File #16000:

**Figure 271: \$\$GET^DDSVAL API—Example 2: Input**

```
S nmspDATE=$$GET^DDSVAL(^DIZ(16000,"",362,20,"","E"))
```

### 6.3.1.3 Example 3

Retrieve the text contained in a WORD-PROCESSING field named DESCRIPTION:

**Figure 272: \$\$GET^DDSVAL API—Example 3: Input**

```
S nmspWP=$$GET^DDSVAL(DIE,.DA,"DESCRIPTION")
```

The text of the DESCRIPTION field is moved to the array as follows:

**Figure 273: \$\$GET^DDSVAL API—Example 3: Output Array**

```
@nmspWP@(0)=Header node of word processing field
@nmspWP@(1,0)=Line 1
@nmspWP@(2,0)=Line 2
...etc.
```

## 6.4 PUT^DDSVAL(): Stuff Data into a Data Dictionary Field

You can use the PUT^DDSVAL API only within a ScreenMan form, in all places where M code can be placed on the form.

The PUT^DDSVAL API stuffs data into a **Data Dictionary** field as part of ScreenMan's transaction. The data passed to this API is filed in the database only when the user explicitly saves changes. Until then, it is stored in a temporary location.

If the specified field is a WORD-PROCESSING field, the value passed to the API is the closed root of the array that contains the text.

If the specified field is a Multiple field, the value passed is the subrecord first displayed to the user as a default at the Multiple field. This value is a default for selection and is *not* actually filed.

Values *cannot* be stuffed into COMPUTED fields.

If, while a form is running, a call to PUT^DDSVVAL fails, ScreenMan prints an error message in the Command Area.

## Format

```
PUT^DDSVVAL(file,[.]record,field,value[,.error][,flags])
```

## Input Parameters

- file: (Required) The global root or number of the file or subfile. At the field level, the local variable **DIE** contains the current global root.
- [.]record: (Required) The internal entry number or an array of internal entry numbers. This parameter has the same form as the **DA** array. At the field level, the local array **DA** contains the current array of record numbers.
- field: (Required) The field name or number.
- value: (Required) The value to stuff into the data dictionary field. If the **flags** parameter does *not* contain an **I**, the value *must* be in the form of a valid, unambiguous user response.

If the **field** parameter is a WORD-PROCESSING field, **value** *must* be the closed root of the array that contains the text. The subscripts of the nodes below the root *must* be positive numbers, although they need *not* be integers, and there can be gaps in the sequence. The text *must* be in these nodes or in the **0** node descendent from these nodes.

If **field** is a Multiple field, **value** determines the subrecord to display to the user as a default for selection. It is *not* a value that is ever filed. The **value** can be “**FIRST**”, “**LAST**”, or the specific internal entry number of the subrecord to display:

- “**FIRST**” indicates that the subrecord with the lowest internal entry number should be displayed.
- “**LAST**” indicates that the subrecord with the highest internal entry number should be displayed.

- .error: (Optional) **\$D(ERROR)>1**, if the API call fails.
- flags: (Optional) Indicates whether the **value** parameter is in internal or external form, as shown below:
- **A**—Append new word-processing text to the current text. This flag can be used only when stuffing text into a WORD-PROCESSING field. If the **A** flag is *not* sent, the current word-processing text is completely erased before the new text is added.
  - **I**—The **value** parameter is in **I**nternal form; it is *not* validated.
  - **E** (Default)—The **value** parameter is in **E**xternal form.

The **I** and **E** flags have no effect when **field** is a WORD-PROCESSING field.

## 6.4.1 Examples

### 6.4.1.1 Example 1

Stuff the value 2940801 into a date Field #20. The value passed is in internal form:

**Figure 274: PUT^DDSVAL API—Example 1: Input**

```
D PUT^DDSVAL(DIE,.DA,20,2940801,"","I")
```

No data validation is performed.

### 6.4.1.2 Example 2

Stuff word-processing text from an array into a WORD-PROCESSING field named DESCRIPTION as shown in [Figure 275](#):

**Figure 275: PUT^DDSVAL API—Example 2: Input**

```
D PUT^DDSVAL(DIE,.DA,"DESCRIPTION",^^nmspWP("TEXT"))
```

The array that contains the text looks like [Figure 276](#):

**Figure 276: PUT^DDSVAL API—Example 2: Output Array (1 of 2)**

```
^nmspWP("TEXT",1,0)=Line 1  
^nmspWP("TEXT",2,0)=Line 2  
...etc.
```

Or [Figure 277](#):

**Figure 277: PUT^DDSVAL API—Example 2: Output Array (2 of 2)**

```
^nmspWP("TEXT",1)=Line 1  
^nmspWP("TEXT",2)=Line 2  
...etc.
```

## 6.5 \$\$GET^DDSVALF(): Retrieve Data from a Form-only Field

You can use the \$\$GET^DDSVALF extrinsic function only within a ScreenMan form, in all places where M code can be placed on the form.

The \$\$GET^DDSVALF extrinsic function retrieves data from a [Form-only](#) field or a [Computed](#) field.

If, while a form is running, a call to \$\$GET^DDSVALF fails, ScreenMan prints an error message in the Command Area.

### Format

```
$$GET^DDSVALF(field,block,page[,flags],iens)
```

### Input Parameters

- field: (Required) The [Field Order](#) number, [Caption](#), or [Unique Name](#) of the [Form-only](#) field.
- block: (Required at the page and form levels) The [Block Order](#) or [Block Name](#). The default is the current block.
- page: (Required at the form level) The [Page Number](#) or [Page Name](#). The default is the current page.
- flags: (Optional) Controls whether the internal or external form is returned, as shown below:
- **I** (Default)—Return the **I**nternal form of the data.
  - **E**—Return the **E**xternal form of the data.
- iens: (Required at the page and form levels) The standard IENS that identifies the entry or subentry associated with the [Form-only](#) field. The default is the current entry or subentry.



**REF:** For a detailed description of IENS, see the “[IENS: Identify Entries and Subentries](#)” section in the “[Database Server \(DBS\) API](#)” section.

### 6.5.1 Examples

#### 6.5.1.1 Example 1

Retrieve the value of a [Computed](#) field called TOTAL on the current block:

**Figure 278: \$\$GET^DDSVALF API—Example 1: Input**

```
>S nmspTOT=$$GET^DDSVALF(TOTAL)
```

### 6.5.1.2 Example 2

Retrieve the external form of a [Form-only](#) date field with caption “DATE OF BIRTH” on a block named “ZZBLOCK 1”:

Figure 279: \$\$GET^DDSVALF API—Example 2: Input

```
>S nmspDATE=$$GET^DDSVALF("DATE OF BIRTH","ZZBLOCK 1","","E")
```

## 6.6 PUT^DDSVALF(): Stuff Data into a Form-only Field

You can use the PUT^DDSVALF API only within a ScreenMan form, in all places where M code can be placed on the form.

The PUT^DDSVALF API stuffs data into a [Form-only](#) field.

If, while a form is running, a call to PUT^DDSVALF fails, ScreenMan prints an error message in the Command Area.

### Format

```
PUT^DDSVALF(field,block,page,value[,flags],iens)
```

### Input Parameters

- field: (Required) The [Field Order](#) number, [Caption](#), or [Unique Name](#) of the [Form-only](#) field.
- block: (Required at the page and form levels) The [Block Order](#) or [Block Name](#). The default is the current block.
- page: (Required at the form level) The [Page Number](#) or [Page Name](#). The default is the current page.
- value: (Required) The value to stuff into the form-only field. If the **flags** parameter does *not* contain an **I**, the value *must* be in the form of a valid, unambiguous user response.
- flags: (Optional) Indicates whether the **value** parameter is in internal or external form, as shown below:
- **I**—The **value** parameter is in **I**nternal form; it is *not* validated.
  - **E** (Default)—The **value** parameter is in **E**xternal form.
- iens: (Required at the page and form levels) The standard IENS that identifies the entry or subentry associated with the [Form-only](#) field. The default is the current entry or subentry.



**REF:** For a detailed description of IENS, see the “[IENS: Identify Entries and Subentries](#)” section in the “[Database Server \(DBS\) API](#)” section.

## 6.6.1 Example

Stuff the value 2940801 into a [Form-only](#) date field with the caption “DATE”, as shown in [Figure 280](#):

Figure 280: PUT^DDSVLFF API—Example: Input

```
>D PUT^DDSVLFF("DATE", "", "", "AUG 1,1994")
```

The value passed is in external form (the default).

## 6.7 HLP^DDSUTL(): Print Help Messages in the Command Area

You can use the HLP^DDSUTL API only within a ScreenMan form, at all places where M code can be placed on the form.

The HLP^DDSUTL API prints messages in the Command Area.

If you pass the string “\$EOP”, then ScreenMan issues the prompt “Press RETURN to continue” in the Command Area. This is useful if, for example, you want to print messages as part of the [Post Action](#) of a page, and need to pause to give the user a chance to read the messages before ScreenMan leaves that page.

### Formats

1. HLP^DDSUTL(string)
2. HLP^DDSUTL(.string)

### Input Parameters

string: (Required; Format 1) The message to print in the Command Area.  
.string: (Required; Format 2) An array of messages to print in the Command Area.

STRING(1), STRING(2), ..., STRING(n) each contain a line of text.

## 6.8 MSG^DDSUTL(): Print Data Validation Messages on a Separate Screen

You can call the MSG^DDSUTL API only within a ScreenMan form and only in the form-level [Data Validation](#).

The MSG^DDSUTL API prints [Data Validation](#) messages on a separate screen. These messages are printed after the user issues the **Save** command or attempts to save the form on **Exit**, but *before* ScreenMan actually updates the database.

### Formats

1. MSG^DDSUTL(string)
2. MSG^DDSUTL(.string)

### Input Parameters

string: (Required; Format 1) The message to print in the Command Area.

.string: (Required; Format 2) An array of messages to print in the Command Area.  
**STRING(1), STRING(2), ..., STRING(*n*)** each contain a line of text.

## 6.9 REFRESH^DDSUTL: Refresh Screen

The REFRESH^DDSUTL API repaints *all* pages on the screen.

You can use the REFRESH^DDSUTL API only within a ScreenMan form, and only in:

- Field-level [Pre Action](#)
- Field-level [Post Action](#)
- Field-level [Branching Logic](#)
- Field-level [Data Validation](#)

### Format

```
REFRESH^DDSUTL
```

## 6.10 REQ^DDSUTL(): Change Required Property of a Field on a Form

You can use the REQ^DDSUTL API only within a ScreenMan form, in all places where M code can be placed on the form.

The REQ^DDSUTL API changes the [Required](#) property of a field on the form.

### Format

```
REQ^DDSUTL(field,block,page,value,iens)
```

### Input Parameters

field: (Required) The [Field Order](#) number, [Caption](#), or [Unique Name](#) of the field.

block: (Required at the page and form levels) The [Block Order](#) or [Block Name](#). The default is the current block.

page: (Required at the form level) The [Page Number](#) or [Page Name](#). The default is the current page.

value: (Required) The value to give the [Required](#) property, listed as follows:

- “” —Restore the [Required](#) property to the value defined in the BLOCK (#.404) file.
- 0 —Make the field *not* required.
- 1 —Make the field required.

iens: (Required at the page and form levels) The standard IENS that identifies the entry or subentry associated with the [Form-only](#) field. The default is the current entry or subentry.



**REF:** For a detailed description of IENS, see the “[IENS: Identify Entries and Subentries](#)” section in the “[Database Server \(DBS\) API](#)” section.



## 6.11 UNED^DDSUTL(): Change Disable Editing Property of a Field on a Form

You can use the UNED^DDSUTL API only within a ScreenMan form, in all places where M code can be placed on the form.

The UNED^DDSUTL API changes the [Disable Editing](#) property of a field on the form.

### Format

```
UNED^DDSUTL(field,block,page,value,iens)
```

### Input Parameters

- field: (Required) The [Field Order](#) number, [Caption](#), or [Unique Name](#) of the field.
- block: (Required at the page and form levels) The [Block Order](#) or [Block Name](#). The default is the current block.
- page: (Required at the form level) The [Page Number](#) or [Page Name](#). The default is the current page.
- value: (Required) The value to give the [Disable Editing](#) property, shown below:
- ""—Restore the [Disable Editing](#) property to the value as defined in the BLOCK (#.404) file.
  - 0—Enable editing, and allow the user to navigate to the field.
  - 1—Disable editing, and prevent the user from navigating to the field.
  - 2—Disable editing, but allow the user to navigate to the field.
- iens: (Required at the page and form levels) The standard IENS that identifies the entry or subentry associated with the [Form-only](#) field. The default is the current entry or subentry.



**REF:** For a detailed description of IENS, see the "[IENS: Identify Entries and Subentries](#)" section in the "[Database Server \(DBS\) API](#)" section.

# III. Other APIs

## 7 Auditing API

### 7.1 Introduction

Auditing allows VA FileMan users and developers to look back through the dimension of time at prior values in any file. Auditing is *not* just a tool that enhances quality control and system security. It also allows the easy retrieval of “old” values (e.g., “address,” “maiden name,” and so on). Also, for the purpose of synchronizing databases remote from one another, it is particularly valuable to be able to determine, via the audit trail, which entries in which files have been changed within a range of time.

VA FileMan provides a set of APIs, so that you can include auditing functionality in your applications.



**REF:** For more information about Auditing, see the “Auditing” section in the *VA FileMan Advanced User Manual*.

### 7.2 Application Programming Interfaces (APIs)

#### 7.2.1 TURNON^DIAUTL(): Enable/Disable Auditing

The TURNON^DIAUTL API turns on (or off) auditing for specified fields in a file (except for COMPUTED and WORD-PROCESSING fields). These changes are recorded in the Data Dictionary audit if the file has Data-Dictionary auditing turned on. Also, input templates containing the changed fields are recompiled.

#### Format

```
TURNON^DIAUTL(file,field[,mode])
```

#### Input Parameters

- File: (Required) File number of a file that is being audited.
- Field: (Required) Specifies which fields from the file are forced on (“ALWAYS”) for auditing. Can be one of the following:
- A single field number.
  - A list of field numbers separated by semicolons.
  - A range of field numbers in the form *M:N*; where *M* and *N* are the end points of the inclusive range. All field numbers within this range are audited.
  - An asterisk (\*) meaning “audit all fields.”
- Mode: (Optional) This is an optional parameter. It defaults to “y,” which means to turn on auditing.
- **y** (Default)—Yes, always audit. Turn auditing on.
  - **e**—Audit only when edited or deleted.
  - **n**—No, do *not* audit. Turn auditing off. ”

### 7.2.1.1 Examples

To turn on auditing for the STOP CODE NUMBER (#8) field in the HOSPITAL LOCATION (#44) file:

**Figure 281: TURNON^DIAUTL API—Example: Input to Turn On Auditing for a Field in a File (1 of 2)**

```
>D TURNON^DIAUTL(44,8)
```

Or:

**Figure 282: TURNON^DIAUTL API—Example: Input to Turn On Auditing for a Field in a File (2 of 2)**

```
>D TURNON^DIAUTL(44,8,"Y")
```

To turn off auditing for that field:

**Figure 283: TURNON^DIAUTL API—Example: Input to Turn Off Auditing for a Field in a File**

```
>D TURNON^DIAUTL(44,8,"N")
```

## 7.2.2 LAST^DIAUTL(): Retrieve Last Person Who Changed Data

The LAST^DIAUTL API uses the audit trail to retrieve the last user who touched a particular field value, and the date/time when this editing occurred.

### Format

```
$$LAST^DIAUTL(file,entry,field)
```

### Input Parameters

- |        |  |
|--------|--|
| file:  | (Required) File number of a file that is being audited.  |
| entry: | (Required) Entry number in the audited file.   |
| field: | (Required) Specifies which fields in the audited file are to be examined for audit history. Can be one of the following: <ul style="list-style-type: none"><li>• A single field number.</li><li>• A list of field numbers, separated by semicolons.</li><li>• A range of field numbers, in the form <i>M:N</i>; where <i>M</i> and <i>N</i> are the end points of the inclusive range. All field numbers within this range are retrieved.</li><li>• Asterisk (*) for all fields.</li></ul> |

### Output

Returns a string, delimited by a caret (^):

- String is null if there is no audit history on file for the given fields in the given entry.
- If there is a history:
  - First caret piece of the returned string is the VA FileMan internal format of the date/time of the most recent audited event.
  - Second caret piece is the user number (**DUZ**) of the user who made that most recent change.

### 7.2.2.1 Example

For example, find who last changed demographics of entry number 666 in File #2.

**Figure 284: LAST^DIAUTL API—Example: Input and Output**

```
>W $$LAST^DIAUTL(2,666,"0:1")
3000708.103432^78
```

In this example (Figure 284), user number 78 was the user who most recently changed any of the audited fields numbered between 0 and 1 in this Entry. This user did so on 8 July, 2000 at 10:34 AM.

### 7.2.3 CHANGED^DIAUTL(): Retrieve Audit History

The CHANGED^DIAUTL API returns a list of IENs of entries that have had audit events within a specified time period. Optionally, the oldest value of each audited field within that time period is returned with each entry.

#### Format

```
CHANGED^DIAUTL(file,fields[,flag],target_root[,start_date][,end_date])
```

#### Input Parameters

- file: (Required) File number of a file that is being audited.
- fields: (Required) Specifies which fields from the audited file are to be examined for audit history. Can be one of the following:
- A single field number.
  - A list of field numbers, separated by semicolons.
  - A range of field numbers, in the form *M:N*; where *M* and *N* are the end points of the inclusive range. All field numbers within this range are retrieved.
  - Asterisk (\*) meaning, “examine all audited fields.”
- flag: (Optional) The **O** flag parameter if the “oldest” values within the specified time period are to be returned. Without the **O** parameter, the API returns only the entry numbers.
- target\_root: (Required) The name of a closed root reference.
- start\_date: (Optional) Beginning date/time, in VA FileMan internal format, of the auditing period. If no **start\_date** is specified, the file’s audit history is scanned from its earliest date/time.
- end\_date: (Optional) Ending date/time, in VA FileMan internal format, of the auditing period. If no **end\_date** specified, the file’s audit history is scanned through its most recent date/time.

#### Output Parameters

- target\_root: The output array is found in **TARGET\_ROOT(IEN)=""**.  
The oldest values, if requested by the **O** parameter, are in **TARGET\_ROOT(IEN,field#)**.



**NOTE:** CHANGED^DIAUTL can only retrieve what is recorded in the VA FileMan AUDIT (#1.1) file, and does *not* look at subfiles (Multiple fields). Data entry events that happen before auditing is turned on for a particular field are *not* recorded.

Also, if the Purge Data Audits option [DIAUDIT PURGE DATA] is run, information from the audit trail is removed.

## 7.2.3.1 Examples

### 7.2.3.1.1 Example 1

In this example([Figure 285](#)), you want to find which entries in (fictitious) File #999000 have been changed since yesterday.

**Figure 285: CHANGED^DIAUTL API—Example 1: Input and Output**

```
>S %DT="",X="T-1" D ^%DT,CHANGED^DIAUTL(999000,"*", "", "^TMP($J)",Y)
^TMP($J,7)=" "
^TMP($J,4878)=" "
^TMP($J,9899)=" "
```

From this example, you find that three records have had audited events since yesterday at 12:01 AM.

### 7.2.3.1.2 Example 2

In this example ([Figure 286](#)), you want to find which NAMES in (fictitious) File #999000 have ever been changed, and retrieve the original NAMES.

**Figure 286: CHANGED^DIAUTL API—Example 2: Input and Output**

```
>D CHANGED^DIAUTL(999000,.01,"O","ARRAY") ZW ARRAY
ARRAY(344)=" "
ARRAY(344,.01)="DELETED,DAVID"
ARRAY(477)=" "
ARRAY(477,.01)="UNMARRIED,UNA"
```

From this example, you find two records are found, because the audit status of the **.01** field of this file is “EDITED OR DELETED”. Entry 344 no longer exists. Entry 477 has a new married name. It is the EXTERNAL version of the old value that is returned. If the name was changed twice in the time period, the oldest value would be returned.

## 8 Browser API

### 8.1 Browser (DDBR) Introduction

The Browser displays ASCII text on a terminal that supports a scroll region. It enables a user to view text *but not to edit it*. The text can be in the form of a VA FileMan WORD-PROCESSING field or sequential local or global array. The call allows the user to navigate within the document, displaying desired parts of the text. It enables the user to scroll:

- Up
- Down
- Right
- Left
- Top
- Bottom

It also allows the user to go to various locations in a document:

- line
- Column
- Screen

The user can:

- Switch to another document instantaneously
- Find a string and select the search direction
- Split the screen to view separate parts of two documents simultaneously

VA FileMan provides a set of APIs so you can include Browser functionality in your applications.



**REF:** For more information about the Browser interface, see the “Browser” section in the *VA FileMan User Manual*.

## 8.2 Application Programming Interfaces (APIs)

### 8.2.1 EN^DDBR: Display Word-Processing Fields in Browser

The EN^DDBR API is an interactive procedure that asks the user for a file, WORD-PROCESSING field, and entry, and then displays the text using VA FileMan’s Browser facility. This API allows the user to navigate within the document, displaying parts of the text.

The Title Bar contains:

- Filename
- Entry or subentry name
- Fieldname

The Status Bar at the bottom displays:

- Leftmost column number
- Line and screen number of the cursor location
- How to exit and to get help

Users can only access WORD-PROCESSING fields in VA FileMan files to which they have Read access.

## Format

EN^DDBR

## Output

After selecting the desired file, field, and record, the WORD-PROCESSING field text is loaded into the Browser and the Browser screen is displayed on the monitor. The user can then view and navigate through the text.

## Details and Features

### 8.2.1.1 Switch Function

Switch allows the user to view more than one document. When using the Switch (<PF1>S) function in the Browser to select other VA FileMan WORD-PROCESSING fields, it is important to note that browsing is done directly on the actual record text.

## 8.2.2 BROWSE^DDBR(): View and Navigate a Document in an Array Using the Browser

The BROWSE^DDBR API enables the user to use VA FileMan's Browser to view and navigate through a document stored in a sequential local or global array.

## Format

BROWSE^DDBR(source\_array[, flags][, title][, line][, tabs][, top][, bottom])

## Input Parameters

**source\_array:** (Required) Source array in a closed root format, passed by value that is the location of a sequential local or global array containing text. This array can optionally include the “,0)” subscript nodes that are contained in VA FileMan WORD-PROCESSING structures.

**flags:** (Optional) Flags to control processing:

- **N**—No copy of the document is made. The Browser uses the source document. Useful for long static documents.



**CAUTION:** When the N flag is used, the Browser does *not* make a copy of the text; instead it uses the actual record array to browse through. Thus, it is best used when documents stored in WORD-PROCESSING fields are static and are *not* likely to be edited by another user during the browse session. This can be preferable if the source array is a scratch global and is very large. Time and resources

are saved by *not* having to copy such a structure into ^TMP("DDB",\$J).

- **R**—Restrict switching.



**REF:** See the "[Switch Function](#)" in the "[Details and Features](#)" section.

title: (Optional) Text centered in screen title.  
line: (Optional) The line in the document that would be at the bottom margin of the opening screen.  
tabs: (Optional) Closed array root, passed by value; used to scroll horizontally. If *not* set, the Browser provides default tab stops.



**REF:** Also see "[Setting Tab Stops](#)" in the "[Details and Features](#)" section.

top: (Optional) A number representing the location of the Title Bar of the Browser screen.  
bottom: (Optional) A number representing the location of the Status Bar of the Browser screen.

## Output

A successful call enables the user to use the Browser to view and navigate throughout a document stored in a sequential local or global array.

### 8.2.2.1 Example

**Figure 287: BROWSE^DDBR API—Example: Input**

```
>K ^TMP("EXAMPLE", $J)
>N I F I=1:1:300 S ^TMP("EXAMPLE", $J, I)="THIS IS LINE "_I
>D BROWSE^DDBR(^TMP("EXAMPLE", $J), "N", "Example")
```



The Browser screen displays as shown in [Figure 288](#):

**Figure 288: BROWSE^DDBR API—Example: Output**

```

-----
                                Example
-----
THIS IS LINE 1
THIS IS LINE 2
THIS IS LINE 3
THIS IS LINE 4
THIS IS LINE 5
THIS IS LINE 6
THIS IS LINE 7
THIS IS LINE 8
THIS IS LINE 9
THIS IS LINE 10
THIS IS LINE 11
THIS IS LINE 12
THIS IS LINE 13
THIS IS LINE 14
THIS IS LINE 15
THIS IS LINE 16
THIS IS LINE 17
THIS IS LINE 18
THIS IS LINE 19
THIS IS LINE 20
THIS IS LINE 21
THIS IS LINE 22
-----
Col>   1 | <PF1>H=help <PF1>E=Exit | Line>       22 of 300   Screen>       1 of 14
-----

```



**NOTE:** Since VA FileMan 22.0, the user is able to change the lines per page length to be more than **25** lines, through the PAGE LENGH property in the TERMINAL TYPE (#3.2) file.

Making this change to the Terminal Type C-VT100 it is possible to see the changes while using the Browser and ScreenMan.

### 8.2.2.2 Error Codes Returned

[Table 97](#) lists the possible error codes returned with the BROWSE^DDBR API:

**Table 97: BROWSE^DDBR API—Error Codes Returned**

Code	Description
<a href="#">200</a>	Invalid field.
<a href="#">202</a>	Invalid parameter.
<a href="#">309</a>	Multiple field. Invalid file and IENS.
<a href="#">401</a>	Data Dictionary reference for file and field not valid.
<a href="#">501</a>	Extended reference invalid.
<a href="#">510</a>	Invalid type in data dictionary.
<a href="#">601</a>	Record entry does not exist.

Code	Description
<a href="#">602</a>	Record unavailable.
<a href="#">842</a>	Device/Terminal type setup issues.



**REF:** For additional information about Browser error messages, see the “[How Information Is Returned](#)” and “[Contents of Arrays](#)” sections in the “[Database Server \(DBS\) API](#)” section.

### 8.2.2.3 Details and Features

#### 8.2.2.3.1 Switch Function

Switch allows the user to view more than one document. When using the Switch (<PF1>S) function in the Browser to select other VA FileMan WORD-PROCESSING fields, it is important to note that browsing is done directly on the actual record text. Users can only access word-processing fields in VA FileMan files for which they have Read access.

#### 8.2.2.3.2 Setting Tab Stops

[Figure 289](#) shows an example of setting up the **TAB** with stops at every tenth column:

**Figure 289: Setting up Tab Stops**

```
F I=10:10:100 S TAB(I)=""
TAB(10)=""
TAB(20)=""
TAB(30)=""
.
.
.
TAB(90)=""
TAB(100)=""
```



**NOTE:** Browser always begins at Column 1.

### 8.2.3 WP^DDBR(): Display Word-Processing Field Using the Browser

The WP^DDBR API displays WORD-PROCESSING fields, as well as allowing navigation throughout the text, in a VA FileMan -compatible database using VA FileMan’s Browser facility.

#### Format

```
WP^DDBR(file,iens,field[,flags][,title][,line][,tabs][,top][,bottom])
```

#### Input Parameters

- file: (Required) File or subfile number.
- iens: (Required) Standard IENS indicating internal entry number string.
- field: (Required) Word-processing field name or number.

flags: (Optional) Flags to control processing:

- **N**—No copy of the document is made. The Browser will use the source document. Useful for long static documents.



**CAUTION:** When the N flag is used, the Browser does *not* make a copy of the text; instead it uses the actual record array to browse through. Thus, it is best used when documents stored in WORD-PROCESSING fields are static and are *not* likely to be edited by another user during the browse session. This can be preferable if the source text is very large. Time and resources are saved by *not* having to copy such a structure into ^TMP("DDB", \$J).

- **R**—Restrict switching.



**REF:** See the "[Switch Function](#)" in the "[Details and Features](#)" section.

title: (Optional) Text that is centered in header. Document title.

line: (Optional) The line in the document that would be at the bottom margin of the opening screen.

tabs: (Optional) Closed array root, passed by value, which is used to scroll horizontally. If *not* set, the Browser provides default tab stops.



**REF:** Also see "[Setting Tab Stops](#)" in the "[Details and Features](#)" section.

top: (Optional) A number representing the location of the Title Bar of the Browser screen.

bottom: (Optional) A number representing the location of the Status Bar of the Browser screen.



**NOTE:** The **top** and **bottom** parameters define the boundaries of the scroll region.

## Output

A successful call results in the Browser screens being displayed and enables the user to use the Browser to view and navigate through WORD-PROCESSING fields in a VA FileMan-compatible database.

### 8.2.3.1 Example

**Figure 290: WP^DDBR API—Example: Input**

```
>D WP^DDBR(999088,"12","","TEXT","N","Programming SAC")
```

### 8.2.3.2 Error Codes Returned

[Table 98](#) lists the possible error codes returned with the WP^DDBR API:

**Table 98: WP^DDBR API—Error Codes Returned**

Code	Description
<a href="#">200</a>	Invalid field.
<a href="#">202</a>	Invalid parameter.
<a href="#">309</a>	Multiple field. Invalid file and IENS.
<a href="#">401</a>	Data Dictionary reference for file and field not valid.
<a href="#">501</a>	Extended reference invalid.
<a href="#">510</a>	Invalid type in data dictionary.
<a href="#">601</a>	Record entry does not exist.
<a href="#">602</a>	Record unavailable.
<a href="#">842</a>	Device/Terminal type set up issues.

### 8.2.3.3 Details and Features

#### 8.2.3.3.1 Switch Function

Switch allows the user to view more than one document. When using the Switch (<PF1>S) function in the Browser to select other VA FileMan WORD-PROCESSING fields, it is important to note that browsing is done directly on the actual record text. Users can only access WORD-PROCESSING fields in VA FileMan files for which they have Read access.

#### 8.2.3.3.2 Setting Tab Stops

This sets up the **TAB** with stops at every tenth column.

```
F I=10:10:100 S TAB(I)=" "
  
TAB(10)=" "
TAB(20)=" "
TAB(30)=" "
.
.
.
TAB(90)=" "
TAB(100)=" "
```

#### 8.2.3.3.3 Margin Note

Browser always begins at Column 1.



**REF:** For additional information about Browser error messages, see the [“How Information Is Returned”](#) and [“Contents of Arrays”](#) sections.

## 8.2.4 DOCLIST^DDBR(): View and Navigate Multiple Documents in an Array Using the Browser

The DOCLIST^DDBR API allows passing more than one document to the Browser facility. It enables the user to use the Browser to navigate through multiple documents stored in sequential local or global arrays.

A list of documents is passed by value as an array root. The array is subscripted by the document title and *must* be set equal to the document's location, in a closed root format. The Browser automatically builds the "Current List" and displays the first document to the screen. When you select the "S"witch function to switch to another document, the rest of the documents are presented as a "Current List." A flag is also available to "R"estrict selection to the "Current List" and prevent selecting VA FileMan WORD-PROCESSING fields in other files.

### Format

```
DOCLIST^DDBR(source_array[, flags][, top][, bottom])
```

### Input Parameters

source\_array: (Required) Source array in a closed root format, passed by value that is subscripted by document titles and set to the source array of the document in a closed root format.

flags: (Optional) Flags to control processing:

**R**—Restrict Switching to other documents *not* in current list. Otherwise, Switch (<PF1>S) function is active and users can look at other VA FileMan WORD-PROCESSING field entries.



**REF:** See the "[Switch Function](#)" in the "[Details and Features](#)" section.

top: (Optional) A number representing the location of the Title Bar of the Browser screen.

bottom: (Optional) A number representing the location of the Status Bar of the Browser screen.

### Output

A successful call enables the user to employ VA FileMan's Browser to view and navigate through multiple documents stored in a sequential local or global array.

### 8.2.4.1 Example

In this example there are three documents.

Document 1, in ^TMP(\$J,"DOC",1), looks like [Figure 291](#):

**Figure 291: DOCLIST^DDBR API—Example: Sample Document in ^TMP**

```

^TMP($J,"DOC",1,1)=Line 1 Document 1
^TMP($J,"DOC",1,2)=Line 2 Document 1
.
.
.
^TMP($J,"DOC",2,1)=Line 1 Document 2
^TMP($J,"DOC",2,2)=Line 2 Document 2
.
.
.
^TMP($J,"DOC",3,1)=Line 1 Document 3
^TMP($J,"DOC",3,2)=Line 2 Document 3
.
.
.

```

Building the document list array looks like [Figure 292](#):

**Figure 292: DOCLIST^DDBR API—Example: Input to Build the Document List Array**

```

>S ^TMP($J,"LIST","DOCUMENT 1")=^^TMP($J,"DOC",1)
>S ^TMP($J,"LIST","DOCUMENT 2")=^^TMP($J,"DOC",2)
>S ^TMP($J,"LIST","DOCUMENT 3")=^^TMP($J,"DOC",3)

```

Making a procedure call with switching restricted to only this list looks like [Figure 293](#):

**Figure 293: DOCLIST^DDBR API—Example: Input Making a Procedure Call with Switching Restricted to Only this List**

```

>D DOCLIST^DDBR(^^TMP($J,"LIST"),"R")

```

### 8.2.4.2 Error Codes Returned

[Table 99](#) lists the possible error codes returned with the DOCLIST^DDBR API:

**Table 99: DOCLIST^DDBR API—Error Codes Returned**

Code	Description
<a href="#">200</a>	Invalid field.
<a href="#">202</a>	Invalid parameter.
<a href="#">309</a>	Multiple field. Invalid file and IENS.
<a href="#">401</a>	Data Dictionary reference for file and field not valid.
<a href="#">501</a>	Extended reference invalid.
<a href="#">510</a>	Invalid type in data dictionary.
<a href="#">601</a>	Record entry does not exist.

Code	Description
<a href="#">602</a>	Record unavailable.
<a href="#">842</a>	Device/Terminal type set up issues.



**REF:** For additional information about Browser error messages, see the “[How Information Is Returned](#)” and “[Contents of Arrays](#)” sections.

### 8.2.4.3 Details and Features

#### 8.2.4.3.1 Switch Function

Switch allows the user to view more than one document. When using the Switch (<PF1>S) function in the Browser to select other VA FileMan WORD-PROCESSING fields, it is important to note that browsing is done directly on the actual record text. Users can only access WORD-PROCESSING fields in VA FileMan files to which they have Read access.

## 8.2.5 \$\$TEST^DDBRT: Verify Monitor Supports Browser

The \$\$TEST^DDBRT extrinsic function determines if the monitor being used can support a scroll region and reverse index. The device *must* have scroll region and reverse index capabilities in order to use the Browser. It returns:

- **1 (true)**—Monitor supports the needed functionality to use the Browser.
- **0 (false)**—Monitor does *not* support the needed functionality to use the Browser.

### Format

```
$$TEST^DDBRT
```

### Input Parameters

None.

### Output

Returns:

- 1—If true
- 0—If false.

#### 8.2.5.1 Example

Figure 294: \$\$TEST^DDBRT API—Example: Input and Output

```
>W $$TEST^DDBRT
1
```

#### 8.2.5.2 Error Codes Returned

None.

## 8.2.6 CLOSE^DDBRZIS: Rewind File and Copy Text to Global

The CLOSE^DDBRZIS API executes the Kernel's \$\$REWIND^%ZISC extrinsic function, to rewind the file and copies the text from the host file into a scratch global. It is used when setting up the Browser as a device on a system running Kernel 8.0 or greater. The call is set up in the CLOSE EXECUTE field of the TERMINAL TYPE (#3.2) file.



**REF:** For operating system information, if any, to be included with this call or the \$\$REWIND^%ZISC API, see the *Kernel 8.0 & Kernel Toolkit 7.3 Developer's Guide*.

### Format

CLOSE^DDBRZIS

### Input Parameters

None.

### Output

None.

#### 8.2.6.1 Error Codes Returned

A message is displayed if the rewinding of the file fails.



**NOTE:** Kernel 8.0 or greater is required.



**REF:** See also the [OPEN^DDBRZIS](#) and [POST^DDBRZIS](#) APIs.

## 8.2.7 OPEN^DDBRZIS: Capture Text in Browser Title

The OPEN^DDBRZIS API captures the text used in the Browser's title. It is used when setting up the Browser as a device on a system running Kernel 8.0 or greater. The call is set up in the OPEN EXECUTE field of the TERMINAL TYPE (#3.2) file.



**REF:** For operating system information, if any, to be included with this call, see the *Kernel 8.0 & Kernel Toolkit 7.3 Developer's Guide*.

### Format

OPEN^DDBRZIS

### Input Parameters

None.

### Output

None.

#### 8.2.7.1 Error Codes Returned

None.



**NOTE:** Kernel 8.0 or greater is required.



**REF:** See also the [CLOSE^DDBRZIS](#) and [POST^DDBRZIS](#) APIs.



## 8.2.8 POST^DDBRZIS: Initialize Browser to Display Text

The POST^DDBRZIS API initializes the Browser to display the text sent to the device. It is used when setting up the Browser as a device on a system running Kernel 8.0 or greater. The call is set up in the POST-CLOSE EXECUTE field of the DEVICE (#3.5) file.



**REF:** For operating system information, if any, to be included with this call, see the *Kernel 8.0 & Kernel Toolkit 7.3 Developer's Guide*.

### Format

POST^DDBRZIS

### Input Parameters

None.

### Output

None.

### 8.2.8.1 Error Codes Returned

None.



**NOTE:** Kernel 8.0 or greater is required.



**REF:** See also the [OPEN^DDBRZIS](#) and [CLOSE^DDBRZIS](#) APIs.

## 9 Coordinated Universal Time (UTC) API

### 9.1 Introduction

The Coordinated Universal Time (UTC) API converts a VA FileMan date/time into Greenwich Mean Time (GMT) with a time zone offset based on various input values entered by the user or the default institution in the **DUZ(2)** variable.

### 9.2 Application Programming Interfaces (APIs)

#### 9.2.1 \$\$UTC^DIUTC(): Return GMT in VA FileMan Internal Format with Time Zone Offset

The \$\$UTC^DIUTC API returns the Greenwich Mean Time (GMT) represented in standard VA FileMan internal date/time format with an internal three-digit time zone offset appended to the end. The calculation for the internal offset is:

1. Convert the external offset to minutes.
2. Divide value from Step 1 by 5.
3. Add value from Step 2 to 500.

For example:

-07:00 = -420 minutes, divided by 5 = -84, and added to 500 = 416

There may be other output variables based on the value of the **extended\_output\_flag** input parameter. The details for the other output values are documented in the “[Output](#)” section.

To determine the offset, the API needs to have the **timezone** and **country** input parameters. These values are determined using the following algorithm:

- If no optional input parameters are passed in, then the user's **DUZ(2)** variable is used to determine the user's default institution within the INSTITUTION (#4) file; where the TIMEZONE (#801) and COUNTRY (#802) fields are located.
- If only the **institution** input parameter is passed in, the time zone and country are determined by fields in the INSTITUTION (#4) file.
- If the **timezone** and **country** input parameters are passed in, the offset is determined from the WORLD TIMEZONE (#1.71) file.

The following errors are returned based on the evaluation of the input parameters:

- If the **timezone** and **country** parameters *cannot* be determined by any of the methods above, an error message is returned.
- If the **timezone** parameter is passed into the API but the **country** parameter is not, an error message is returned.
- If the **country** parameter is passed into the API but the **timezone** parameter is not, an error message is returned.
- If the **institution** parameter is passed in with either the **timezone** or **country** parameter, or both, an error message is returned.
- Once the **timezone** and **country** input parameters are determined, they are validated for consistency. An error message is returned if they are inconsistent.

For example: if the user passes in **timezone** = "Australian Eastern Time" and **country** = "Mexico", the \$\$UTC^DIUTC API returns an error message.

## Format

```
$$UTC^DIUTC(fm_datetime[, timezone][, institution][, country][, extended_output_flag])
```

## Input Parameters

**fm\_datetime:** (Required) Standard internal or external VA FileMan DateTime (e.g., NOW, T@12A). The Time portion of the input is required.



**NOTE:** The **NOW** input parameter is based on the current system time. If **NOW** is passed in with a **timezone** and **country** input parameter that is different than the system's time zone and country, inconsistent output may occur.

**timezone:** (Optional) Can be either of the following:

- Pointer to the WORLD TIMEZONES (#1.71) file.
- Value from the NAME (#.01) field if the WORLD TIMEZONES (#1.71) file (e.g., EASTERN).

**institution:** (Optional) Pointer to the INSTITUTION (#4) file.

**country:** (Optional) Can be either of the following:

- Pointer to the COUNTRY CODE (#779.004) file.
- Valid entry from the uppercase DESCRIPTION (#2) field of the COUNTRY CODE (#779.004) file.

**extended\_output\_flag:** (Optional) This parameter is an indicator of whether to do either of the following:

- Return the default output (GMT+offset in internal format).
- Include any extended return values.

If the **extended\_output\_flag** parameter is set to:

- **Null or Missing**—Only the default value is outputted.
- **1**—Additional values are returned as documented in the [“Output”](#) section.

## Output

The function can have two different outputs depending on the value of the **extended\_input\_flag** input parameter. If the **extended\_output\_flag** is set to:

- **Null or Missing**—Default output (GMT+offset in internal format) is returned.
- **1**—Output is multiple caret- (^) delimited pieces:
  - Piece 1: GMT+offset in internal format (e.g, 3160105.080715416)
  - Piece 2: GMT+offset in external format [e.g., JAN 5,2016@08:07:15 (UTC-7:00)]
  - Piece 3: Offset in external format (e.g., -7:00)
  - Piece 4: Time zone (e.g., EASTERN STANDARD TIME, ESTONIA STANDARD TIME)
  - Piece 5: Country Name (e.g., UNITED STATES, FRANCE)

Piece 6: Time zone abbreviation (e.g., EST, PST)

Piece 7: Timeframe (e.g., DAYTLIGHT, STANDARD, SUMMER)

Piece 8: Institution Name from the INSTITUTION (#4) file (e.g., CHEYENNE VAMC).

This piece is set to null if **timezone** and **country** are passed in as input parameters.

## 9.2.1.1 Examples

### 9.2.1.1.1 Example 1

The default output **DUZ(2)** variable is used, as shown in [Figure 295](#):

**Figure 295: \$\$UTC^DIUTC API—Example 1: Input and Output**

```
>W $$UTC^DIUTC(3160816.120016)
3160816.160016452
```

### 9.2.1.1.2 Example 2

The extended output **DUZ(2)** variable is used, as shown in [Figure 296](#):

**Figure 296: \$\$UTC^DIUTC API—Example 2: Input and Output**

```
>W $$UTC^DIUTC("T+1@11",,,,1)
3160811.150000452^AUG 11, 2016@15:00:00 (UTC-04:00)^-04:00^EASTERN^UNITED
STATES^EDT^DAYLIGHT SAVINGS^SOFTWARE SERVICE
```

### 9.2.1.1.3 Example 3

The time zone and country are passed in, as shown in [Figure 297](#):

**Figure 297: \$\$UTC^DIUTC API—Example 3: Input and Output**

```
>W $$UTC^DIUTC("NOW","EASTERN",,"UNITED STATES",1)
3160815.133449452^AUG 15, 2016@13:34:49 (UTC-04:00)^-04:00^EASTERN^UNITED STATES
^EDT^DAYLIGHT SAVINGS^
```

### 9.2.1.1.4 Example 4

The time zone and country are passed in and extended output, as shown in [Figure 298](#):

**Figure 298: \$\$UTC^DIUTC API—Example 4: Input and Output**

```
>W $$UTC^DIUTC("2/1/16@1500","CENTRAL",,"UNITED STATES",1)
3160201.210000428^FEB 01, 2016@21:00:00 (UTC-06:00)^-06:00^CENTRAL^UNITED STATES
^CST^STANDARD^
```

### 9.2.1.1.5 Example 5

The institution is passed in and extended output, as shown in [Figure 299](#):

**Figure 299: \$\$UTC^DIUTC API—Example 5: Input and Output**

```
>W $$UTC^DIUTC("Jan 15, 2016@11",,,1,,1)
3160115.160000440^JAN 15, 2016@16:00:00 (UTC-05:00)^-05:00^EASTERN^UNITED STATES
^EST^STANDARD^SOFTWARE SERVICE
```

### 9.2.1.2 Error Messages Returned

[Table 100](#) lists the possible error messages returned with the \$\$UTC^DIUTC API:

**Table 100: \$\$UTC^DIUTC API—Error Messages Returned**

Description
Date/Time parameter is missing.
Institution parameter cannot include Country or Timezone parameter.
Timezone parameter must include Country parameter.
Country parameter must include Timezone parameter.
Extended parameter must be NULL or a 1 for extended output.
Cannot determine Country and Timezone from the Institution.
Cannot determine User location.
Cannot determine Country and Timezone from User location.
Invalid Timezone.
Invalid Country.
Mismatch of Country and Timezone.



**NOTE:** All of the error messages returned from the \$\$UTC^DIUTC API are preceded by a: **-1^**. For example, “**-1^Invalid Country**”.

# 10 Data Access Control (DAC) API

## 10.1 Introduction

The Data Access Control (DAC) utility, released with VA FileMan Patch DI\*22.2\*8, is based upon the XACML (eXtensible Access Control Markup Language) standard, an extension of XML. XACML assumes an attribute-based rule structure that can permit or deny a user access to a resource (e.g., a record in a file). It uses pre-defined target attribute values to match appropriate policies to the action being taken. Policies are made up of rules that can be combined as needed. This allows you to create simple or very complex access policies.



**REF:** For more information on the Data Access Control (DAC) utility and setting up policies, which *must* be in place before calling the \$\$CANDO^DIAC1 API, see the *VA FileMan 22.2; Patch DI\*22.2\*8 Data Access Control (DAC) User Guide*.

## 10.2 Application Programming Interface (API)

### 10.2.1 \$\$CANDO^DIAC1(): Policy Evaluation

Once a policy has been created and tested, it is ready to be used by the new VA FileMan Web service or within an application's own code. The \$\$CANDO^DIAC1 API evaluates a policy to determine if the action being attempted is permitted.

If a matching entry exists in the APPLICATION ACTION (#1.61) file for the requested action and specified file or sub-file, its policy is evaluated to determine the user's authorization to access the file and/or record. Policy rules are evaluated in sequence, and processing continues until the stop criteria for the policy is met.

#### Format

```
$$CANDO^DIAC1(file,iens,action[,user][,.value][,.fields][,msg_root][,err_root])
```

#### Input Parameters

- file:** (Required) A VistA file number or sub-file number.
- iens:** (Required/Optional) Standard IENS string indicating internal entry numbers. It is required if evaluating an action on an existing record.
- action:** (Required) The API name of the action to be taken on the record; the **file** and **action** parameters should identify an entry in the APPLICATION ACTION (#1.61) file.
- user:** (Optional) Pointer to the NEW PERSON (#200) file; defaults to the current value of **DUZ** if *not* defined.
- value(name):** (Optional) Array of additional attribute values to use when evaluating policies, passed by reference in the form:

```
VALUE("name") = "value"
```

The name-value pairs could match target attributes in the policy for supplementing the results of the ATTRIBUTE FUNCTION, or simply be additional values used by other functions or messages.



**NOTE:** The ATTRIBUTE FUNCTION (#.04) field of the POLICY (#1.6) file points to the TYPE (#.03) field of the POLICY (#1.62) file.

- .fields:** (Optional) Local variable that receives output from the call:
- If the AVAILABLE FIELDS (#5) field of the POLICY (1.6) file have been defined for the application action and its policy returns a permit result, that field string is be returned.
  - If the AVAILABLE FIELDS (#5) field of the POLICY (1.6) file have been defined for the policy or rule that determined the result, that string takes precedence over the action's and be returned instead.
  - The ADDITIONAL FIELDS (#5.1) field of the POLICY (1.6) file can also be returned here, as an array of the same name subscripted by the file or sub-file number.



**NOTE:** The **.fields** parameter is passed by reference, which is indicated by the dot (.) in front of the name in the parameter list. Every parameter is passed using variables, but if it's passed by reference then whatever happens to the variable inside the call also happens to the variable in the calling program. (That is *not* the case with normal parameter passing, without the leading dot.) The **fields** variable is KILLED at the beginning of each call.

**msg\_root:** (Optional) Closed root into which any relevant advice messages is returned. If this parameter is *not* passed, the array is put into nodes descendant from ^TMP("DIMSG", \$J).

**err\_root:** (Optional) Closed root into which the error messages are returned. If this parameter is *not* passed, the array is put into nodes descendant from ^TMP("DIERR", \$J).

## Output

This Boolean extrinsic function returns the following:

- **1**—If authorization is permitted (Permit).
- **0**—If authorization is denied (Deny).
- **Null**—If authorization *cannot* be determined (i.e., no policies exist in the POLICY [#1.6] file that apply).
- **-1**—Error.

Advice messages can be returned for either a Permit or Deny result. Available Fields are only returned on a Permit.

### 10.2.1.1 Examples

#### 10.2.1.1.1 Example 1

To check the current user's authorization to view a chemistry result using our sample Lab policy, a simple call could be made to the API, as shown in [Figure 300](#):

**Figure 300: \$\$CANDO^DIAC1—Example 1: Input and Output**

```
>S OK=$$CANDO^DIAC1(63.04,"7019779.8679,12345","read") W !,OK
1
```

### 10.2.1.1.2 Example 2

A different user may *not* be permitted to view the result, and the message array can show why, as shown in [Figure 301](#):

**Figure 301: \$\$CANDO^DIAC1—Example 2: Input and Output**

```
>S OK=$$CANDO^DIAC1(63.04,"7019779.8679,12345","read",1000406,,,"ZZMSG")
>W OK,! ZW ZZMSG
0
ZZMSG(1)="FMUSER,ONE is not authorized to view preliminary results."
ZZMSG(2)="Please contact Lab staff."
```

### 10.2.1.1.3 Example 3

An incomplete call to the API returns an error, as shown in [Figure 302](#):

**Figure 302: \$\$CANDO^DIAC1—Example 3: Input and Output**

```
>S OK=$$CANDO^DIAC1(63.04,"7019779.8679,12345",,,,,,"ZZMSG","ZZERR")
>W OK,! ZW ZZERR
-1
ZZERR(1)="The input parameter that identifies the ACTION is missing or invalid."
```



# 11 Import and Export Tools

## 11.1 Introduction

If you want to use *non-M* applications (e.g., a PC-based application like Microsoft® Excel) to manipulate data stored in a VA FileMan file, then you need a way to exchange VA FileMan data with your application. VA FileMan provides the interactive Import and Export Tools for these purposes. These tools are made available to users through interactive options.

VA FileMan 22.2 provides APIs for both the Import Tool (FILE^DDMP) and the Export Tool (EXPORT^DDXP), so that you can incorporate their functionality into your applications.



**REF:** For more information about the Import and Export Tools, see the “Import and Export Tools” section in the *VA FileMan Advanced User Manual*.

## 11.2 Application Programming Interfaces (APIs)

### 11.2.1 FILE^DDMP(): Data Import

The FILE^DDMP API imports data from ASCII host files into VA FileMan file entries. Each record (line of data) in the host file is stored as a new entry in a specified VA FileMan file.



**REF:** For additional information about the Import Tool, see the “Import and Export Tools” section in the *VA FileMan Advanced User Manual*.

#### Format

```
FILE^DDMP([file][,[.]fields][,.control],.source,[.]format)
```

#### Input Parameters

**file:** (Optional) File number into which imported data is filed. Do *not* pass this parameter if the import file specifies the destination VA FileMan file and fields. The file *must* already exist.

**[.]fields:** (Optional) Array specifying the fields into which imported data is filed. The array can either:

- Name an IMPORT template.

Or:

- Directly specify the fields for import.

Do *not* pass this parameter if the import file specifies the destination VA FileMan file and fields.

If you have the import fields stored in an IMPORT template, simply set the top-level, unsubscripted node to the name of the template, surrounded by [brackets].

If you are directly specifying fields in this array, set the top-level, unsubscripted node in the **FIELDS** array to the list of destination field numbers at the top-level of the file. Separate each field number with a semicolon. The list of field numbers should match the order of the corresponding data pieces in each import file record.

For any field number that identifies a Multiple, include the top-level field number of the Multiple in the top-level node of the **FIELDS** array. Then, set an additional node in the **FIELDS** array for the Multiple, subscripted by the data dictionary subfile number of the Multiple. Set this additional node to the list of subfield numbers in the Multiple into which to have data filed, separated by semicolons. The order of subfield numbers in this node should match the order of the corresponding data pieces for the Multiple in the import file record.

For subfiles within subfiles, repeat this process of identifying the top-level field number of the Multiple in the appropriate **FIELDS** node (one data dictionary level above that of the Multiple). Then add an additional node subscripted by data dictionary number identifying the fields in the subfile into which data is to be filed.

You can add more than one subentry for the same subfile.



**REF:** For more information, see “[Importing into Subfiles](#)” in the “[Details and Features](#)” section.

If the import is based on fixed length (rather than character-delimited) data, follow each field’s number with the length of the data for that field enclosed in square brackets. For example:

```
" .01[30]; .02[30]; .03[10]"
```

.control:

(Optional) Pass this array by reference. You can control the behavior of FILE^DDMP by setting the following nodes in the **CONTROL** array:

- **CONTROL(“FLAGS”)**—(Optional) Concatenated string of character flags to control processing of the import:
  - **E**—External values are contained in the import file. Convert the values to VA FileMan internal format and verify during import. If the **E** flag is *not* present, data is assumed to be in VA FileMan internal format and is *not* verified.
  - **F**—Import File contains identity of destination VA FileMan file and fields. If the **F** flag is *not* present, the **file** and **fields** parameters are required and *must* contain file and field information.
- **CONTROL(“MSGS”)**—(Optional) Set to the root of an array (local or global) into which error messages should be returned. If a value is *not* passed, messages are returned in nodes descendent from ^TMP(“DIERR”, \$J).
- **CONTROL(“MAXERR”)**—(Optional) Set to the number of errors that may be encountered before aborting the import.  
Default is *not* to abort.
- **CONTROL(“IOP”)**—(Optional) Set to the name of the device (as stored in the DEVICE [#3.5] file) on which to print the Import Report. This pre-selects the output device. You can also set **CONTROL(“IOP”)** to match any of the additional formats for the **IOP** input variable recognized by the ^%ZIS API.



**REF:** For more information on `^%ZIS` and **IOP**, see the Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide.

Default is to ask the user for output device.

- **CONTROL(“QTIME”)**—(Optional) Set to the time for queuing the data filing and subsequent printing of the Import Results report. This pre-selects the time for queuing. The time can be in any format that [^%DT](#) recognizes.

Default is to ask the user whether or not to queue and for the queuing time.

`.source:` (Required) An array that identifies the import file. Pass this array by reference:

- **SOURCE(“FILE”)**—(Required) Set this node to the import file name.
- **SOURCE(“PATH”)**—(Optional) Path or directory where the file can be found. If this node is *not* defined, the default path is used to locate the file.

`[.]format:` (Required) Specifies the format of the incoming data. You can either:

- Pass the name of a FOREIGN FORMAT (#.44) file entry in the top-level, unsubscripted node of this array.

Or:

- Set individual nodes in this array to define the import format (pass by reference).

If you set individual nodes in the array to define the format, you can set:

- **FORMAT(“FDELIM”)**—Set this node to the field delimiter used for the imported data, if a field delimiter is used.
- **FORMAT(“FIXED”)**—Set this node to **YES** if the incoming data is in fixed-length format. If *not* set to **YES**, the default format is field-delimited.
- **FORMAT(“QUOTED”)**—Set this node to **YES**, if you would like VA FileMan to ignore the field delimiter in any quoted strings in the incoming data.

## Output

Error messages and information supplied via [EN^DDIOL](#) are returned in `^TMP` or in the array specified by `MSG_ROOT`. **DIERR** is defined if there was an error. Error messages are *not* returned for individual records whose import fails, however.

### 11.2.1.1 Example

In [Figure 303](#), the import file is PEOPLE2.CSV. The import file is in Microsoft® Excel (Comma) format, which means the data is comma-delimited. There is a corresponding entry in the FOREIGN FORMAT (#.44) file called “Excel (Comma)” describing the Excel (Comma) format.

The code in [Figure 303](#) calls FILE^DDMP to import data from PEOPLE2.CSV:

**Figure 303: FILE^DDMP API—Example: Input Code to Import Data**

```
S FILE=16100
S CONTROL("MSG")="MYMSG"
S CONTROL("FLAG")="E"
S FIELDS=".01;14;14"
S FIELDS(16100.014)=".01;1"
S SOURCE("FILE")="PEOPLE2.CSV"
S SOURCE("PATH")="VA6$:[FMPERSON]"
D FILE^DDMP(FILE,.FIELDS,.CONTROL,.SOURCE,"EXCEL(COMMA)")
```

The import data is in external format, so the call to FILE^DDMP uses the **E** flag. The data in the import file contains records of five comma-delimited values that are to be imported into (fictitious) File #16100, as specified in the FIELDS parameter:

- Data piece **1**: File as the **.01** field of File #16100.
- Data pieces **2** and **3**: File as first entry in Subfile #16100.014 (field #s **.01** and **1**).
- Data pieces **4** and **5**: File as second entry in Subfile #16100.014 (field #s **.01** and **1**).

If the data for this import were in fixed length format, the code to set the **FIELDS** array might look like this:

**Figure 304: FILE^DDMP API—Example: Input Code to Set the Array**

```
S FIELDS=".01[30];14;14"
S FIELDS(16100.014)=".01[30];1[25]"
```



**NOTE:** The field numbers that specify a Multiple at the top-level have no length associated with them.

### 11.2.1.2 Error Codes Returned

[Table 101](#) lists the possible error codes returned with the FILE^DDMP API:

**Table 101: FILE^DDMP API—Error Codes Returned**

Code	Description
<a href="#">202</a>	Incorrect parameter was passed.
<a href="#">312</a>	Required identifier is missing.
<a href="#">409</a>	File does not exist.
<a href="#">501</a>	Field does not exist.
<a href="#">520</a>	A word-processing field was specified.
<a href="#">525</a>	Multiple specified, but no fields in subfile chosen.

Code	Description
<a href="#">1810</a>	Data could not be moved into M environment.
<a href="#">1812</a>	No data found in host file.
<a href="#">1820</a>	Format could not be found in the Foreign Format file.
<a href="#">1821</a>	Inconsistencies in the format chosen.
<a href="#">1822</a>	Incorrect data length for a fixed length format.
<a href="#">1833</a>	Inconsistency involving the “F” flag.
<a href="#">1850</a>	Error in device selection or queuing setup.
<a href="#">1870</a>	The IMPORT template does not exist for the file.

### 11.2.1.3 Details and Features

#### 11.2.1.3.1 Data Formats

Data fields in the import file can be either character-delimited or fixed length. The method used should match the method described in the FOREIGN FORMAT (#.44) file entry whose name is passed to FILE^DDMP. Alternatively, you can specify these values directly in the FORMAT parameter and not reference a FOREIGN FORMAT File entry. The only fields from the FOREIGN FORMAT (#.44) file entry used during import are:

- FIELD DELIMITER
- RECORD LENGTH FIXED?
- QUOTE NON-NUMERIC FIELDS

#### 11.2.1.3.2 Required Fields

All required VA FileMan identifier fields for the destination file *must* have data filed into them from the import record:

- If a field defined as a required identifier is *not* a destination field, the import is *not* performed.
- If a record being filed has a null value for a required identifier, that record is *not* filed.

#### 11.2.1.3.3 Identifying Destination File and Fields in Import File

You can store the destination VA FileMan file and fields in the import file, rather than passing them to FILE^DDMP in the **file** and **fields** parameters. Use the **F** flag to indicate that file and field information is being sent in the import file.

To specify the file and fields in the import file, the first line of data in the import file *must* be:

```
FILE=filename
```

Do *not* leave any spaces between the literal tag “**FILE=**” and the name of the file involved. You can identify the file by file number rather than name, also.

The second line in the import file *must* contain a list of destination field names, in the order of the data pieces in each import file record. You can use field numbers rather than field names to identify the fields. For example, you might want to specify a field by number if its name contains punctuation characters.

If the import is delimited, the names should be separated by whatever the specified delimiter is:

```
NAME,ADDRESS
```

If the import is fixed length, the field names should be followed by the field length in [brackets], and then separated by a comma:

```
NAME[25],ADDRESS 1[20]
```

To specify a field in a subfile, show the complete path to the field using the format:

```
Multiple fieldname:fieldname
```

Specify as many Multiple field names as necessary (separated by colons) to indicate a complete path to the field being imported.

The third and subsequent lines of the import file should contain the data records to be filed.

[Figure 305](#) is a listing of an example import file containing destination field information:

**Figure 305: Sample Listing of an Import File**

```
FILE=DA RETURN CODES
DA RETURN STRING,TERMINAL TYPE STRING
[=7c,C-QVT103
[?1;0c,C-WYSE 75
[?1;2c,C-VT100
[?1;6c,C-VT100
```

#### 11.2.1.3.4 Importing into Subfiles

Each record (line of data) from an import file is always stored as a new record at the top-level of the destination VA FileMan file. However, you can populate more than one entry in a subfile descendent from the new entry, from a single import record.

To file more than one entry in a subfile, repeat the subfile's Multiple field number in the field string of the higher level file or subfile. Each import record *must* add the *same set of fields* to the subfile in question; however, as specified by the set of fields you list in the subfile's **FIELDS(subfile#)** node.

Also, new subentries need to be added to every subfile on a path to the lowest level subfile. Because of this, you *must* include fields for the **.01** field and all the required identifiers for every subfile as well as at the top-level of the file.

## 11.2.2 EXPORT^DDXP(): Data Export

The EXPORT^DDXP API exports data from VA FileMan files into ASCII host files. Each entry in a specified VA FileMan file is stored as a line of data in the host file.



**REF:** For additional information about the Export Tool, see the “Import and Export Tools” section in the *VA FileMan Advanced User Manual*.

### Format

```
EXPORT^DDXP(file,export_template[,delete_flag][,sort_template][,].[fr][,].[to],.dis
)[,].[distop][,iop][,dqtime]
```

### Input Parameters

file: (Required) File number from the file where the data to be exported is located.



**NOTE:** A special case occurs when exporting data from the AUDIT (#1.1) file. In this case, **file** then becomes:

**1.1^<file number of the audited file>**

For example, if the audited data is associated with the PATIENT (#2) file, then the string would look like:

**1.1^2**

export\_template: (Required) The name of the export template, *without* the surrounding brackets “[ ]”, that was created when the developer used the Create Export Template option [DDXP CREATE EXPORT TEMPLATE].

delete\_flag: (Optional) Indicates whether or not the export template should be deleted when exporting of the data is finished.

It has two possible values:

- **0 (zero)**—Do *not* delete the export template when the export has finished. This is the default.
- **1**—Delete the export template when the export has finished.

sort\_template: (Optional) The name of the sort template, *without* the surrounding brackets “[ ]”, that are used for file sorting. If this parameter is null, then the user sees the standard VA FileMan sort dialogue.

[.]fr: (Optional) The “START WITH:” values of the sort by fields. If **fr** is undefined, the user is asked the “START WITH:” question for each sort by field. If **fr** is defined, it consists of one or more comma pieces, where the piece position corresponds to the order of the sort field in the **BY** variable.

Passed by reference.

The details of this parameter are identical to those of the **FR** input variable of the Classic VA FileMan print routine [EN1^DIP](#). For additional information, see that description.

[.]to: (Optional) The “GO TO:” values of the sort by fields. Its characteristics correspond to the **FR** variable. If undefined, the user is asked the “GO TO:”

questions for each SORT BY field. If **to** is defined, it consists of one or more comma pieces.

Passed by reference.

The details of this parameter are identical to those of the **TO** input variable of the Classic VA FileMan print routine [EN1^DIP](#). For additional information, see that description.

**.dis:** (Optional) You can screen out certain entries so that they do *not* appear on the output by setting the optional array **DIS**. the first subscript in this array can be **0** (zero). This variable (as well as all the others) contains an executable line of M code that includes an **IF**-statement.

Passed by reference.

The details of this parameter are identical to those of the **DIS(0)** and **DIS(n)** input variables of the Classic VA FileMan print routine [EN1^DIP](#). For additional information, see that description.

**[.]distop:** (Optional) If Kernel is present, by default prints queued through the [EN1^DIP](#) call can be stopped by the user with a TaskMan option. However, if this parameter is set to **0**, users are *not* able to stop their queued prints.

Passed by reference.

The details of this parameter are identical to those of the **DISTOP** input variable of the Classic VA FileMan print routine [EN1^DIP](#). For additional information, see those descriptions.

**iop:** (Optional) EXPORT^DDXP calls the ^%ZIS API to determine to which device output should go. This requires user interaction; unless you pre-answer the device prompt. You can do this by setting **iop** equal to the name of the device (as it is stored in the DEVICE [#3.5] file) to which the output should be directed.

Passed by reference.

The details of this parameter are identical to those of the **IOP** input variable of the Classic VA FileMan print routine [EN1^DIP](#). For additional information, see that description.

**dqtime:** (Optional) If output is queued, this parameter contains the time for printing. You can set it equal to any value that [%DT](#) recognizes.

Passed by reference.

The details of this parameter are identical to those of the **DQTIME** input variable of the Classic VA FileMan print routine [EN1^DIP](#). For additional information, see that description.

## Output Parameters

None.

### 11.2.2.1 Examples

See examples below for ways to use EXPORT^DDMP.



**NOTE:** In all of these examples, the **delete\_flag** input parameter is null (i.e., **0** [zero]).



### 11.2.2.1.1 Example 1

In this example ([Figure 306](#)), no sort template is provided and the user is asked sort dialogue:

**Figure 306: EXPORT^DDXP API—Example 1: Input and Output**

```
>D EXPORT^DDXP(2,"ZZS0 SKIP TEST")  
  
SORT BY:  NAME// <Enter>  
START WITH NAME:  FIRST// <Enter>  
DEVICE:
```

### 11.2.2.1.2 Example 2

In this example ([Figure 307](#)), a sort template is provided:

**Figure 307: EXPORT^DDXP API—Example 2: Input and Output**

```
>D EXPORT^DDXP(2,"ZZS0 SKIP TEST",,"ZZS0 TEXPORT #1")  
  
*Previous selection: DATE ENTERED INTO FILE from Jan 1,1997 to Jun 4,1999  
START WITH DATE ENTERED INTO FILE: FIRST// 1/1/97 <Enter> (JAN 01, 1997)  
GO TO DATE ENTERED INTO FILE: LAST// T <Enter> (JUN 07, 1999)  
DEVICE:
```

### 11.2.2.1.3 Example 3

In this example ([Figure 308](#)), a sort template is provided and the **fr** and **to** input parameter values are supplied:

**Figure 308: EXPORT^DDXP API—Example 3: Input and Output**

```
S FR="1/1/97"  
S TO=DT  
D EXPORT^DDXP(2,"ZZS0 SKIP TEST",,"ZZS0 TEXPORT #1",FR,TO)  
DEVICE:
```

### 11.2.2.1.4 Example 4

This example shows the special case of the AUDIT (#1.1) file.

Because users can export information from the AUDIT (#1.1) file, a special case has been created. All parameters that are to be passed remain the same as above, *except* for the **file** parameter. In this special case, the format is as shown in [Figure 309](#):

**Figure 309: EXPORT^DDXP API—Example 4: Input for Special Case with the AUDIT (#1.1) File**

```
FILE "1.1^<file number of audited file>"
```

[Figure 310](#) is an example:

**Figure 310: EXPORT^DDXP API—Example 1: Input and Output**

```
>D EXPORT^DDXP("1.1^16200","ZZSO",,"ZZSO AUDIT")

Previous selection: DATE/TIME RECORDED from Jan 1,1997 to Dec 31,1997@24:00 START
WITH DATE/TIME RECORDED: FIRST// 1/1/97 <Enter> (JAN 01, 1997)
GO TO DATE/TIME RECORDED: LAST// 12/31/97 <Enter> (DEC 31, 1997@24:00)
DEVICE:
```

### 11.2.2.1.5 Example 5

This example shows a sample sort template, export template, and routine.

In [Figure 311](#), you want to use Microsoft Word Mail Merge to send a brochure to the new patients who visited the Medical Center in the previous month. For purposes of illustration, you are going to assume the month in question was March of 2000.

**Figure 311: EXPORT^DDXP API—Example 5: Sample Sort Template Used**

```
NAME: ZZSO NEW PATIENTS// <Enter>
READ ACCESS: @// <Enter>
WRITE ACCESS: @// <Enter>
SORT BY: ]NAME// <Enter>
* Previous selection: NAME not null
START WITH NAME: FIRST// <Enter>
WITHIN NAME, SORT BY: DATE ENTERED INTO FILE Replace <Enter>
* Previous selection: DATE ENTERED INTO FILE from Feb 1, 2000 to Feb 29,
2000
START WITH DATE ENTERED INTO FILE: FIRST// 3/1/00 <Enter> (MAR 01, 2000)
GO TO DATE ENTERED INTO FILE: LAST// 3/31/00 <Enter> (MAR 31, 2000)
WITHIN DATE ENTERED INTO FILE, SORT BY: <Enter>
STORE IN 'SORT' TEMPLATE: ZZSO NEW PATIENTS <Enter> (Jun 17, 1999@05:14)
User #9152 File #2 SORT

DATA ALREADY STORED THERE....OK TO PURGE? NO// YES
DESCRIPTION:
 1>Get previous month's New Patients for mass marketing mailing.
EDIT Option: <Enter>

SHOULD TEMPLATE USER BE ASKED 'FROM'-'TO' RANGE FOR 'DATE ENTERED INTO FILE'?
NO// YES
```

Figure 312: EXPORT^DDXP API—Example 5: Export Template Used

```
NAME: ZZSO PATIENT ADDRESS X
DATE CREATED: JUN 17, 1999@08:26
READ ACCESS: @
USER #: 9152
DATE LAST USED: MAR 01, 2000
FIELD ORDER: 1
FIELD ORDER: 2
FIELD ORDER: 3
FIELD ORDER: 4
FIELD ORDER: 5
EXPORT FORMAT: EXCEL (COMMA)
HEADER (c): @@
FIRST PRINT FIELD: W $(34)//
THEN PRINT FIELD: NAME;X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: W $(44);X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: STREET ADDRESS [LINE 1];X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: W $(44);X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: CITY;X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: W $(44);X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: STATE;X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: W $(44);X//
HEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: ZIP CODE;X//
THEN PRINT FIELD: W $(34);X//
THEN PRINT FIELD: W $(44);X//
COMPILED (c): NO
FILE: PATIENT
WRITE ACCESS: @
TEMPLATE TYPE: EXPORT
DATA TYPE: FREE TEXT
DATA TYPE: FREE TEXT
DATA TYPE: FREE TEXT
DATA TYPE: FREE TEXT
DATA TYPE: FREE TEXT
SUB-HEADER SUPPRESSED: YES
```

**Figure 313: EXPORT^DDXP API—Example 5: Routine and Output**

```
ZZSONPAD --
;SFISC/SO-Sample Export API Usage ;7:18 AM 1 APR 2000
;1.0
N %DT
S %DT="AEPX"
S %DT("A")="Enter Beginning of previous Month: "
D ^%DT
I Y<1 Q
S FR=","_$(Y,".")
S %DT="AEPX"
S %DT("A")="Enter End of previous Month: "
D ^%DT
I Y<1 Q
S TO=","_$(Y,".")
K %DT
D EXPORT^DDXP(2,"ZZSO PATIENT ADDRESS X",,"ZZSO NEW PATIENTS",FR,T
O)
Q FM22 >D ^ZZSONPAD

Enter Beginning of previous Month: 3/1/00 <Enter> (MAR 01, 2000) Enter End of
previous Month: 3/31/00 <Enter> (MAR 31, 2000) DEVICE: <Enter> Telnet terminal
"FMPATIENT,FIVE","111 FIVE BLVD.,"LAS VEGAS","NEVADA","89101",
"FMPATIENT,FOUR","301 FOUR St.,"San Francisco","CALIFORNIA","99999",
"FMPATIENT,ONE","123 ONE ST.,"SAN FRANCISCO","CALIFORNIA","99999",
"FMPATIENT,SEVEN","234 SEVEN","SAN DIEGO","CALIFORNIA","99999",
"FMPATIENT,SIX","234 SIX ST.,"SAN FRANCISCO","CALIFORNIA","99999",
"FMPATIENT,THREE","132 THREE ST","SAN FRANCISCO","CALIFORNIA","99999",
"FMPATIENT,TWO","123 TWO ST","SAN FRANCISCO","CALIFORNIA","99999",
```

# 12 Extract Tool

## 12.1 Introduction

The Extract Tool lets you move or copy records from one VA FileMan file to another; a typical use is to archive records. Two APIs are provided:

- [EN^DIAXU: Extract Data](#)
- [EXTRACT^DIAXU\(\): Extract Data](#) (preferred API to use for extracting data records)



**REF:** The extract tool can also be used interactively from a set of options; this is described in the “Extract Tool” section in the *VA FileMan Advanced User Manual*.

## 12.2 Application Programming Interfaces (APIs)

### 12.2.1 EN^DIAXU: Extract Data (Single Entry)

The EN^DIAXU API extracts data specified in the EXTRACT template for a single entry and moves that data to a destination file. The source entry can be deleted after the extract process is completed.

If you need to extract in batches (more than one entry), you should use the [EXTRACT^DIAXU](#) API instead.

#### Input Variables

- DIAXF: (Required) The number of the file that contains the source entry.
- DIAXT: (Required) The EXTRACT template name enclosed in brackets in the source file that contains specifications of data to be extracted.
- DIAXFE: (Required) Internal entry number of the source entry from which data is extracted.
- DIAXDEL: (Optional) This variable:
- **Defined**—Tells the program to delete the source entry.
  - **Not Defined**—The source entry is unchanged.

#### Output Variables (Successful Extracts)

If the extract process was completed and the data was *successfully* moved to the destination file, the following variables are returned:

DIAXDA: Internal entry number of entry created in the destination file.

In addition to **DIAXDA**, the following is returned:

```
^TMP("DIAXU", $J, "RESULT", DIAXF, DIAXFE) = DIAXDA
```

DIAXNTC: No longer returned. For batch processing of extracts, you should use the EXTRACT^DIAXU entry point instead of this one.

DIAXFE: No longer KILLED upon exit.

DIAXF: *Not* KILLED.

DIAXT: *Not KILLed.*

DIAXDEL: *Not KILLed.*

### 12.2.1.1 Output Variables (If an Error Occurs)

If an *error* occurs during the extract process, the following variables and global arrays are returned instead:

DIERR: Contains the following two ^-pieces of information:

- Number of errors generated during the call.
- Total number of lines of the error messages.

In addition, the following “**RESULT**”, “**ERR**” node is returned:

```
^TMP( "DIAXU" , $J , "RESULT" , "ERR" , file# , ien )
```

For example:

```
^TMP( "DIAXU" , $J , "RESULT" , "ERR" , 662001 , 5 )
```

No longer indicates the total number of errors encountered during the extract process.

(array in ^TMP): Error information is returned in ^TMP(“**DIERR**”, \$J), in the same format that error information is returned for DBS calls.



**REF:** For a complete description of this array, see the “[Database Server \(DBS\) API](#)” section.

DIAXDA: *Not defined.*

All Input Variables: *Left defined.*

### 12.2.1.2 Error Codes Returned

The EN^DIAXU API calls the following APIS:

- \$\$FIND1^DIC
- LIST^DIC
- UPDATE^DIE
- \$\$GET1^DIQ
- GETS^DIQ

Any errors returned by these APIs can also be returned by EN^DIAXU. In addition, [Table 102](#) lists the possible error codes that can be returned with the EN^DIAXU API:

**Table 102: EN^DIAXU—Error Codes Returned**

Code	Description
<a href="#">201</a>	An input variable is missing or invalid.
<a href="#">601</a>	The entry does not exist.

## 12.2.2 EXTRACT^DIAXU(): Extract Data (Multiple Entries)

The EXTRACT^DIAXU API is the preferred API for extracting data records. The principal features of this API for extracting data are:

- More than one record can be extracted in a call.
- Subrecords can be extracted as individual transactions. Previously, an entire record including all subrecords had to be extracted as a single entity.
- DBS-style error reporting is used.

Like the [EN^DIAXU](#) API, the EXTRACT^DIAXU API extracts data from the fields specified in the EXTRACT template and places that data in an entry in a destination file. You can optionally delete the source entry after the extract process is completed.

### Format

```
EXTRACT^DIAXU(file,source,extract_template,flags[,.screens][,.filing_level][,target_root][,msg_root])
```

### Input Parameters

file: (Required) File number of source file.

source: (Required) Can be one of the following two formats:

- IEN: The record number of a single record, at the top-level of the file, to extract.
- SEARCH template name: The name of a SEARCH template, in brackets, that contains SEARCH results (a list of record numbers). For example:

```
S SOURCE="[ TEMPLATE_NAME ]"
```

extract\_template: (Required) The name of the EXTRACT template, in brackets, containing what fields to move.

flags: (Optional) A string of characters to modify the behavior of the Extract Tool. Permissible characters in the string are:

**D**—Tells the extract tool to **Delete** source records if they were moved successfully. Deletion is only done for entire (top-level) records. Subrecords are *not* individually deleted, even if they are individually extracted.



**NOTE:** If the **source** parameter is set to a SEARCH template, and you include a **D** in the **flags** parameter, the record numbers of any successfully extracted records are removed from the list of record numbers in the SEARCH template. If an error is encountered, the source record is *not*

deleted and the record number is *not* removed from the list of record numbers in the SEARCH template.

.screens:

(Optional) Local array containing screens to apply to subrecords at various subrecord levels. The screens determine whether to move individual subrecords at a given level or not. The screens can be any valid M code that sets \$TEST to:

- **1**—Subrecord at a given level should be moved.
- **0**—Subrecord at a given level should *not* be moved.

Set up nodes in this array subscripted by **subfile#** for each subrecord level you want to screen.



**REF:** For a list of the variables you can reference and change in the screen, see the SCREEN parameter description in the [LIST^DIC](#) DBS call.

Example:

```
S MYARRAY(999.01)="I $P(^(),U,2)=""Y"" "
```

.filing\_level:

(Optional) Local array you can use to tell the Extract Tool to file subrecords as *individual* transactions, at one or more subfile levels. The default filing mode is to file an *entire* record, including all subrecords, as a single transaction.

You should consider using the **filing\_level** feature when extracting records with *many* subrecords at a given subfile level. This lets you restrict the scope of an extract transaction (every part of the transaction *must* succeed or the entire transaction fails) to individual subrecords rather than to a record *and* all of its subrecords.

For example, suppose the records you are extracting have one Multiple field in particular in which there can be a thousand or more subrecords for every record. The subfile level of this Multiple is a very good candidate to be filed individually:

- *Without* filing individually, failure to successfully extract any *one* of a record's thousand subrecords aborts the extract for the top-level record and *all* of its subrecords (no changes are filed).
- *With* filing individually, if any data in the subrecord causes an error, the subrecord is *not* extracted, but the extract for the top-level record and its other subrecords continue.

Another drawback of filing a record and a large number of subrecords as a single transaction is that a very large **FDA** array can be created; this can be resource intensive and could exhaust scratch storage space in ^TEMP.

To file subrecords at any given subfile level individually, set up an array with a node subscripted by **subfile#** and pass the array by reference as this parameter. You can set more than one subfile level to file individually, by passing one node for each subfile level in the array



Example:

```
S F_ARRAY(999.01)=""
```

**target\_root:** (Optional) Array that should receive the results generated during the Extract Tool process. This *must* be a closed array reference and can be either local or global. If you specify your own array for results, make sure it is empty before calling EXTRACT^DIAXU.

If you do *not* pass this parameter, the results are returned in ^TMP("DIAXU", \$J).

**msg\_root:** (Optional) Array that should receive error messages generated during the Extract Tool process. This *must* be a closed array reference and can be either local or global. If you specify your own array for error messages, be sure it is empty before calling EXTRACT^DIAXU.

If you do *not* pass this parameter, error messages are returned in ^TMP("DIERR", \$J).

### Output Variables and Parameters

**DIERR:** This variable is returned if an error condition occurred. It contains two ^-pieces of information:

- Number of errors generated during the call.
- Total number of lines of the error messages.

Associated error messages are stored, DBS-style, in **msg\_root**.

**target\_root:** One "RESULT" node is returned for each record extracted (or attempted to be extracted).

The format of the "RESULT" nodes for a *successful* extract is:

- The **target\_root** parameter passed:

```
TARGET_ROOT("RESULT", source_file, source_iem) =  
destination_file_iem
```

- No **target\_root** parameter passed:

```
^TMP("DIAXU", $J, "RESULT", source_file, source_iem) =  
destination_file_iem
```

The format of the “**RESULT**” nodes for an *unsuccessful* extract is:

- The **target\_root** parameter passed:

```
TARGET_ROOT("RESULT", "ERR", source_file, source_ien) =
error_list
```

- No **target\_root** parameter passed:

```
^TMP("DIAXU", $J, "RESULT", "ERR", source_file,
source_ien) = error_list
```

The error list for an unsuccessful extract contains the error numbers, each followed by a semicolon. For example, if a “**RESULT**” node is:

```
TARGET_ROOT("RESULT", "ERR", 16151, 6)=1;2;
```

This means that errors **1** and **2** are caused by the extract of record **6**. Errors one and two are returned in the **MSG\_ROOT** array.

If the **filing\_level** parameter is being used such that subrecords are being filed individually at some subfile levels, results (successful or unsuccessful) are returned for *each* individual subrecord extracted, in the same format as above, except that:

- “source\_file” is the subfile number
- “source\_ien” is the IENS string for the subfile entry
- “destination\_file\_ien” is the IENS string for the destination subfile entry

If one or more subrecords extracted *unsuccessfully* using the **filing\_level** parameter, a single error (1300) is returned for the top-level record in a “**RESULT**”, “**ERR**” node, but this does *not* abort the extract. So, in this case a top-level extracted record can have both a “**RESULT**” node (indicating success at the top-level and the destination file IEN) and a “**RESULT**”, “**ERR**” node (indicating errors during subfile filing).

If the extract fails for any subrecord at some subfile level *not* filed individually via the **filing\_level** parameter, a “**RESULT**”, “**ERR**” node is returned for the top-level record, and the extract for the top-level record aborts.

msg\_root:

Error messages are returned in **MSG\_ROOT**(“**DIERR**”) (if the **msg\_root** input parameter is passed) or **^TMP**(“**DIERR**”,**\$J**) (if no array is specified). Errors are returned in DBS-style format.



**REF:** For more information on the format of DBS-style error arrays, see the “[DIERR Array](#)” section in the “[Contents of Arrays](#)” section in the “[How the Database Server \(DBS\) Communicates](#)” section.

## 12.2.2.1 Examples

### 12.2.2.1.1 Example 1

In this example, `EXTRACT^DIAXU` is called with a `SEARCH` template containing a list of three record numbers to extract. Two records (#7 and #32) are moved successfully and one record (#34) fails to be moved. As a result of the error, the **DIERR** variable would be returned (set to "1^1"). The call might look like:

**Figure 314: EXTRACT^DIAXU API—Example 1: Input**

```
>D EXTRACT^DIAXU(16151,"[EXTRACT SEARCH]","[EXTRACT TEMPLATE]")
```

The results messages would be returned as shown in [Figure 315](#):

**Figure 315: EXTRACT^DIAXU API—Example 1: Output Results Messages**

```
^TMP("DIAXU",627068728,"RESULT",16151,7) = 1
^TMP("DIAXU",627068728,"RESULT",16151,32) = 13
^TMP("DIAXU",627068728,"RESULT","ERR",16151,34) = 1;
```

The error messages would be returned as shown in [Figure 316](#):

**Figure 316: EXTRACT^DIAXU API—Example 1: Output Error Messages**

```
^TMP("DIERR",627068728,1) = 701
^TMP("DIERR",627068728,1,"PARAM",0) = 3
^TMP("DIERR",627068728,1,"PARAM",3) = NEWONE
^TMP("DIERR",627068728,1,"PARAM","FIELD") = .01
^TMP("DIERR",627068728,1,"PARAM","FILE") = 16299
^TMP("DIERR",627068728,1,"TEXT",1) = The value 'NEWONE' for field NAME in file
  FTEXT EXTRACT is not valid.
^TMP("DIERR",627068728,"E",701,1) =
```

### 12.2.2.1.2 Example 2

Suppose that the call to EXTRACT^DIAXU is made using the **FILING\_LEVEL** array. This means that subrecords at some subfile levels are extracted individually. Suppose only one record is being extracted (IEN #5), and two subrecords are extracted individually with the **FILING\_LEVEL** array. Subrecord #1 extracts successfully, and subrecord #2 fails. The results and error messages would be returned as shown in [Figure 317](#):

**Figure 317: EXTRACT^DIAXU API—Example 2: Output Results and Error Messages**

<code>^TMP("DIAXU",541074770,"RESULT",662001,5) = 75</code>	(record #5, success)
<code>^TMP("DIAXU",541074770,"RESULT",662001.1,"1,5,") = 1,75,</code>	(subrecord #1, success)
<code>^TMP("DIAXU",541074770,"RESULT","ERR",662001,5) = 2</code>	(record #5, error 2 from subrecord failure)
<code>^TMP("DIAXU",541074770,"RESULT","ERR",662001.1,"2,5,") = 1;</code>	(subrecord #2, error 1)
<code>^TMP("DIERR",541074770,1) = 330</code>	(error 1)
<code>^TMP("DIERR",541074770,1,"PARAM",0) = 2</code>	
<code>^TMP("DIERR",541074770,1,"PARAM",1) = 99</code>	
<code>^TMP("DIERR",541074770,1,"PARAM",2) = pointer to File #200</code>	
<code>^TMP("DIERR",541074770,1,"TEXT",1) = The value '99' is not a valid pointer to File #200.</code>	
<code>^TMP("DIERR",541074770,2) = 1300</code>	(error 2)
<code>^TMP("DIERR",541074770,2,"PARAM",0) = 1</code>	
<code>^TMP("DIERR",541074770,2,"PARAM","IEN") = 5</code>	
<code>^TMP("DIERR",541074770,2,"TEXT",1) = "The entry encountered an error during subfile filing."</code>	
<code>^TMP("DIERR",541074770,"E",330,1) =</code>	
<code>^TMP("DIERR",541074770,"E",1300,2) =</code>	

### 12.2.2.2 Error Codes Returned

The EXTRACT^DIAXU API calls the following APIs:

- [\\$\\$FIND1^DIC](#)
- [LIST^DIC](#)
- [UPDATE^DIE](#)
- [\\$\\$GET1^DIQ](#)
- [GETS^DIQ](#)

Any errors returned by these APIs can also be returned by the EXTRACT^DIAXU API.

In addition, [Table 103](#) lists the possible error codes returned with the EXTRACT^DIAXU API:

**Table 103: EXTRACT^DIAXU API—Error Codes Returned**

Code	Description
<a href="#">202</a>	An input parameter is missing or not valid.
<a href="#">601</a>	The entry does not exist.
<a href="#">1300</a>	The entry encountered an error during subfile filing.



# 13 Filegrams API

## 13.1 Introduction

Filegrams are a feature in VA FileMan intended for use by system managers and application developers.

A Filegram is a process that moves a record (also called an entry) from a file on one computer system to a duplicate file on another *independent* computer system. An independent computer system is defined as a system having its own database. Sending data from the “live” account at a site to the “test” account at the same site is an example of moving a Filegram locally. Sending data from a computer in the San Francisco Medical Center to a computer in the Salt Lake City Medical Center is an example of moving a Filegram remotely.

The Filegram process consists of the following three components:

- Filegram generator (DIFGG routines)
- Filegram installer (DIFG routines)
- FILEGRAM template (stored in the PRINT TEMPLATE [#.4] file)

Although there is a set of options to work with Filegrams, developers find that the only routines necessary to process a Filegram are the installer and the generator routines that are described in the [^DIFG](#) and [EN^DIFGG](#) sections, respectively.



**REF:** For more information about Filegrams, see the “Filegrams” section in the *VA FileMan Advanced User Manual*.

## 13.2 Application Programming Interfaces (APIs)

### 13.2.1 ^DIFG: Filegram Installer

The Filegram process consists of the following three components:

- Filegram generator (DIFGG routines)
- Filegram installer (DIFG routines)
- FILEGRAM template (stored in the P PRINT TEMPLATE [#.4] file)

Developers can find that the only routines necessary to process a Filegram are the installer and the generator routines.

The following key variables *must* be present in addition to the required variables described below:

- **DUZ**
- **DUZ(0)**
- **DT**

Use the ^DIFG API to install Filegrams. The installer part of the Filegram requires the **DIFGLO** variable in addition to the VA FileMan key variables mentioned just above. The other input variables are optional.

**D ^DIFG** installs the Filegram.

## Input Variables

- DIFGLO: (Required) This variable *must* be the global root of the Filegram to be installed.
- DIADD: (Optional) If this variable is defined, a new entry is created in the base file.
- DINUM: (Optional) Entry number in base file at which new file entry, if added, is created.

## Output Variables

DIFGER: This output variable is defined if an error has occurred.



**NOTE:** It is defined even if the install fails after the base file has been processed. Thus, it could exist even if **DIFGY** is *not* equal **-1**.



**REF:** For a list of error codes that can be found in **DIFGER**, see the “[Error Codes Returned](#)” section.

- DIFGY: ^DIFG always returns **DIFGY**. **DIFGY** can have one of the following values:
- **DIFGY=-1**—Indicates that the lookup on the initial file processed (the base file) was *unsuccessful*.
  - **DIFGY=N^F**—Where **N** is the internal number of the entry in the base file and **F** is the base file’s number.
  - **DIFGY=N^F^1**—Where **N** and **F** are defined as above and **1** indicates that a new entry has been added to the base file.

### 13.2.1.1 Error Codes Returned

If a soft error occurs, the variable **DIFGER** is defined when the Filegram routines are exited. This variable contains information about the problem encountered. It consists of two ^-pieces:

- First piece indicates the error number.
- Second piece usually contains a line number in the Filegram that indicates where the Filegram process failed.

[Table 104](#) lists the error codes found in **DIFGER** along with their specific meanings:

**Table 104: ^DIFG: Installer—Error Codes Returned**

Code	Description
1^0	The Filegram global root was <i>not</i> passed in <b>DIFGLO</b> .
1.25^0	The Filegram global root format is invalid.
1.5^0	The Filegram global root is passed but the global does <i>not</i> exist.
2^1	The first line of the Filegram does <i>not</i> contain a <b>\$DAT</b> .
3^#	A line other than the first line has a <b>\$DAT</b> as its first colon-piece.
4^#	The field does <i>not</i> exist within this file.
5^#	<a href="#">^%DT</a> was called and <b>Y</b> was returned equal to <b>-1</b> .

Code	Description
6^#	Line after a context switch, subfile; and any field that required a lookup was <i>not</i> a <b>BEGIN</b> condition.
7^#	<b>DINUM</b> variable exists, the mode is <b>A</b> or <b>L</b> , and the INPUT transform contains the word <b>DINUM</b> (files or subfiles only).
8^#	<b>DINUM</b> or <b>DIADD</b> variables exist and the mode is neither <b>A</b> nor <b>L</b> (files or subfiles only).
9^#	File or subfile lookup failed and mode type does <i>not</i> permit addition of an entry to this file. In other words, the mode type was either <b>D</b> or <b>M</b> .
10^#	Lookup failed during a context or subfile shift, the <b>.01</b> field of the file or subfile is a pointer, and LAYGO to the pointed-to file is <i>not</i> allowed. This code is also generated if lookup failed and LAYGO is <i>not</i> allowed for a pointer that is an identifier or specifier.
11^#	A lookup for a single valued pointer field fails and LAYGO is <i>not</i> allowed.
12^#	A lookup failed for a file or subfile and the mode is <b>M</b> .
13^#	There is a key for a given entry and the internal entry number was <i>not</i> found in the cross-reference or the cross-reference did <i>not</i> exist.
14^#	<a href="#">^DIE</a> called for a <b>MODIFY</b> or <b>DELETE</b> Filegram and <b>Y</b> was returned defined.
15^#	<a href="#">^DIE</a> called for an entry that was an <b>ADD</b> and <b>Y</b> was returned as defined.
16^#	Call to <a href="#">^DIC</a> or <a href="#">FILE^DICN</a> and <b>Y</b> was returned equal to -1. Error occurred during installation.
17^#	Entry of a WORD-PROCESSING field failed.
18^#	Lookup failed when a “ <b>B</b> ” index lookup was specified and the <b>B</b> cross-reference did <i>not</i> exist.
19^#	<b>DINUM</b> was passed to <b>DIFG</b> , the mode of the baseline file was <b>M</b> or <b>D</b> , and the entry did <i>not</i> exist in the baseline file.
20^#	File does <i>not</i> exist.
21^#	A field has a “@link” value that is unresolved and is <i>not</i> LAYGOed to the pointed-to file during installation.

### 13.2.2 EN^DIFGG: Filegram Generator

The Filegram process consists of the following three components:

- Filegram generator (DIFGG routines)
- Filegram installer (DIFG routines)
- FILEGRAM template (stored in the PRINT TEMPLATE [#.4] file)

Developers can find that the only routines necessary to process a Filegram are the installer and the generator routines.



The following key variables *must* be present in addition to the required variables described below:

- **DUZ**
- **DUZ(0)**
- **DT**

In order to create (or generate) a Filegram, **D EN^DIFGG** with the key variables just above and the required input variables listed below. **DUZ** should refer to a valid user. The optional input variables can be used to customize the Filegram.

### Input Variables

- DIFGT: (Required) This variable *must* equal the internal entry number in the PRINT TEMPLATE (#.4) file of the FILEGRAM template that defines the data to be sent.
- DIFG("FE"): (Required) This variable *must* equal the internal number in the base file of the entry to be sent.
- DIFG("FUNC"): (Required) This variable *must* equal **A**, **M**, **L**, or **D**. The meanings of these codes, which indicate the mode of the Filegram, are:
- **A—ADD** (force an add)
  - **M—MODIFY**
  - **L—LAYGO**
  - **D—DELETE**
- DIFG("FGR"): (Optional) Set this variable equal to the root of the global or local array in which the Filegram is built. The default is **^UTILITY("DIFG",\$J**, if this variable is *not* defined.
- DILC: (Optional) One fewer than the first subscript to generate. Default=**0**.
- DITAB: (Optional) Initial indentation level for Filegram text.

### Output Variables

- DIFGER: This output variable is defined if an error has occurred. The possible values are:
- A required variable was *not* passed.
  - A variable's format is invalid.
  - A variable's content is invalid.

# 14 Meta Data Dictionary

## 14.1 Introduction

The META DATA DICTIONARY (#.9) file is a summary of all the VA FileMan files within a Veterans Health Information Systems and Technology Architecture (VistA) installation. It enables users to quickly identify where information is stored within files and fields throughout the VistA system.

The META DATA DICTIONARY (#.9) file contains the following fields:

- NAME (#.01)—Contains the dictionary name followed by the field name with the underscore (“\_”) connecting the two. If the field is a Multiple, then the Multiple name is included.
- LOOKUP TERM (#.02)—Final field name.
- DATA DICTIONARY NUMBER (#.03)—Internal entry number (IEN) for the dictionary represented.
- FIELD NUMBER (#.04)—Internal entry number (IEN) for the field represented.
- DATA (#.05)—Indicator that the field contains data.
- OBJECT NAME (#.06)—CamelCase representation of the NAME (#.01) field.
- LAST UPDATED (#.07)—Indicates the last date/time this field was last edited.
- DESCRIPTION (#1)—Field description.
- BUILD(S) (#9.6)—Displays all of the builds where this field was included.
- TYPE (#25)—Data Type of the field.

**Figure 318: META DATA DICTIONARY (#.9) File Sample Entry**

```
NUMBER: 21336                                NAME: NEW PERSON_NAME
LOOKUP TERM: NAME                            DATA DICTIONARY NUMBER: 200
FIELD NUMBER: .01                           OBJECT NAME: newPerson.name
LAST UPDATED: DEC 30,2015@08:02:19
DESCRIPTION: Answer must be 3-35 upper-case characters in length, and be in
the format Family(Last),Given(First) Middle Suffix. Enter '??' for more help.
Enter only data that is actually part of the person's name. Do not include
extra titles, identification, flags, local information, etc. Enter the
person's name in 'LAST,FIRST MIDDLE SUFFIX' format. This value must be 3-35
characters in length and may contain only uppercase alpha characters, spaces,
apostrophes, hyphens and one comma. All other characters and parenthetical
text will be removed.
BUILD(S) (c): XU*8.0*120
              : XU*8.0*135
              : XU*8.0*134
              : XU*8.0*551
TYPE (c): FREE TEXT
```

## 14.2 Application Programming Interfaces (APIs)

### 14.2.1 ^DDD: Build the Meta Data Dictionary

You can build the Meta Data Dictionary (MDD) by directly initiating the DDD routine at the top-level from the M programmer's prompt (e.g., >D ^DDD) or by using the DDU UPDATE META DD menu option. The ^DDD API removes all current entries and fully reproduces the Meta Data Dictionary.

## Format

^DDD

## Input Parameters

None.

## Output

Meta Data Dictionary (MDD).

### 14.2.1.1 Example

```
>D ^DDD
```

## 14.2.2 FILELIST^DDD(): File List Partial Update

The FILELIST^DDD API can be run directly from the M programmer's prompt. It requires an array passed by reference that includes files that are to be updated.

### Format

```
FILELIST^DDD(.array)
```

### Input Parameters

.array: (Required) A subscripted array of files where the subscript is the file number.

### Output

None.

### 14.2.2.1 Example

For example:

```
S ARRAY(2)= "" ;PATIENT FILE
S ARRAY(200)= "" ;NEW PERSON FILE
D FILELIST^DDD(.ARRAY)
```

## 14.2.3 PARTIAL1^DDD: Partial Update using ^DIC(DDD,“%MSC”)

The PARTIAL1^DDD API makes use of the Data Dictionary ^DIC(DDD,“%MSC”) variable that includes the date that this file was last updated. The PARTIAL1^DDD API updates all files where the ^DIC(DDD,“%MSC”) variable is greater than the date and time stamp that the Meta Data Dictionary (MDD) was last updated.



**NOTE:** Currently, the ^DIC(DDD,“%MSC”) variable is *not* updated for field description changes.

## Format

Partial1^DDD

## Input Variables

**^DIC(DDD,“%MSC”)**: (Required) Includes the date that this file was last updated.

## Output

Updates all files where the **^DIC(DDD,“%MSC”)** variable is greater than the date and time stamp that the Meta Data Dictionary (MDD) was last updated.

## 14.2.4 PARTIAL2^DDD: Partial Update using ^DD(FILE,FIELD,“DT”)

The PARTIAL2^DDD API makes use of the **^DD(FILE,FIELD,“DT”)** variable that includes the date that the field was last updated. The PARTIAL2^DDD API updates all files where there is a field that the **^DD(FILE,FIELD,“DT”)** variable is equal to or greater than the date and time stamp that the Meta Data Dictionary (MDD) was last updated.

## Format

Partial2^DDD

## Input Variables

**^DD(FILE,FIELD,“DT”)**: (Required) Includes the date that this field was last updated.

## Output

Updates all files where there is a field that the **^DD(FILE,FIELD,“DT”)** variable is equal to or greater than the date and time stamp that the Meta Data Dictionary (MDD) was last updated.

# 15 Create Sort Templates Silently API

## 15.1 BUILDNEW^DIBTED(): Sort Template Builder

The BUILDNEW^DIBTED API silently creates an entry in the SORT TEMPLATE (#.401) file. SORT templates can be used for any purpose; however, you primarily use them with the [LIST^DIC\(\): Lister](#) API. The SORT templates created “on-the-fly” by the BUILDNEW^DIBTED API can be used in the [LIST^DIC\(\): Lister](#) API in conjunction with the “X” flag to control the output of that procedure.

### Format

```
BUILDNEW^DIBTED(.return,file,sort_criteria,template_name)
```

### Input Parameters

**.return:** (required) This parameter is passed by reference. It contains the result of the API call.

Possible returned values are:

- **-1**—Failure; no returned error message.
- **-1^error**—Failure; with a returned error message.
- **Template\_IEN^Template\_Name^1**—Success; with a *new* entry in the SORT TEMPLATE (#.401) file at **Template\_IEN** and with the name indicated. The name should be the SORT template name passed into the API in the **template\_name** parameter.
- **Template\_IEN^Template\_Name**—Success; with an *existing* entry in the SORT TEMPLATE (#.401) file being overwritten with the new sort criteria. The SORT template name passed into the API already existed in the SORT TEMPLATE (#.401) file.

**file:** (required) Number of the file on which the SORT template is created.

**sort\_criteria:** (required) Name of the array containing the sort criteria. The array should be subscripted with positive numbers. The contents of the array *must* match exactly the format expected by the SORT template engine. The best way for the developer to create the array is to make a SORT template using the Print File Entries option [DIPRINT] and copy the array produced. The properly formatted elements of the array can be found using the Template Edit option [DITEMP] on the second page of the screen mode form.

**template\_name:** (required) Name you want to give the SORT template. Do *not* include brackets. If a SORT template with that name already exists, it is overwritten with the new sort criteria.

### Output

The primary output is the creation of a new SORT template. A description of the result of the call is returned in the [.return](#) parameter as described in the “Input Parameters” section.

### Example

[Figure 319](#) illustrates the creation of a SORT template using BUILDNEW^DIBTED API. Note the specific spacing in the nodes of SORT().

The **RET** variable returns the IEN of the entry in the SORT TEMPLATE (#.401) file (i.e., **922**) as well as the name of the new SORT template, which is the same name passed into the API.

The “1” in the third piece of **RET** indicates that a new template was created. The [LIST^DIC\(\): Lister](#) call makes use of the newly created template.



**NOTE:** Brackets are added to the Template Name for the [LIST^DIC\(\): Lister](#) call.

**Figure 319: BUILDNEW^DIBTED—Example**

```
>S SORT(1)="SORT BY: -COUNT(COUNTY)"
>S SORT(2)="From:"
>S SORT(3)="To:"
>S SORT(4)="    WITHIN COUNT(COUNTY), SORT BY: $E(NAME,1,3)=""NEW""
>S FILE=5
>N RET
>S TNAME="ZZD STATE SORT 1"
>D BUILDNEW^DIBTED(.RET,FILE,$NA(SORT),TNAME)
>W RET
922^ZZD STATE SORT 1^1
>D LIST^DIC(FILE,,".01;COUNT(COUNTY)","X",,,,"[ZZD STATE SORT 1]")
```

# IV. Developer Tools


## 16 ^DI: Programmer Access

Often, VA FileMan’s options are accessed through a menu system that calls up the main VA FileMan menu. For example, if Kernel is installed, VA FileMan can be entered from Kernel’s menu system if a user has been granted access.

However, the main menu can also be displayed directly from the M command prompt. When you call VA FileMan directly, you are using “programmer mode.”

There are four entry points in the **DI** routine that you can use to enter VA FileMan. Each way of calling up the main menu has a different effect upon the local M variables that are defined when you begin your VA FileMan session. They are described in [Table 105](#):

**Table 105: ^DI API—Entry Points**

Entry Point	Description
P^DI	This entry point cleans the symbol table; it KILLS all local variables except those that are required for VA FileMan’s operation. (The variables <b>DUZ</b> and <b>DTIME</b> are unchanged.) In addition, the variable <b>DUZ(0)</b> is set equal to the at-sign (@). The at-sign gives you complete programmer access to all of VA FileMan’s files and functionality.  <b>NOTE:</b> Included in the variables KILLED are the input/output (IO) variables.
Q^DI	Like P^DI, this entry point sets <b>DUZ(0)</b> =“@”. However, the remaining variables in the local symbol table are unchanged.
C^DI	Like P^DI, this entry point cleans the symbol table. However, it leaves <b>DUZ(0)</b> unchanged; whatever Access code string was in <b>DUZ(0)</b> before the call remains to control access within VA FileMan.
D^DI	This entry point leaves all local variables alone. It neither cleans the symbol table nor resets <b>DUZ(0)</b> .

In addition, other necessary variables are set to default values if they are undefined when you start VA FileMan from programmer mode.



**CAUTION:** Programmer access in VistA is defined as **DUZ(0)**=“@”. It grants the privilege to become a developer in VistA. Programmer access allows you to work outside many of the security controls enforced by VA FileMan, enables access to all VA FileMan files, access to modify data dictionaries, etc. It is important to *proceed with caution* when having access to the system in this way.

# 17 ^DIKCBLD: Build an M Routine that Makes a Call to CREIXN^DDMOD

The ^DIKCBLD programmer mode utility creates a routine that makes a call to [CREIXN^DDMOD](#) to create a New-Style cross-reference.

## 17.1 Details

If you use KIDS to transport a field that is a value in a New-Style cross-reference, that cross-reference is *automatically* transported and installed at the installing site. In some situations, however, you can create a New-Style cross-reference definition on a target system *without* sending fields, or create a New-Style cross-reference on-the-fly on a running system. To do this, you can write an M routine that makes a call to [CREIXN^DDMOD](#).

The input parameters to the [CREIXN^DDMOD](#) API are fairly extensive. ^DIKCBLD can be used to facilitate the development of the code that calls [CREIXN^DDMOD](#). It *automatically* builds an M routine that sets up the input parameters and makes the call to [CREIXN^DDMOD](#).

When ^DIKCBLD is run, it asks you for the following information:

- Name of a routine.
- Namespace to use for local variables within that routine.
- New-Style cross-reference that exists in the development account.

The input parameters to the [CREIXN^DDMOD](#) call in the generated routine are set based on the selected cross-reference.



**NOTE:** The routine generated by ^DIKCBLD is a skeleton. You *must* still edit the routine to fill in the missing details on the first and second lines, as well as customize the parameters routine to the [CREIXN^DDMOD](#) call.



## 17.2 Example

Figure 320: ^DIKCBLD API—Sample User Dialogue

```
>D ^DIKCBLD

Routine name: ZZTEST

Routine ZZTEST already exists.
Do you wish to replace routine ZZTEST? NO// YES

Programmer initials: OX
Namespace to use for local variables: MY

CROSS-REFERENCE FROM WHAT FILE: 16012 <Enter> ZZMYTESTFILE (1 entry)

Current Indexes on file #16012:
220 'AD' index

Which Index do you wish to build a routine for? 220 <Enter> AD

'ZZTEST' ROUTINE FILED.

Done!

Be sure to edit the routine to fill in the missing details,
and to customize the call to CREIXN^DDMOD.

>ZL ZZTEST ZP
ZZTEST ;xxxx/OX-CREATE NEW-STYLE XREF ;11:06 AM 9 Jul 2002
;1.0
;
N myXR,myRES,myOUT
S myXR("FILE")=16012
S myXR("NAME")="AD"
S myXR("TYPE")="MU"
S myXR("USE")="A"
S myXR("EXECUTION")="F"
S myXR("SHORT DESCR")="This MUMPS cross-reference updates
field #2 when field #1 is deleted."
S myXR("DESCR",1)="The kill logic of this cross-reference
calls the Filer to stuff today's"
S myXR("DESCR",2)="date into field #2 whenever the value
of field #1 is deleted."
S myXR("DESCR",3)=" "
S myXR("DESCR",4)="The set logic calls the Filer to
delete the contents of field #2"
S myXR("DESCR",5)="when a value is placed into field #1."
S myXR("SET")="N ZZFDA,ZZMSG,DIERR
S ZZFDA(16012,DA_"",",",2)="""
D FILE^DIE("","", "ZZFDA", "ZZMSG")"
S myXR("KILL")="N ZZFDA,ZZMSG,DIERR
S ZZFDA(16012,DA_"",",",2)=DT
D FILE^DIE("","", "ZZFDA", "ZZMSG")"
S myXR("SET CONDITION")="S X=X1(1)="""
S myXR("KILL CONDITION")="S X=X2(1)="""
S myXR("VAL",1)=1
D CREIXN^DDMOD(.myXR,"SW",.myRES,"myOUT")
Q
```

## 18 LANG^DIALOGZ(): File Modification for Multiple Languages

The LANG^DIALOGZ API is invoked from programmer mode to modify the user dialogue to show file components in a language different than the one used to define the file. It is part of the ongoing initiative to internationalize VA FileMan.

Among the items that you can translate are:

- File name
- Field name
- Help text for a field
- External value of SET OF CODES fields

You can see the translated values using the Standard output of the List File Attributes option [DILIST].

### Format

```
LANG^DIALOZ (LangNum)
```

### Input Parameters

LangNum: (Required) The ID NUMBER (#.001) field value from the LANGUAGE (#.85) file of the language you want to translate.

The sample dialogue in [Figure 321](#) illustrates the addition of French language translations to some items in a file. The examples below do *not* include possible translations of any of the VA FileMan prompts.

During this session, the following fields are translated:

- Name of the file
- Name of two fields
- Help text for one field
- External values of a SET OF CODES for the other field



**NOTE:** The syntax for entering the translated SET OF CODES is: the external values in order, separated by a semicolon.

**Figure 321: LANG^DIALOGZ API—Sample User Dialogue**

```
>D LANG^DIALOGZ(4) <Enter> ;4 is ID NUMBER of French in Language File (#.85)

Modify what File: ZZD TEST FILE1 <Enter> (3 entries)
FRENCH translation of ZZD TEST FILE1: ZZD FICHER DE TEST

Select FIELD: NAME
FRENCH translation of NAME: NOM
Current NAME Field Help Prompt:
  NAME MUST BE 3-30 CHARACTERS, NOT NUMERIC OR STARTING WITH PUNCTUATION
FRENCH translation of Prompt: NOM EST 3-30 CARACTERES, PAS NUMERIC NI COMMENCEMENT
AVEC DES SIGNES DE PONCTUATION.

Select FIELD: YES/NO
FRENCH translation of YES/NO: OUI/NON
Current SET values: Y:Yes;N:No;U:Unknown
FRENCH translation of SET values: ?
YOU MUST ENTER 3 EXTERNAL VALUES, SEPARATED BY SEMICOLONS(;).
FRENCH translation of SET values: Oui;Non;Inconnu
Select FIELD: <Enter>
```

The user sees the translated values when the value of **DUZ**(“LANG”) is set and the **ID NUMBER** of a language for which the translations are performed. In the examples in [Figure 322](#), **DUZ**(“LANG”)=4.

The complete integration of the translated values is a work in progress. The sample dialogue in [Figure 322](#) shows how the translated values are used. Comments are added in callouts to illustrate interesting aspects of the current state of the translation program.

Figure 322: LANG^DIALOGZ API—Sample Translated Editing Dialogue

Select OPTION: ENTER OR EDIT FILE ENTRIES

Translated file name *cannot* be used here.

Input to what File: ZZD TEST FILE1

Translated field name is echoed.

EDIT WHICH FIELD: ALL// .01 <Enter> NAME NOM

Original field name *must* be used; translated is echoed.

THEN EDIT FIELD: YES/NO <Enter> OUI/NON  
THEN EDIT FIELD: <Enter>

In editing dialogue, translated file and field names used.

Select ZZD FICHIER DE TEST NOM: EN FRANCAIS  
Are you adding 'EN FRANCAIS' as a new ZZD FICHIER DE TEST (the 4TH)? No// Y  
(Yes)

Translated external values for sets of codes are displayed.

OUI/NON: ?  
Choose from:  
1 Oui  
2 Non  
3 Inconnu

Translated external value is echoed.

OUI/NON: 2 <Enter> Non

Select ZZD FICHIER DE TEST NOM: EN FRANCAIS NUMERO DEUX  
Are you adding 'EN FRANCAIS NUMERO DEUX' as  
a new ZZD FICHIER DE TEST (the 5TH)? No// Y <Enter> (Yes)

Untranslated external value is *not* accepted.

OUI/NON: Yes??  
Choose from:  
1 Oui  
2 Non

```

3          Inconnu
OUI/NON: 0 <Enter>  Oui

Select ZSD FICHER DE TEST NOM: EN FRANCAIS NUMERO DEUX
NOM: EN FRANCAIS NUMERO DEUX  Replace ?
      NOM EST 3-30 CARACTERE, PAS NUMERIC NI COMMENCEMENT AVEC DES SIGNES DE
      PONCTUATION.

Help text is translated.

NOM: EN FRANCAIS NUMERO DEUX  Replace DEUX With TROIS
Replace <Enter>
      EN FRANCAIS NUMERO TROIS
OUI/NON: Oui// In <Enter>      Inconnu

```

During the Print File Entries dialogue, you *must* use the untranslated values for the file and field names. However, the output shows translated file and field names as well as translated external values for the SET OF CODES.



**NOTE:** The internal values of the set of codes field remain as originally defined.

**Figure 323: LANG^DIALOGZ API—Sample Translated Print File Entries Dialogue**

```

Select OPTION: PRINT FILE ENTRIES

Output from what File: ZSD TEST FILE1 <Enter> (5 entries)
Sort by: NAME// <Enter>
Start with NAME: FIRST// <Enter>

Translated field names are echoed.

First Print FIELD: .01 <Enter>  NAME      NOM
Then Print FIELD: YES/NO <Enter>      OUI/NON
Then Print FIELD: INTERNAL(YES/NO)
By 'YES', do you mean ZSD TEST FILE1 'YES/NO'? Yes// <Enter> (Yes)
Then Print FIELD: <Enter>

Heading is translated.

Heading (S/C): ZSD FICHER DE TEST List Replace <Enter>
STORE PRINT LOGIC IN TEMPLATE: <Enter>
DEVICE: HOME// <Enter>  TELNET

ZSD FICHER DE TEST List                                     MAR 11, 2013@10:19  PAGE 1
NOM                                                         OUI/NON  INTERNAL(YES/NO)
-----
EN FRANCAIS                                               Non      N
EN FRANCAIS NUMERO DEUX                                   Oui      Y
FIRST ENTRY
SECOND ENTRY
THIRD ENTRY

```

DIALOGZ places the translations as shown in [Figure 324](#).

**Figure 324: LANG^DIALOGZ API—Translations**

```
^DIC(filenumbr,"ALANG",LangNum, -- Contains the Translation of the file name  
caption for the indicated language.  
^DD(filenumbr,FieldNum,.008,LangNum -- Contains the Translation of the field  
name caption for the indicated language.
```

# 19 Global File Structure

## 19.1 Introduction

This section describes the storage of VA FileMan files, including the file structure and the actual file data.

Throughout this section, these basic components of a VA FileMan file are described by way of an example: how the rudiments of a (fictitious) EMPLOYEE file would be mapped into a (fictitious) global called ^EMP using VA FileMan. File number 3 is assigned to this (fictitious) file in the examples.

Global File Structure includes the following sections:

- [Data Storage Conventions](#)
- [File's Entry in the Dictionary of Files](#)
- [File Header](#)
- [File Entries \(Data Storage\)](#)
- [Cross-References](#)
- [INDEX File](#)
- [KEY File](#)
- [Attribute Dictionary:](#)
  - [File Characteristics Nodes](#)
  - [Field Definition 0-Node](#)
  - [Other Field Definition Nodes](#)
  - [Reading the Attribute Dictionary—Example](#)

## 19.2 Data Storage Conventions

VA FileMan stores the data of every file descendent from a single M global array (or from a node of a global array). When the routines, internally and externally, make reference to a file in a global notation, VA FileMan expects the following format:

- ^GLOBAL(—For an entire global
- ^GLOBAL(X,Y,—For a subtree of a global



**NOTE:** A global notation *must* terminate with an open parenthesis (“(”) or a comma (,). Indirection (@) is always used by VA FileMan routines when referring to data files.

For the most part, VA FileMan packs data into subscripts using the caret (^) character as the \$PIECE delimiter. You refer to a data element as being stored in the  $n^{\text{th}}$  ^-piece of a global node.

## 19.3 File's Entry in the Dictionary of Files

All VA FileMan files, regardless of the global used for data storage, have an entry in the Dictionary of Files (i.e., the **^DIC** global descendent from the file's DD number).

The zero subscript contains the file name and file number.

The global location (**GL**) node descendent from subscript zero is set to the root of the global used to store data for this file. So, the (fictitious) EMPLOYEE file example could have the following:

**Figure 325: ^DIC Global—Sample File Entry in the Dictionary of Files**

```
^DIC(3,0)          = "EMPLOYEE^3"
^DIC(3,0,"GL")    = "^EMP("
```

The **^DIC** global also contains the file's security protection codes, if any, descendent from the zero subscript in the following nodes:

**Figure 326: ^DIC Global—Sample File Security Protection Codes**

```
^DIC(filename,0,"AUDIT")    -- Audit Access
^DIC(filename,0,"DD")      -- Data Dictionary Access
^DIC(filename,0,"DEL")     -- Delete Access
^DIC(filename,0,"LAYGO")   -- LAYGO Access
^DIC(filename,0,"RD")     -- Read Access
^DIC(filename,0,"WR")     -- Write Access
```

The rest of the **^DIC** global descriptors for a file are listed in [Figure 327](#):

**Figure 327: ^DIC Global—Sample File Descriptors**

```
^DIC(filename,"%",      -- At lower subscript levels, contains the application
groups.
^DIC(filename,"%A")    -- Creator's DUZ^file creation date. DIFROM does not send
this node.
^DIC(filename,"%D",    -- At lower subscript levels, contains the text of the
file's DESCRIPTION.
^DIC(filename,"ALANG",LangNum, -- Contains the Translation of the filename
caption for the indicated language. (Built by DIALOGZ)
^DIC(filename,"%MSC")  -- The date/time the Data Dictionary was last edited.
```

## 19.4 File Header

A descriptor string is stored in the zero subscript of the file's (fictitious) global root-**^EMP**( in the example. This is simply a ^-piece-delimited string containing the following:

**Table 106: File Header—Descriptor String**

^-piece	Contains
piece 1	File name.
piece 2	File number with file characteristics codes.
piece 3	Most recently assigned internal entry number.
piece 4	Current total number of entries.





**NOTE:** The most recently assigned number is *not* necessarily the largest entry number. The file number is the record number of the file in the attribute (or data) dictionary that describes the data fields for this file. Thus, if a file has three employees and if the file’s most recently added employee was assigned entry number 9, you have:

```
^EMP(0) = "EMPLOYEE^3I^9^3"
```

The data dictionary number (second ^-piece) can also be followed by a string of alphabetic characters that are used by VA FileMan as flags to indicate various characteristics of the file. [Table 107](#) lists the values this string can contain:

**Table 107: File Header—Descriptor String: Second ^-Piece**

second ^-piece	Contains
D	.01 field of the file is a Date/Time.
P	.01 field of the file is a Pointer to another file.
S	.01 field of the file is a SET OF CODES.
V	.01 field of the file is a VARIABLE POINTER.
A	Automatically adds entries without asking: "ARE YOU ADDING A NEW ENTRY?"
I	File has Identifiers.
O	The user is asked "...OK?" whenever a matching entry is found during lookup.
s	(lowercase s) File has a screen defined in ^DD(filename,0, "SCR").

## 19.5 File Entries (Data Storage)

Each entry in a file corresponds to a positive-valued key subscript, the internal entry number, of the file global. All data pertaining to an entry is stored in global nodes descendent from that subscript. The value of the .01 field of an entry is always stored in the first ^-piece of subscript zero, descendent from the internal entry number subscript. Thus, for entry #1, an employee named THREE FMEMPLOYEE, you would have:

**Figure 328: File Entries (Data Storage)—Sample File Entry**

```
^EMP(1,0) = "FMEMPLOYEE,THREE^"
```

Suppose you want to store the following data:

- Employee’s sex in the second ^-piece of subscript zero
- Date of birth in the third ^-piece
- Department in the fourth ^-piece.

You would have what is shown in [Figure 329](#):

**Figure 329: File Entries (Data Storage)—Sample File Entry with Additional Data Fields**

```
^EMP(1,0) = "FMEMPLOYEE, THREE^M^2341225^3"
```

Notice that the entry for the employee's department in this file is a number. This means that the employee's department is internal entry number 3 in the (fictitious) DEPARTMENT file; and to find the employee's department, you would have to consult that file. The 7-digit number representing the employee's date of birth (e.g., 2341225) is VA FileMan's way of internally representing 12/25/1934.

How is Multiple-valued data (e.g., skill stored? There can be one or five or ten skills on file for a given employee and they obviously *cannot* all be stored (in the general case) in a single subscript. VA FileMan's answer is to make the skills list a subfile within the employee entry. This requires adding subscripts beyond the first internal key subscript that are different in value from the zero subscript that stores each employee's name, sex, and birth date. For example, if THREE FMEMPLOYEE currently has two (FREE-TEXT) skills on file, you can consider those to be entries #1 and #2 in a two-entry file, which can extend at a lower level from any unused subscript, say from SX as shown in [Figure 330](#):

**Figure 330: File Entries (Data Storage)—Sample File Entry with Multiple Data Fields**

```
^EMP(0) = "EMPLOYEE^3I^9^3"  
^EMP(1,0) = "FMEMPLOYEE, THREE^M^2341225^3"  
^EMP(1,"SX",0) = "^3.01A^2^2"  
^EMP(1,"SX",1,0) = "TYPING"  
^EMP(1,"SX",2,0) = "STENOGRAPHY"
```

Notice that the (fictitious) data global ^EMP has ^EMP(1,"SX",0) for the SKILL Multiple. The zero node, except for the first ^-piece, has the same structure as ^EMP(0). The second ^-piece is the subfile ^DD number. This tells VA FileMan which subsidiary dictionary to use for the data stored in this node. The actual data (the employee's skills in the example) are stored in the next lower level of subscripting. In the same manner that entries in the (fictitious) EMPLOYEE file have internal entry numbers, entries in the Multiple field also have internal entry numbers in the subfile. In the example above, TYPING is the first entry and STENOGRAPHY the second.

## 19.6 Cross-References

The M capabilities of string-valued array subscripting offer a simple, general way to cross-reference VA FileMan files. To minimize the number of global names used by the system, VA FileMan stores each cross-reference set as a descendent of an alphanumeric subscript of the file's global. A file, such as a (fictitious) EMPLOYEE file, that should be accessible by name, is set up by the system so that there is a subscript "B", which in turn is subscripted by strings corresponding to the first 30 characters from the .01 field for every entry in the file. For each such string-valued subscript, the next level of subscripting contains the internal entry numbers of the entries that contain the name.

Adding to the previous example (Section [19.5](#)) a second employee, internal entry number 9, also named THREE FMEMPLOYEE, and a third employee, internal number 7, whose name is ONE FMEMPLOYEE. Then you would have:

**Figure 331: Cross-References—Sample File Entry with Multiple Records**

```
^EMP(1,0) = "FMEMPLOYEE, THREE^M^2341225^3"  
^EMP(7,0) = "FMEMPLOYEE, ONE^M^2231109^2"  
^EMP(9,0) = "FMEMPLOYEE, THREE^M^2500803^18"  
^EMP("B", "FMEMPLOYEE, THREE", 1) = ""  
^EMP("B", "FMEMPLOYEE, THREE", 9) = ""  
^EMP("B", "FMEMPLOYEE, ONE", 7) = ""
```

Notice that all the data is in the subscripting and the (fictitious) global nodes under **^EMP("B")** are simply null strings. VA FileMan allows for these strings to be *non-null* in the case where a mnemonic cross-reference is set up for the name. Multiple cross-references (C, D, etc.) are also allowed.

In VA FileMan, cross-references (indexes) can be defined that have more than one data field subscript before the record number. These cross-references can then be used for a lookup and the user is prompted for more than one lookup value, one for each data subscript on the index. Such compound indexes *must* be defined as a New-Style index on the INDEX(#.11) file .

[Figure 332](#) is a sample cross-reference entry with the name and the date-of-birth on the data in [Figure 331](#):

**Figure 332: Cross-References—Sample Entry with Additional Data Fields**

```
^EMP("C", "FMEMPLOYEE, THREE", 2341225, 1) = ""
```

## 19.7 INDEX File

The Cross-Reference A Field option [DIXREF] on the Utility Functions menu [DIUTILITY] asks if the developer wants to add/edit a Traditional index or a New-Style index. Use of the INDEX(#.11) file allows for design of more sophisticated indexes, including:

- Compound indexes (i.e., with more than one data field subscript).
- Indexes where transforms are done on fields.
- Indexes with computed subscripts.
- Indexes whose normal collation sequence is backward.
- Indexes whose **SET/KILL** logic is executed once per record rather than once per field.

These indexes can then be used by the VA FileMan code for such things as looking up a record on the file. The INDEX (#.11) file stores all information describing the new indexes. Data is stored descendent from ^DD("IX"). The INDEX (#.11) file is stored in the ^DD("IX",) global.



REF: See also the "[KEY File](#)" section.

## 19.8 KEY File

VA FileMan allows you to uniquely identify a record on a file. The developer defines a field or fields as belonging to a KEY. The developer *must* also build an index for those fields. Fields in the Primary KEY are displayed during a Classic VA FileMan lookup [^DIC](#). KEY fields are used to decide whether a record already exists on the target file during transfer or during data Installation using the Kernel Installation and Distribution System (KIDS). The KEY (#.31) file is stored in the ^DD("KEY",) global.



REF: See also the "[INDEX File](#)" section.

## 19.9 Attribute Dictionary: ^DD(Filenumber

The attribute dictionary describes the data fields that a file contains within the global ^DD (the data dictionary). Each attribute dictionary is stored descendent from a positive-valued, first-level subscript of this global. Each attribute dictionary, in itself, is also in the form of a file, and thus, consists of:

- Entries
- Cross-references
- Descriptor
- Reference to the data dictionary of the attribute of attributes [[^DD\(0\)](#)].

This section is broken down further into the following subsections:

- [File Characteristics Nodes](#)
- [Field Definition 0-Node](#)
- [Other Field Definition Nodes](#)
- [Reading the Attribute Dictionary—Example](#)

## 19.9.1 File Characteristics Nodes

Certain file characteristics are kept in the subtree descendent from **^DD(filenumbe,r,0)**. These characteristics with their subscripted location and brief explanation are:

**Table 108: Attribute Dictionary—Characteristics, Subscripted Location, and Brief Explanation**

Global Node	Meaning
<b>^DD(filenumbe,r,0,“ACT”)</b>	Post-Action
<b>^DD(filenumbe,r,0,“DDA”)</b>	Data Dictionary Audit
<b>^DD(filenumbe,r,0,“DIC”)</b>	Special Lookup
<b>^DD(filenumbe,r,0,“ID”,field)</b>	Field identifiers
<b>^DD(filenumbe,r,0,“ID”,“WRITE”)</b>	Write identifiers
<b>^DD(filenumbe,r,0,“IX”,cross-reference name,(sub)filenumbe,r,field)</b>	Cross-references
<b>^DD(filenumbe,r,0,“SCR”)</b>	File Screen
<b>^DD(filenumbe,r,0,“VR”)</b>	Version Number
<b>^DD(filenumbe,r,0,“VRPK”)</b>	Distribution Package
<b>^DD(filenumbe,r,0,“VRRV”)</b>	Package Revision Data

### 19.9.1.1 Post-Action

**Figure 333: Attribute Dictionary—File Characteristics Nodes: Post-Action**

```
^DD(filenumbe,r,0,“ACT”)
```

After an entry has been selected, some action can be taken to examine or verify the selection. This executable code is stored at this global location. If you decide that the entry should *not* be selected, set **Y=-1**.



**REF:** See the “[Advanced File Definition](#)” section.

### 19.9.1.2 Data Dictionary Audit

**Figure 334: Attribute Dictionary—File Characteristics Nodes: Data Dictionary Audit**

```
^DD(filenumbe,r,0,“DDA”)
```

This node is set to **Y** if auditing is turned on for the data dictionary. The node is nonexistent, null, or set to **N** if data dictionary auditing is *not* on.

### 19.9.1.3 Special Lookup

**Figure 335: Attribute Dictionary—File Characteristics Nodes: Special Lookup**

```
^DD(filenumbe,r,0,“DIC”)
```

A special lookup program can be written to facilitate selection from a particular file. If such a program is to be used, its name is stored at this location.



**NOTE:** The lookup program reference *cannot* be a labeled entry point to a routine. The routine’s name is stored without the caret (^); it *cannot* begin with **DI**.



**REF:** See the “[Advanced File Definition](#)” section.

### 19.9.1.4 Field Identifiers

**Figure 336: Attribute Dictionary—File Characteristics Nodes: Field Identifiers**

```
^DD(filenum,0,"ID",field)
```

Field Identifiers are defined using the VA FileMan Identifier option [DIIDENT]. The value at the node is a WRITE statement. If the identifier is to be used only to ask fields when a new entry is added, then the statement only writes null; otherwise, it contains the code to write the external value of the field. An **I** is added to the second piece of the File Header when you add a field identifier, (as described in the “[File Header](#)” section).



**NOTE:** WRITE statements in the VA FileMan-generated field identifier nodes are *not* executed when VA FileMan is in silent mode. Since FileMan generates the Field Identifier nodes, it knows their format. So, in silent mode, VA FileMan places what would have been written into an array instead for use by DBS calls. So, Field Identifier nodes, although they contain WRITE statements, are compatible with GUI applications (in contrast to [Write Identifier Nodes](#)).

### 19.9.1.5 Write Identifier Nodes

**Figure 337: Attribute Dictionary—File Characteristics Nodes: Write Identifiers**

```
^DD(filenum,0,"ID","ASTRING")
^DD(filenum,0,"ID","W1")
^DD(filenum,0,"ID","W2")
^DD(filenum,0,"ID","WRITE1")
```

You can use M code to define additional custom identifier text to be displayed along with field identifiers. To do this, add “write identifier” nodes one level descendent from **^DD(filenum,0,“ID”)**. The write identifier nodes you add *must* be subscripted with strings that begin with an *uppercase alphabetic* character.

Set the value of each write identifier node to the M code that produces the desired output. Write out your output using either the [EN^DDIOL](#) entry point (*preferred*) or the M WRITE command (*not* compatible with access to your file by GUI applications). In your M code for each write identifier node, you can refer to the values in [Table 109](#) that are defined at the time the node is executed:

**Table 109: Attribute Dictionary—Write Identifier Nodes: M code to Produce Desired Output**

Write Identifier Node	M Code
Y	Current record number
Naked Reference	Set to the 0-node of the entry

Write identifiers are displayed after any field identifiers are displayed. If there is more than one write identifier, they are displayed in the collating order of the write identifier subscripts.

Since you *must* hard-set any “WRITE” nodes, you *must* also add an **I** (if one is *not* already there) to the second piece of the [File Header](#).

### 19.9.1.6 Cross-References

**Figure 338: Attribute Dictionary—File Characteristics Nodes: Cross-References**

```
^DD(filenum ber,0,"IX",cross-reference name,(sub)filenum ber,field)
```

For cross-references, this node is set equal to null.

The INDEX (#.11) file is an alternate way to define indexes on a file. The information is descendent from ^DD(“IX”).



**REF:** See a description in the “[INDEX File](#)” section.

### 19.9.1.7 Screens

**Figure 339: Attribute Dictionary—File Characteristics Nodes: Screens**

```
^DD(filenum ber,0,"SCR")
```

If you want to screen access to entries in a file, set the screen code into this node. The screen should be written like a screen put into the local variable **DIC(“S”)** for an [^DIC](#) call. The code in this node is executed for each entry in the screened file. If **\$T=0** is returned when the node is executed, the entry being screened is unavailable for:

- Lookups
- Prints
- Inquiries
- Searches
- Other actions

In order for the screen in this global to be used, you *must* put a lowercase “s” into the second piece of the file’s header following the file number (as described in the “[File Header](#)” section).

### 19.9.1.8 Version Number

**Figure 340: Attribute Dictionary—File Characteristics Nodes: Version Number**

```
^DD(filenum ber,0,"VR")
```

This node is created during an INIT built by the VA FileMan package distribution routine (**DIFROM**) or an installation using the Kernel Installation and Distribution System (KIDS). It contains the current version number for the package that distributes this file. This node and the Distribution Package node are updated for any file sent by a KIDS installation. The only time these nodes are *not* updated is when a partial DD is sent.



**REF:** For additional information on KIDS, see the “KIDS” section in the *Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide* and *Kernel 8.0 & Kernel Toolkit 7.3 Developer’s Guide*.

### 19.9.1.9 Distribution Package

**Figure 341: Attribute Dictionary—File Characteristics Nodes: Distribution Package**

```
^DD(filenumbr,0,"VRPK")
```

This node is created during an installation using the Kernel Installation and Distribution System (KIDS). It contains the name of the package that distributes this file. The only time this is *not* updated is when a partial DD is sent.



**REF:** For additional information on KIDS, see the “KIDS” section in the *Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide* and *Kernel 8.0 & Kernel Toolkit 7.3 Developer’s Guide*.

### 19.9.1.10 Package Revision Data

**Figure 342: Attribute Dictionary—File Characteristics Nodes: Package Revision Data**

```
^DD(filenumbr,0,"VRRV")
```

This optional node, if present, is created during an installation using the Kernel Installation and Distribution System (KIDS). The node is defined by the developer who distributes the package. It can contain patch or other package revision information used to designate the version of the file that is installed at the site. Updating this node is done in the KIDS Post Install Routine (formerly the POST-INIT with DIFROM/INITs) using [PRD^DILFD](#).



**REF:** For additional information on KIDS, see the “KIDS” section in the *Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide* and *Kernel 8.0 & Kernel Toolkit 7.3 Developer’s Guide*.

## 19.9.2 Field Definition 0-Node

Each entry in the attribute dictionary is a descriptor of one of the data fields in the file. VA FileMan always assigns the internal number **.01** to the NAME field and lets you assign numbers to the other fields. The attribute dictionary stores the definition of each field descendent from the node **^DD(filenumbr,fieldnumbr)**. Crucial information about the field is stored in:

**Figure 343: Attribute Dictionary—Field Definition 0-Node: ^DD(filenumbr,fieldnumbr Node**

```
^DD(filenumbr,fieldnumbr,0)
```

Every field has this **0**-node defined in the attribute dictionary.



In the example, the (fictitious) EMPLOYEE file has four fields in addition to the NAME field:

- SEX
- BIRTHDATE
- DEPARTMENT
- SKILL

SKILL is Multiple-valued. Suppose that the attribute dictionary for this file is stored in:

**Figure 344: Attribute Dictionary—Field Definition 0-Node: Sample Attribute Dictionary File Storage**

```
^DD(3)
```

**Piece 1:** The field’s label is always found as the first ^-piece in subscript zero. Thus, for the example, you would have:

**Figure 345: Attribute Dictionary—Field Definition 0-Node: Piece 1 Sample Labels**

```
^DD(3,.01,0)="NAME^"
^DD(3,1,0)="SEX^"
^DD(3,2,0)="DOB^"
^DD(3,3,0)="DEPARTMENT^"
^DD(3,4,0)="SKILL^"
```

**Piece 2:** A string containing any of the letters and symbols in [Table 110](#):

**Table 110: Attribute Dictionary—Field Definition 0-Node: Piece 2 Sample Strings**

Character	Meaning
<b>a</b>	The field has been marked for auditing all the time.
<b>e</b>	The auditing is only on <b>edit</b> or <b>delete</b> .
<b>A</b>	For Multiples, a user entering a new subentry is not <b>Asked</b> for verification.
<b>BC</b>	The data is <b>B</b> oolean <b>C</b> omputed (true or false).
<b>C</b>	The data is <b>C</b> omputed.
<b>Cm</b>	The data is <b>m</b> ultiline <b>C</b> omputed.
<b>D</b>	The data is <b>D</b> ate-valued.
<b>DC</b>	The data is <b>D</b> ate-valued, <b>C</b> omputed.
<b>F</b>	The data is <b>F</b> ree text.
<b>I</b>	The data is uneditable.
<b>Jn</b>	To specify a print length of <b>n</b> characters.
<b>Jn,d</b>	To specify printing <b>n</b> characters with <b>d</b> ecimals.
<b>K</b>	The data is M code.
<b>M</b>	For <b>M</b> ultiples, after selecting or adding a subentry, the user is asked for another subentry.
<b>N</b>	The data is <b>N</b> umeric-valued.
<b>O</b>	The field has an <b>O</b> UTPUT transform.

Character	Meaning
<b>Pn</b>	The data is a <b>P</b> ointer reference to file " <b>n</b> ".
<b>Pn'</b>	LAYGO to the <b>P</b> ointed-to file is <i>not</i> (^) allowed.
<b>R</b>	Entry of data is <b>R</b> equired.
<b>S</b>	The data is from a discrete <b>S</b> ET OF CODES.
<b>V</b>	The data is a <b>V</b> ARIABLE POINTER.
<b>W</b>	The data is <b>W</b> ORD-PROCESSING.
<b>WL</b>	The <b>W</b> ORD-PROCESSING data is normally printed in <b>L</b> ine mode (i.e., <i>without</i> word wrap).
<b>X</b>	<p>Editing is <i>not</i> allowed under the Modify File Attributes option [DIMODIFY] because the INPUT transform has been modified by the Input Transform (Syntax) option [DIITRAN] on the Utility Functions menu [DIUTILITY].</p> <p>To make a field uneditable, you need the <b>X</b> (uppercase) flag in the 2<sup>nd</sup> piece of the Zero node.</p> <p>For example:</p> <pre> ^DD(200,501.2,0) = SUBJECT ALTERNATIVE NAME^FaX^^501;2^K:\$L(X)&gt;50!(\$L(X)&lt;3 = )!'(X["@") X I \$D(X) N XUSSAN S XUSSAN=\$O(^VA(200,"ASAN = ",X,"")) K:(XUSSAN&gt;0)&amp;(XUSSAN'=DA) X </pre>
<b>x</b>	Word-processing text that contains the vertical bar ( ) is displayed exactly as they are stored, (i.e., no window processing takes place).
*	If there is a screen associated with a DATA TYPE field with values of POINTER or SET OF CODES.



**NOTE:** The second ^-piece begins with the subfile number if the field is a Multiple.

**Piece 3:** Only contains data for DATA TYPE fields with values of POINTER and SET OF CODES. In those cases, the data is:

**Table 111: Attribute Dictionary—Field Definition 0-Node: Piece 3 Data Types**

Data Type	Description
POINTER	The global root of the pointed-to file.
SET OF CODES	The set of codes of allowed responses and their meanings.

**Piece 4:** One of the following, based on the kind of data storage:

- Subscript location and ^-piece, separated by a semicolon (;).
- Subscript location and character-positions, also separated by a semicolon (;); where **Em,n** designates character-positions *m* through *n*.
- Subscript location, followed by a semicolon (;) followed by **0** (zero), to designate multiple-valued data.
- Semicolon preceded and followed by a space (“ ; ”) to indicate no data storage (i.e., computed fields).


**Piece 5:** M code to check an input in the variable **X**. If the input is invalid, the variable **X** is **KILLED** by the code. This is the field’s INPUT transform. In the case of a computed field, the code creating the variable **X** is stored here. (Pieces following the fifth piece are part of this M code.)


### 19.9.3 Other Field Definition Nodes

Every field *must* have a zero node. All other nodes describing a field are presented in [Table 112](#), but *none are mandatory*. Each subscript listed is at least the third level. The global reference appears in the following format:

**^DD(File#,Field#,Subscript)**

**Table 112: Attribute Dictionary—Other Field Definition Nodes**

Subscript	Definition
.1	Contains the full-length title of the field.
1	Contains, at lower subscript levels, executable M code to <b>SET</b> and <b>KILL</b> cross-references based on the value of the field (in the variable <b>X</b> ).
2	Contains the OUTPUT transform: M code to display the field value in a format that differs from the format in which it is stored.  <b>REF:</b> See the “ <a href="#">Advanced File Definition</a> ” section.
3	Contains the help prompt message that is displayed when the user types a question mark.
4	Contains M code that is executed when the user types one or two question marks. (Other help messages are also displayed.)
5	Contains, at lower subscript levels, pointers to trigger cross-references to this field.
7.5	Is valid only on <b>.01</b> fields. It contains M code that is executed to check the user input (in the variable <b>X</b> ). This code is executed at the start of the <b>^DIC</b> routine before the lookup on <b>X</b> has begun. If <b>X</b> is <b>KILLED</b> , the lookup terminates. Special lookup programs naturally have a way to look at <b>X</b> .
8	Read access for the field.
8.5	Delete access for the field.
9	Write access for the field.
9.01	The fields used if the field is a <b>COMPUTED</b> field.
9.1	The expression entered by the user to create the <b>COMPUTED</b> field.
9.2 to 9.9	The overflow executable M code that can be part of the specification of a field definition,

Subscript	Definition
	INPUT transform, or cross-reference.
10	Contains the source of the data.
11	Contains the destination of the data.
12	Contains the explanation of the screen on node <b>12.1</b> .
12.1	Contains the code that sets <b>DIC("S")</b> if a screen has been written for a POINTER or a SET OF CODES.
20	A Multiple that lists the fields that belong to certain groups.
21	A WORD-PROCESSING field that holds the field description.
22	The name of a help frame presented to a user who entered two question marks.  <b>NOTE:</b> This subscript is being phased out.
23	A WORD-PROCESSING field that holds the technical description of the field.
AUDIT	Contains a code defining the status of an audit trail for changes to the data in the field. Possible codes are: <ul style="list-style-type: none"> <li>• <b>y</b>—Always audited</li> <li>• <b>e</b>—Changes and deletions only audited</li> <li>• <b>n</b>—No audit recorded</li> </ul>
AX	Contains the executable code that determines if a field should be audited.
DEL	In this example, a string of executable M code that determines if the field can be deleted. This code <i>must</i> contain an M <b>IF</b> statement to set the value of <b>\$T</b> . If <b>\$T</b> is set to <b>1</b> , the field <i>cannot</i> be deleted. Normally, the <b>^DD</b> format is: <pre> ^DD(File#,Field#,"DEL",#,0)="executable MUMPS code" </pre> <p>Where <b>#</b> is an arbitrary number to distinguish each condition. If the condition was based on a particular field, then the field number was traditionally used. If "<b>DEL</b>" nodes are on the <b>.01</b> field of a file, deletion of the entire entry can be blocked.</p> <p>If an entry is being deleted by a direct call to <a href="#">^DIK</a>, the "<b>DEL</b>" nodes are <i>not</i> checked.</p>
DT	Contains the date the field was last edited.
LAYGO	A string of executable M code that determines if an entry can be added. This code <i>must</i> contain an M <b>IF</b> statement to set the value of <b>\$T</b> . If <b>\$T</b> is set to <b>0</b> , the entry <i>cannot</i> be added. Normally, the <b>^DD</b> format is: <pre> ^DD(File#, .01,"LAYGO",#,0)="executable MUMPS code" </pre> <p>Where <b>#</b> is an arbitrary number to distinguish each condition. LAYGO nodes only apply to <b>.01</b> fields.</p>
V	Descendent from these nodes is information regarding variable pointers including: <ul style="list-style-type: none"> <li>• Pointed-to file</li> <li>• Message</li> </ul>

Subscript	Definition														
	<ul style="list-style-type: none"> <li>• Order</li> <li>• Prefix</li> <li>• Screen</li> <li>• LAYGO status</li> </ul> <p style="margin-left: 40px;">^DD(File#,Field#,"V",n,0)</p> <p>Where "<b>n</b>" is a sequential number representing a different pointed-to file. The pieces within this <b>0</b> node are:</p> <p style="text-align: center;"><b>Table 113: Field Definition 0-Node—Pieces</b></p> <table border="1" data-bbox="342 787 1427 1146"> <thead> <tr> <th data-bbox="342 787 488 846">^-Piece</th> <th data-bbox="488 787 1427 846">Contents</th> </tr> </thead> <tbody> <tr> <td data-bbox="342 846 488 898">Piece 1</td> <td data-bbox="488 846 1427 898">File number of the pointed-to file.</td> </tr> <tr> <td data-bbox="342 898 488 951">Piece 2</td> <td data-bbox="488 898 1427 951">Message defined for the pointed-to file.</td> </tr> <tr> <td data-bbox="342 951 488 1003">Piece 3</td> <td data-bbox="488 951 1427 1003">Order defined for the pointed-to file.</td> </tr> <tr> <td data-bbox="342 1003 488 1056">Piece 4</td> <td data-bbox="488 1003 1427 1056">Prefix defined for the pointed-to file.</td> </tr> <tr> <td data-bbox="342 1056 488 1108">Piece 5</td> <td data-bbox="488 1056 1427 1108"><b>y/n</b> indicating if a screen is set up for the pointed-to file.</td> </tr> <tr> <td data-bbox="342 1108 488 1146">Piece 6</td> <td data-bbox="488 1108 1427 1146"><b>y/n</b> indicating if the user can add new entries to the pointed to file.</td> </tr> </tbody> </table> <ul style="list-style-type: none"> <li>• ^DD(File#,Field#,"V",n,1) <p style="margin-left: 40px;">Contains the M code defined as a screen on the pointer to the file defined in the <b>0</b> node above.</p> </li> <li>• ^DD(File#,Field#,"V",n,2) <p style="margin-left: 40px;">Contains a description of the screen.</p> </li> </ul>	^-Piece	Contents	Piece 1	File number of the pointed-to file.	Piece 2	Message defined for the pointed-to file.	Piece 3	Order defined for the pointed-to file.	Piece 4	Prefix defined for the pointed-to file.	Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.	Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed to file.
^-Piece	Contents														
Piece 1	File number of the pointed-to file.														
Piece 2	Message defined for the pointed-to file.														
Piece 3	Order defined for the pointed-to file.														
Piece 4	Prefix defined for the pointed-to file.														
Piece 5	<b>y/n</b> indicating if a screen is set up for the pointed-to file.														
Piece 6	<b>y/n</b> indicating if the user can add new entries to the pointed to file.														

## 19.9.4 Reading the Attribute Dictionary—Example

Figure 346 shows the ^DD nodes associated with the sample (fictitious) EMPLOYEE file:

Figure 346: Attribute Dictionary—Reading the Attribute Dictionary: Sample ^DD Nodes

```
^DD(3,.01,0)="NAME^FR^0;1^I X'?1A.AP1",".AP K X"
^DD(3,.01,.1)="EMPLOYEE NAME"
^DD(3,.01,1,0)="^.1^1^1"
^DD(3,.01,1,1,0)="3^B"
^DD(3,.01,1,1,1)="S ^EMP("B", $E(X,1,30),DA)=" "
^DD(3,.01,1,1,2)="K ^EMP("B", $E(X,1,30),DA)"
^DD(3,.01,3)="NAME MUST BE 3-30 CHARACTERS, IN THE FORMAT LAST,FIRST"
^DD(3,1,0)="SEX^RS^M:MALE;F:FEMALE^0;2^Q"
^DD(3,2,0)="DOB^D^0;3^S %DT="EX" D ^%DT S X=Y I X<1400000 K X"
^DD(3,2,.1)="DATE OF BIRTH"
^DD(3,3,0)="DEPARTMENT^P13'^DIZ(13,^0;4^Q"
```

Their meaning can be translated to:

- The first field is NAME (full title: EMPLOYEE NAME). It is free text data that *must* start with at least one alpha character followed by other alpha and punctuation characters and contains a comma. It is always required from the user and is stored in subscript 0, ^-piece 1 of each employee's entry. If the user types a question (?) when asked for the NAME, the user sees:

Figure 347: Attribute Dictionary—Reading the Attribute Dictionary: Sample Translated Meaning

```
NAME MUST BE 3-30 CHARACTERS, IN THE FORMAT LAST,FIRST
```

The (fictitious) EMPLOYEE file is cross-referenced by NAME, so every time a name is changed, the corresponding subscript under (fictitious) ^EMP("B") is also changed. DA is always the internal number of the employee when the cross-referencing code is executed. If a second cross-reference for NAME existed (for example, a trigger), it would be descendent from:

Figure 348: Attribute Dictionary—Reading the Attribute Dictionary: Sample DD Descendent Cross-references

```
^DD(3,.01,1,2
```

- The second field is SEX. It is stored as either **M** or **F** in the second ^-piece position of subscript 0 of each (fictitious) EMPLOYEE file entry. The user is required to respond and can type **MALE** instead of **M**, and **FEMALE** instead of **F**. The user sees the two choices displayed if a ? is typed when asked for SEX.
- The third field is DOB (full title: DATE OF BIRTH). It is *not* required. If entered, it *must* be in the format of a date after **1840**. It is stored in the third ^- piece of subscript 0 of the (fictitious) EMPLOYEE file entry.
- The fourth field is DEPARTMENT; it is *not* required. It is a pointer to file number 13 and adding new entries (LAYGO) to the (fictitious) DEPARTMENT file from the (fictitious) EMPLOYEE file is *not* allowed as indicated by the apostrophe (') after the number 13. It is stored in the fourth ^-piece of subscript zero of the (fictitious) EMPLOYEE file entry. The internal value of the Employee's department in the (fictitious) DEPARTMENT file is stored in this location. The data of the (fictitious) DEPARTMENT file can be found in ^DIZ(13,

Suppose there is also a Multiple-valued field, SKILL. A Multiple-valued field is described by a separate data dictionary. VA FileMan creates this new data dictionary descendent from a *non-integer* subscript of **^DD**. In the case of the (fictitious) EMPLOYEE file described by **^DD(3)**, it would store subsidiary data dictionaries in **^DD(3.01)**, **^DD(3.02)**, etc. The subsidiary data dictionary for the Multiple-valued SKILL field could look like this:

**Figure 349: Attribute Dictionary—Reading the Attribute Dictionary: Sample Subsidiary Data Dictionary**

```
^DD(3.01,0)="SKILL subfield^^1^2"
^DD(3.01,.01,0)="SKILL^MF^0;1^K:$L(X)>30!($L(X)<3) X"
^DD(3.01,.01,3)="ANSWER MUST BE FROM 3 TO 30 CHARACTERS IN LENGTH"
```

The only new element here is the **M** in the second **^**-piece of **^DD(3.01,.01,0)**. This is the flag corresponding to the **YES** answer to the question:

**Figure 350: Attribute Dictionary—Reading the Attribute Dictionary: Sample Auxiliary User Prompts**

```
HAVING ENTERED OR EDITED ONE SKILL, SHOULD USER BE ASKED ANOTHER?
```

If you answer **YES** to this question, each time the user enters data, the “Select SKILL:” prompt is repeated until the user enters a null response. There is also an entry corresponding to SKILL in the principal (fictitious) EMPLOYEE file’s data dictionary as follows:

**Figure 351: Attribute Dictionary—Reading the Attribute Dictionary: Updated Data Dictionary for New Data**

```
^DD(3,4,0)="SKILL^3.01A^^SX;0"
```

The **3.01** points to the subsidiary data dictionary of that number; it says that, to find the data descriptors of SKILL (and all fields pertaining to SKILL), you *must* look in **^DD(3.01)**. The **A** indicates that every time the user enters a new SKILL, it is *automatically* added to the file and the user is *not* asked:

**Figure 352: Attribute Dictionary—Reading the Attribute Dictionary: Sample User Prompt Confirming Data Entry**

```
ARE YOU ADDING A NEW SKILL?
```

The **SX;0** in the fourth **^**-piece tells us the entire SKILL Subfile is stored descendent from the **SX** subscript in each employee’s record.

## 20 Advanced File Definition

### 20.1 Introduction

When VA FileMan routines are invoked with the local variable **DUZ(0)** set to the at-sign (@), the user is understood by VA FileMan to be an M-proficient developer who has “programmer access.” Those working with programmer access can control certain file-definition options that are otherwise handled invisibly by VA FileMan. These features are described in this section.



**CAUTION:** Programmer access in VistA is defined as **DUZ(0)="@**”. It grants the privilege to become a developer in VistA. Programmer access allows you to work outside many of the security controls enforced by VA FileMan, enables access to all VA FileMan files, access to modify data dictionaries, etc. *It is important to proceed with caution when having access to the system in this way.*



**REF:** For a description of the file and field definition options available to everyone, see the “Creating Files and Fields” section in the *VA FileMan Advanced User Manual*.

### 20.2 File Global Storage

#### 20.2.1 Storing Data in a Global other than ^DIZ

When setting up a new file, (Modify File Attributes option [DIMODIFY]), you can instruct VA FileMan to do either of the following:

- Store the new file’s data in the default **^DIZ** global array, descendent from the file number just assigned.
- Store the new file in another global array.

The dialogue looks like [Figure 353](#):

**Figure 353: File Global Storage—Storing Data in a Global Other than ^DIZ: Sample User Prompts**

```
MODIFY WHAT FILE: TEST
ARE YOU ADDING 'TEST' AS A NEW FILE? Y <Enter> (YES)
FILE NUMBER: 24000// <Enter>
INTERNAL GLOBAL REFERENCE: ^DIZ(24000, //
```

At this prompt ([Figure 354](#)), you either press the **Enter** key to choose the default or you type an explicit global reference. This reference is in the following format:

**Figure 354: File Global Storage—Storing Data in a Global Other than ^DIZ: Global Reference Format**

```
^GLOBAL( or ^GLOBAL(subscript1,subscript2,...
```

The caret (^) preceding **GLOBAL(** need *not* be entered. Extended global reference ([UCI]) can be entered ahead of the global name. If the subscripted global already exists with data in it, a warning message is displayed.



If the subscripted global is a descendent of a global that stores the data for another file, an error message is displayed. For example, if a file's data is stored at:

**Figure 355: File Global Storage—Storing Data in a Global Other than ^DIZ: Sample Global Storage Location of a Subscripted Descendent Global**

```
^GLOBAL(662001,
```

You *cannot* define another file that stores its data at:

**Figure 356: File Global Storage—Storing Data in a Global Other than ^DIZ: Incorrect Global Storage Location of a Subscripted Descendent Global**

```
^GLOBAL(662001,"A",
```

## 20.3 Field Global Storage

### 20.3.1 Assigning a Location for Fields Stored within a Global

When creating a new field, (Modify File Attributes option [DIMODIFY]), press the **Enter** key at the “IS THIS FIELD MULTIPLE” window. If you are a developer, you are asked in a “popup” window for the global subscript and ^-piece position to specify where in each file entry to store the data element being defined. For example, if you were creating a field that you wanted to be stored in the first ^-piece position of the global subscript **DEMOG** for every entry, you would enter the following:

**Figure 357: Field Global Storage—Assigning a Location for Fields Stored within a Global**

```

Field #77 in File #100
FIELD LABEL: EMAIL ADDRESS          DATA TYPE... FREE TEXT
-----
SUBSCRIPT: DEMOG_
AUDIT C | PIECE POSITION: 1
REA -----
DELETE ACCESS:
WRITE ACCESS:
SOURCE:
DESCRIPTION...      TECHNICAL DESCRIPTION...

IS THIS FIELD MULTIPLE... NO

MANDATORY: NO
HELP-PROMPT: Answer must be 1-11 characters in length
EXECUTABLE HELP:

Enter name of MUMPS Global subscript where this Field's data will be stored.
Already assigned:
    0      1      2      3      4      4.5      5      6
    8      9

COMMAND:                               Press <PF1>H for help  Insert

```

To aid in the process, VA FileMan prompts you with the highest subscript previously used for the file, and then, when the subscript has been entered, it prompts the ^-piece position one past the highest previously assigned for that subscript. VA FileMan allows up to **4094** characters of data and data dictionary construction storage capacity in any single global node and that no two fields are assigned to the same subscript and ^-piece position.



**NOTE:** At the bottom of the screen, a list of the Global subscripts already in use is displayed.

### 20.3.2 Storing Data by Position within a Node

If you want to store a field's data by character position within the global node, rather than by ^-piece position. This is called extract storage instead of ^-piece storage. To accomplish this, after specifying a subscript, respond to the ^-piece prompt with ***Em,n***; where *m* is the first character position for data storage and *n* is the last. For example, to store data in character positions 1 to 3 of subscript 20, do the following:

**Figure 358: Field Global Storage—Storing Data by Position within a Node**

```
SUBSCRIPT: 20
^-PIECE POSITION: E1,3
```

One advantage of specifying your field data location using the ***Em,n*** format is that caret (^) can be part of the stored data. It is *recommended* that you do *not* mix extract and ^-piece storage on the same global node.

## 20.4 Assigning Sub-Dictionary Numbers

The [“LANG^DIALOGZ\(\): File Modification for Multiple Languages”](#) section points out that data specifications for subfields of a Multiple are kept in a subsidiary data dictionary. Such a sub-dictionary is stored in the global **^DD(sub-dictionary\_number)**; where **sub-dictionary\_number** is a number with a fractional portion. For example, the specifications for the RESPONSES Multiple in the (fictitious) ORDER (#100) file, are stored in **^DD(100.045)**. Normally, when a new Multiple-valued field is created, VA FileMan automatically assigns the fractional sub-dictionary number. The developer, however, is allowed to choose the desired number.

When creating a new Multiple field, (Modify File Attributes option [DIMODIFY]), if you are a developer, you are asked in a “popup” window for the global subscript at which to store the data element being defined. Under this question is the SUB-DICTIONARY question. The RESPONSES Multiple in the (fictitious) ORDER (#100) file would have been defined like [Figure 359](#).

**Figure 359: Assigning Sub-Dictionary Numbers—Sample Dialogue Assigning Sub-dictionary Numbers**

```

Field #4.5 in File #100
FIELD LABEL: RESPONSES          DATA TYPE... NUMERIC
    TITLE:
    AUDIT:
AUDIT CONDITION:
    READ ACCESS:
    DELETE ACCESS:
W -----
DES | SUBSCRIPT: 4.5
   | SUB-DICTIONARY NUMBER: 100.045
   |-----
IS THIS FIELD MULTIPLE... NO
MANDATORY: NO
HELP-PROMPT: Type a number between 1 and 9999999, 0 Decimal Digits
EXECUTABLE HELP:
-----
Enter name of MUMPS Global subscript where this Field's data will be stored.
Already assigned:
    0
^DD number must be between 100 and 101 and not already used
COMMAND:                          Press <PF1>H for help  Insert

```

## 20.5 Computed Expressions

A developer can enter an executable line of M code at any point where one would normally be allowed to use the computed expression syntax.



**REF:** For more information on computed expression syntax, see the “Computed Expressions” section in the *VA FileMan Advanced User Manual*.

The Computed-Expression M code *must* create a variable **X**, which is understood to be the value of its computation.



**NOTE:** Because of concatenation, **IF**, **FOR**, and **QUIT** statements are *not recommended* in M computed expressions.

### 20.5.1 Computed Dates

A Computed Date has **CD** in the Field Specifier. The **X** value created by the code should look like the [numerical internal form of a Date](#), or a null string if the computation results in no legal date.

### 20.5.2 Computed Pointers

A Computed Pointer has **Cp** in the Field Specifier, followed immediately by the file number of the pointed-to. The **X** value created by the code should look like the numerical internal entry number of an entry in that file, or a null string if the computation results in no legal pointer value.

### 20.5.3 Computed Multiples

A Computed Multiple has **Cm** in the Field Specifier. The code should create a value **X** several times, once for each Multiple. Then, in the same loop, it should EXECUTE **DICMX**. **DICMX** exists at the time the code is used. The code should also create a variable **D** each time. Executing **DICMX** can result in **D** being KILLED, in which case the code should quit its loop.



**NOTE:** A M Computed Expression should be written so that more code can be concatenated to the end of it. **IF** statements, **QUIT** commands, and **FOR** loops should *not* appear. For an expression of any complexity, the best form to use is:

- SET X=\$\$ROUTINE(D0)

Or:

- DO ^ROUTINE

**Figure 360: Computed Expressions—Computed Multiples: Sample Dialogue Creating a Computed Pointer from File #2 to File #200; Pointing at Last User Who Edited Patient**

```
Field #10000 in File #2
FIELD LABEL: LAST USER WHO EDITED          DATA TYPE... COMPUTED
-----
COMPUTED-FIELD EXPRESSION:
A | S X=$P($$LAST^DIAUTL(2,DO,"*"),U,2)
  |   TYPE of RESULT: POINTER
  |   NUMBER OF FRACTIONAL DIGITS TO OUTPUT:
  |   SHOULD VALUE ALWAYS BE ROUNDED:
  |   WHEN TALLING, SHOULD SUMS BE SUMS OF COMPONENT FIELDS:
  |   LENGTH OF FIELD:          POINT TO FILE: NEW PERSON
-----
IS THIS FIELD MULTIPLE... NO

MANDATORY:
HELP-PROMPT:
EXECUTABLE HELP:

COMMAND:                                     Press <PF1>H for help  Insert
```

**Figure 361: Computed Expressions—Computed Multiples: Sample Dialogue Creating a Computed Date that Gives the Patient’s Next Birthday**

```

Field #662000 in File #2
FIELD LABEL: NEXT BIRTHDAY          DATA TYPE... COMPUTED
-----
COMPUTED-FIELD EXPRESSION:
A | S X=$E($P(^DPT(DO,0),U,3),4,7) S X=$S(X:$E(DT,1,3)+($E(DT,4,7)>X)_X,1:" ")
  | TYPE of RESULT: DATE
  |
  | NUMBER OF FRACTIONAL DIGITS TO OUTPUT:
  | SHOULD VALUE ALWAYS BE ROUNDED:
  | WHEN TALLING, SHOULD SUMS BE SUMS OF COMPONENT FIELDS:
  | LENGTH OF FIELD:                POINT TO FILE:
  |
-----
IS THIS FIELD MULTIPLE... NO

MANDATORY:
HELP-PROMPT:
EXECUTABLE HELP:
-----
COMMAND:                               Press <PF1>H for help  Insert

```

## 20.6 MUMPS Data Type

A DATA TYPE field with a value of MUMPS is available to those with programmer access. The input to this field is executable M code. Each field of this type is stored on its own global node using the extract format (**Em,n**).

When a MUMPS field type is created, it is automatically given a WRITE protection of @. Unless this is modified, only those with programmer access can enter data into an MUMPS field type.

Developers are allowed to change the data type of MUMPS to, for example, FREE TEXT. However, the values are still stored in extract format on the subscripted node.

## 20.7 Screened Pointers and Set of Codes

A developer modifying a DATA TYPE field of POINTER is asked:

**Figure 362: Screened Pointers and Set of Codes—Sample User Prompt**

```

SHOULD POINTER ENTRIES BE SCREENED? NO// Y <Enter> (YES)

```

Answering **YES** allows entry of a line of M code. The variable **DIC("S")** is set equal to this code. The code is used in the **DIC** lookup routine to screen out certain entries in the pointed-to file.



**REF:** For details about the use of **DIC("S")**, especially in regard to the naked indicator, see the description of the [^DIC: Lookup/Add API](#) in the [“Classic VA FileMan API”](#) section.

For example, the trick in [Figure 363](#) could be used to make sure that all providers being pointed to from a SURGERY file had an S code in some auxiliary field:

**Figure 363: Screened Pointers and Set of Codes—Sample Screening Code**

```

SCREEN:  S DIC("S")="I $D(^1), $P(^1),U,5) ["S" ""

```

Each pointed-to file defined for a VARIABLE POINTER field can be screened in a similar way.

Also, the developer can put a screen on a DATA TYPE field of SET OF CODES. After the set values have been described, the user is asked:

**Figure 364: Screened Pointers and Set of Codes—Sample User Prompt on Screened Data**

```
SHOULD SET ENTRIES BE SCREENED? NO//
```

Again, answering **YES** allows entry of a line of M code. This code should set the variable **DIC("S")**, which is applied to the selection of the member of the set. When this **DIC("S")** is executed, the variable **Y** contains the internal value of the member of the set.

## 20.8 LABEL REFERENCE Data Type

The user is asked an additional input question for the LABEL REFERENCE data type. The user should specify whether parameters are allowed to be included with the LABEL REFERENCE input.

**Figure 365: Label Reference—Sample User Prompt**

```
PARAMETERS ALLOWED: YES
```

## 20.9 TIME Data Type

The user is asked an additional input question for the TIME data type. The user should specify whether seconds are allowed for TIME input.

**Figure 366: Time—Sample User Prompt**

```
SECONDS ALLOWED: YES// <Enter>
```

## 20.10 YEAR Data Type

The user is asked an additional input question for the YEAR data type. The user should specify the lowest possible date allowed.

**Figure 367: Year—Sample User Prompt**

```
EARLIEST DATE: 1/1/1970
```

## 20.11 FT POINTER Data Type

The user is asked two additional input questions for the FT POINTER data type:

- **POINTER:** Enter an open root that is a global root ending in either an open parenthesis or a comma.
- **LAYGO:** Specify whether adding a new entry is allowed.

**Figure 368: FT Pointer—Sample Use Prompts**

```
POINTER: VA(200,  
LAYGO: YES// <Enter>
```

## 20.12 FT DATE Data Type

The user is asked additional input questions for the FT DATE data type. The user should specify the following:

- EARLIEST DATE: The lowest possible date allowed.
- IMPRECISE DATE: Entering **YES** indicates that the date does not require a day of the month.
- TIME OF DAY: Entering **YES** indicates that a Time value can be entered.
- TIME REQUIRED: Entering **YES** indicates that a Time value *must* be entered.
- SECONDS ALLOWED: Entering **YES** indicates that a seconds can be entered with the time value.

Figure 369: FT Date—Sample User Prompts

```
EARLIEST DATE: 1/1/1970
IMPRECISE DATE: NO// <Enter>
TIME OF DAY: YES// <Enter>
TIME REQUIRED: NO
SECONDS ALLOWED: YES// <Enter>
```

## 20.13 RATIO Data Type

The user is asked four additional input questions for the RATIO data type. The user should indicate the minimum and maximum values for each portion of the ratio.

Figure 370: Ratio—Sample User Prompts

```
LEFT SIDE MINIMUM: (0-9999): 1
LEFT SIDE MAXIMUM: (1-9999): 10
RIGHT SIDE MINIMUM: (1-9999): 1
RIGHT SIDE MAXIMUM: (1-9999): 20
```

## 20.14 INPUT Transform

An INPUT transform is M code for a particular field that is executed to determine if the data for that field is valid.

The M code for some field types' INPUT transforms is automatically generated when you create the field. This is the case for:

- Free Text
- Numeric
- Date/Time
- Computed
- MUMPS
- Screened Pointer field types

The Input Transform (Syntax) option [DIITRAN] of the Utility Functions menu [DIUTILITY] allows those with programmer access to customize the M code in automatically generated INPUT transforms. It also lets you create INPUT transforms for other field types. In the Input Transform (Syntax) option

[DIITRAN], when you select the field, you see an M statement that validates the variable **X** and KILLS it if it is invalid. Here, **X** usually contains the user's response that is being validated. If the DATA TYPE field value is VARIABLE POINTER, **X** contains the value in internally stored format (i.e., "record\_number;storage\_root").

You can rewrite this line of code to meet individual requirements. If desired, the code can transform **X** by resetting it to another value to be filed. An example would be a name transform that deletes an extraneous space character following a comma as shown in [Figure 371](#):

**Figure 371: INPUT Transform—Sample Code**

```
INPUT TRANSFORM: K:$L(X)>30!($L(X)<3) X      Replace K
With S:X[" , " X=$P(X," , ")_"_"_ $P(X," , ",2) K
Replace <Enter>
S:X[" , " X=$P(X," , ")_"_"_ $P(X," , ",2) K:$L(X)>30!($L(X)<3) X
```

Unlike the M code for the [OUTPUT Transform](#), you *can* use the **IF**, **FOR**, and **QUIT** commands in the M code for INPUT transforms.

Once an INPUT transform has been created for a field, the syntax checking that the field performs can no longer be modified using the Modify File Attributes option [DIMODIFY]. A data dictionary listing shows XXXX for such a field.

For a COMPUTED field, the INPUT transform is simply the M code that is executed whenever the field is computed. Hence, a COMPUTED field calculation can be edited by a developer using this option.

For FREE TEXT fields, you can also indicate the maximum *output* length in the Input Transform (Syntax) option [DIITRAN]. The value you enter does *not* affect the length of data that can be entered and stored for the field; that length remains under the control of the INPUT transform code. Only the length output in VA FileMan generated reports is affected. [Figure 372](#) shows a field defined with a maximum (input) length of 30, but an output length of only 10. The Print example shows the truncation of the 20 entered characters to 10.



Figure 372: INPUT Transform—Maximum (Output) Length

```
Select OPTION: UTILITY FUNCTIONS
Select UTILITY OPTION: INPUT TRANSFORM (SYNTAX)

Modify what File: ZSD TEST1// <Enter> (7 entries)
Select FIELD: SHORTENED TEXT
SHORTENED TEXT INPUT TRANSFORM: K:$L(X)>30!($L(X)<1) X
  Replace <Enter>
'HELP'-PROMPT: Answer must be 1-30 characters in length.
  Replace <Enter>
XECUTABLE 'HELP': <Enter>

MAXIMUM LENGTH OF 'SHORTENED TEXT': (1-250): 30// ?

THIS MAXIMUM WILL BE USED FOR OUTPUT PURPOSES, BUT WILL NOT BE PART OF THE INPUT
CHECK FOR THE FIELD.

MAXIMUM LENGTH OF 'SHORTENED TEXT': (1-250): 30// 10

Select OPTION: ENTER OR EDIT FILE ENTRIES

Input to what File: ZSD TEST1// <Enter> (7 entries)
EDIT WHICH FIELD: SHORTENED TEXT
THEN EDIT FIELD: <Enter>

Select ZSD TEST1 NAME: 5 <Enter> Second Entry from ScreenMan
SHORTENED TEXT: 12345678901234567890

Data is 20 characters.

Select OPTION: PRINT FILE ENTRIES

Output from what File: ZSD TEST1// <Enter> (7 entries)
Sort by: <Enter>
First Print FIELD: .01 <Enter> NAME
Then Print FIELD: SHORTENED TEXT
Then Print FIELD: <Enter>
Heading (S/C): ZSD TEST1 List// <Enter>
DEVICE: <Enter> TELNET Right Margin: 80// <Enter>

ZSD TEST1 List                                MAR 29,2016@08:58    PAGE 1
NAME                                           SHORTENED
-----
Another ScreenMan
Entry from ScreenMan
First entry
ScreenMan #3
Second Entry from ScreenMan    1234567890

Output data is 10 characters.

Second entry (2)
Third entry                    MORE THAN
```

## 20.14.1 INPUT Transforms and the Verify Fields Option

INPUT transforms are ordinarily executed before data is filed (in which case the INPUT transform expects data in *external* form, *not yet filed*). But the INPUT transform is also executed by VA FileMan's Verify Fields option [DIVERIFY] (in which case the data being checked is in *internal* form, and *already filed*). Some parts of your INPUT transform may *not* be compatible with data in its internal form or when the data is already filed. For example, you can check to make sure a field's value is *not* stored in a cross-reference before you file it; once you file the entry, however, the field value does exist in the cross-reference and the Verify Fields option [DIVERIFY] would report the entry as invalid.

To help the Verify Fields option [DIVERIFY] report fewer invalid values in this situation, the Verify Fields option sets the variable **DIUTIL** to "**VERIFY FIELDS**" when it is running. You can then check for this variable in your custom INPUT transform and skip any checks that would *not* be compatible with data that is in its internal form or already filed.

For example:

**Figure 373: INPUT Transform—Checking for Variables**

```
I $G(DIUTIL)'="VERIFY FIELDS"
```

The Verify Fields option [DIVERIFY] does *not* execute the INPUT transform for the following field types:

- Screened Pointers
- Screened Set of Codes

## 20.15 OUTPUT Transform

The developer can write an M OUTPUT transform to convert internal data values to a different external form. Use the variable **Y** (*not X*, as used with INPUT transforms).



**NOTE:** Due to concatenation, do *not* use **IF**, **FOR**, or **QUIT** statements when defining OUTPUT transforms. Also, any variables you introduce within an OUTPUT transform (but *not Y*) should be NEWed.

To reverse the above example, suppose you wanted always to display the name field with a space character following the comma, even though the space is *not* stored. You could do something like this:

**Figure 374: OUTPUT Transform—Sample Code**

```
S Y=$P(Y,"")_"", "_$P(Y,"",2,9)
```

In addition to containing M code setting **Y**, OUTPUT transforms can consist of a computed expression. For example, if you wanted always to display the month and year from a date/time field called FOLLOW-UP, you could write:

**Figure 375: OUTPUT Transform—Sample Code with Computed Expression**

```
MONTH(FOLLOW-UP)
```

## 20.16 Special Lookup Programs

At times you can write a lookup program to respond to unique characteristics of a file. The Edit File option [DIEDFILE] on the Utility Functions menu [DIUTILITY] allows you to tell VA FileMan what this program is. The information is stored at `^DD(filenumber,0,"DIC")`. The routine's name *cannot* begin with **DI**. These programs *must* respond to all the variables that [^DIC](#) does.



**REF:** For additional information, see the description of [^DIC](#).

The calls to [DO^DIC1](#), [DQ^DICQ](#), and [FILE^DICN](#) can be quite useful to maintain VA FileMan compatibility. You can tell VA FileMan to ignore these special programs by including an **I** in `DIC(0)`.



**NOTE:** Only the [^DIC](#) call honors the special lookup routines. Those calls that allow the user to specify the indexes ([IX^DIC](#) and [MIX^DIC1](#)), and the Database Server calls ([FIND^DIC](#), [\\$\\$FIND1^DIC](#), and [UPDATE^DIE](#)) all ignore the Special Lookup Program.



**REF:** For assistance with special lookups, contact the VA FileMan developers.

## 20.17 Post-Selection Action

When it is necessary to examine an entry after it has been selected by DIC, the post-selection action can be invoked. The Edit File option [DIEDFILE] on the Utility Functions menu [DIUTILITY] allows you to tell VA FileMan what code to execute upon selection. This is stored at `^DD(filenumber,0,"ACT")` and can be any standard line of M code. If you decide that the entry should *not* be selected, the variable **Y** should be set to `-1`.



**NOTE:** The Database Server calls ([FIND^DIC](#), [\\$\\$FIND1^DIC](#), [UPDATE^DIE](#)) all ignore the Post-Selection Action node.

## 20.18 Audit Condition

You can make a data audit conditional when you define a field as being audited. An audit condition is a line of M code with the characteristics that follow:

- Condition *must* contain an **IF** statement or in some way set **\$T**.
- Audit takes place only if **\$T=1**.
- Variables available to a developer are as follows:

**Table 114: Audit Condition—Variables**

Variable	Description
DA	Internal number of the entry being audited. The <b>DA</b> -array exists if the audit is in a subfile.
DIE	The global root of the file or subfile being audited.
DIIX	A two-piece variable described below: <ul style="list-style-type: none"> <li>• <b>piece 1:</b> <ul style="list-style-type: none"> <li>○ <b>3</b>—If this audit is taking place during a <b>SET</b>.</li> <li>○ <b>2</b>—If this audit is taking place during a <b>KILL</b>.</li> </ul> </li> <li>• <b>piece 2</b>—Field number being edited.</li> </ul>
X	The internal representation of a field's value (i.e., the actual stored value). <b>X</b> is <i>always</i> present, but its value varies based on the first piece of <b>DIIX</b> : <ul style="list-style-type: none"> <li>• If <b>\$P(DIIX,U,1)=3</b>, then <b>X</b> equals the new value in the field.</li> <li>• If <b>\$P(DIIX,U,1)=2</b>, then <b>X</b> equals the old value in the field.</li> </ul>

If the DATA TYPE field value of the field being audited is a POINTER, VARIABLE POINTER, or SET OF CODES, then the internal value of the field and its data type is stored. The old value is stored on node **2.1** of the entry in the AUDIT (#1.1) file and the new value is stored on node **3.1**.

## 20.19 Editing a Cross-Reference

A developer can edit the **SET** and **KILL** statements in a MUMPS cross-reference. The logic for other types of cross-reference *cannot* be edited. After selecting a cross-referenced field in the Cross-Reference A Field option [DIXREF] on the Utility Functions menu [DIUTILITY], choose the Edit File option [DIEDFILE]. You are prompted with the MUMPS cross-reference's current **SET** and **KILL** statements for editing. After you have edited the MUMPS cross-reference, you are given the option of running the *old KILL* logic and of cross-referencing existing data (i.e., of running the **SET** logic).

For *all* types of cross-references, you can describe the cross-reference in the DESCRIPTION field and enter a free text message in the NO-DELETION field. To make a cross-reference uneditable, enter a message in the NO-DELETION field; it should be a “*do not-delete-me*” type of warning, since the message entered is displayed under the type of cross-reference prompt presented to someone inquiring about deleting or attempting to delete the cross-reference. For example, possible messages could be:

- “*PLEASE DO NOT DELETE THIS*”
- “*This field should not be deleted.*”

The NO-DELETION field *must* be null *before* the cross-reference can be deleted.

## 20.20 Executable Help

In addition to placing online help in a field's HELP PROMPT and DESCRIPTION attributes, you can enter EXECUTABLE HELP if you have programmer access. When defining a field's attributes using the Modify File Attributes option [DIMODIFY], you receive the "EXECUTABLE 'HELP':" prompt. Here, you can enter M code that is executed when the user requests help while editing data in the field. If the user enters one question mark, the code is executed *after* the help prompt is displayed. With two question marks, it is executed *before* the field's description is displayed.

# 21 Trigger Cross-References

## 21.1 Introduction

A trigger causes something else to happen. In VA FileMan, you can set up a trigger so that the entry of data in one field automatically updates a second field value. Since a trigger is considered a type of cross-reference on the field for which data is entered, a trigger is logically created under the Cross-Reference A Field option [DIXREF] located on the Utility Functions menu [DIUTILITY].

To understand how a trigger is set up, you *must* first understand that every cross-reference specification describes both:

- What happens when a new value is entered, either initially or when an existing value is changed (**SET** logic).
- What happens when an old value is changed or deleted (**KILL** logic).

In other words, when patient FMPATIENT,ONE is first entered into a file of patients, a FMPATIENT,ONE regular cross-reference on the name is built (and nothing is deleted). Then, when this name is edited (changed) to be FMPATIENT,TWO Q, the following two things happen:

- The FMPATIENT,ONE regular cross-reference is deleted.
- An FMPATIENT,TWO Q regular cross-reference is created.

Finally, when this patient is deleted from the file, the FMPATIENT,TWO Q cross-reference is deleted (and none is created).

When you are using the Cross-Reference A Field option [DIXREF] and you specify a trigger, you *must* identify both what happens when a new field value is entered (either initially or through an edit on an existing value) and when an old value is changed or deleted.

You *must* be careful in setting up any trigger cross-reference, since unexpected effects can sometimes result. At the moment when the trigger actually occurs:

- No validity check is made on the value being forced into the field (in other words, the value does *not* go through the triggered field's INPUT transform).
- Cross-references (if any) do occur on the triggered field (e.g., a triggered field can in turn trigger other fields in a chain reaction!).

## 21.2 Trigger on the Same File

Adding a time and date stamp to the file whenever a particular field is updated is a simple example of a trigger. Suppose the PATIENT (#2) file has a date-valued field called DATE NAME CHANGED. The following figures illustrate how you could put the current date and time into this field whenever the patient's NAME is entered or changed:

**Figure 376: Trigger Cross-References—Creating Trigger**

```
Select OPTION: UTILITY FUNCTIONS
Select UTILITY OPTION: CROSS-REFERENCE A FIELD

MODIFY WHAT FILE: PATIENT <Enter> (1890 entries)
Select FIELD: NAME

CURRENT CROSS-REFERENCE IS REGULAR 'B' INDEX OF FILE

Choose E (Edit)/D (Delete)/C (Create): CREATE
WANT TO CREATE A NEW CROSS-REFERENCE FOR THIS FIELD? NO// Y <Enter> (YES)
CROSS-REFERENCE NUMBER: 2// <Enter>
Select TYPE OF INDEXING: REGULAR// TRIGGER

WHEN THE NAME field (#.01) of the PATIENT File (#2) IS CHANGED, WHAT FIELD SHOULD
BE 'TRIGGERED': DATE NAME CHANGED <Enter> ..OK
```

The field to be triggered *must* already exist.

**Figure 377: Trigger Cross-References—SET Logic**

```
---- SET LOGIC ----

IN ANSWERING THE FOLLOWING QUESTION, 'DATE NAME CHANGED'
CAN BE USED TO REFER TO THE EXISTING TRIGGERED FIELD VALUE.
PLEASE ENTER AN EXPRESSION WHICH WILL BECOME THE VALUE OF THE DATE
NAME CHANGED field (#2) OF THE 'PATIENT' File (#2)
WHENEVER 'NAME' FIELD IS ENTERED OR CHANGED: NOW

DO YOU WANT TO MAKE THE SETTING OF 'DATE NAME CHANGED' CONDITIONAL?
NO// <Enter> (NO)
```

If you answered **YES**, you can set conditions for the trigger. You get the following prompt:

**Figure 378: Trigger Cross-References—KILL Logic**

```
ENTER AN EXPRESSION FOR THE CONDITION: <Enter>

--- KILL LOGIC ---

IN ANSWERING THE FOLLOWING QUESTION, 'DATE NAME CHANGED'
CAN BE USED TO REFER TO THE EXISTING TRIGGERED
FIELD VALUE. NOTE: 'OLD NAME' CAN BE USED TO REFER TO THE VALUE
OF THE NAME FIELD BEFORE ITS CHANGE OR DELETION.
PLEASE ENTER AN EXPRESSION WHICH WILL BECOME THE VALUE OF
THE 'DATE NAME CHANGED' field (#2) OF THE 'PATIENT' File (#2)
WHENEVER 'NAME' IS CHANGED OR DELETED: <Enter> NO EFFECT
```

You have specified that the NAME field triggers the DATE NAME CHANGED field (noting that the NAME field is already cross-referenced in the usual way). You have requested that the current date/time (NOW) be stuffed into the triggered field.

Since this triggering occurs whenever NAME is changed, you do *not* have to specify anything else that depends on the pre-existing value of NAME. When the entire patient entry is deleted, the DATE NAME CHANGED is deleted along with the name. Thus, no **KILL** logic is needed. The response to pressing the **Enter** key at that prompt is “NO EFFECT”.

Since you always want the trigger to take place when NAME is changed, no condition is placed on the trigger. A trigger can be set up that only occurs under specified circumstances.

**Figure 379: Trigger Cross-References—Conditions**

```
WANT TO PROTECT THE 'DATE NAME CHANGED' FIELD, SO THAT  
IT CAN'T BE CHANGED BY THE 'ENTER & EDIT' ROUTINE? NO// YES
```

You specify that the only way you want the DATE NAME CHANGED field to be updated is via this trigger. No Enter or Edit File Entries option [DIEDIT] user (not even one with an at-sign [@]) is able to change a patient's DATE NAME CHANGED field directly.

**Figure 380: Trigger Cross-References—Deletion Restrictions**

```
NO-DELETION MESSAGE: <Enter>
```

If you enter a free text message at this prompt, this cross-reference *cannot* be deleted.

**Figure 381: Trigger Cross-References—Description**

```
DESCRIPTION:  
1>The DATE NAME CHANGED field is triggered whenever the  
2>NAME field is entered or updated. The triggered value is  
3>NOW. This field cannot be edited.  
4><Enter>
```

The description appears in a standard DD listing.

**Figure 382: Trigger Cross-References—Confirmation**

```
...CROSS-REFERENCE IS SET  
  
DO YOU WANT TO RUN THE CROSS-REFERENCE FOR EXISTING  
ENTRIES NOW? NO// <Enter>
```

Finally, you have the option of using the new trigger to update the file. In this case, it would *not* be useful to put the current date and time into the DATE NAME CHANGED field for every existing entry. Thus, the **NO** default is accepted.



## 21.3 Triggers for Different Files

A trigger can also update a field in a file different than the one in which the edited field exists. To illustrate this, the previous example from the “[Trigger on the Same File](#)” section is extended to show how a separate (fictitious) MONITOR file could be updated whenever a patient name is added or changed.

First of all, define this (fictitious) MONITOR file using the Modify File Attributes option [DIMODIFY]. The (fictitious) MONITOR file’s NAME field contains the same value as the NAME field in the PATIENT (#2) file. A TIME field should be defined as a DATA TYPE field of DATE/TIME; this field contains the time the NAME field in the PATIENT (#2) file was added or changed. Use the Cross-Reference A Field option [DIXREF] on the Utility Functions menu [DIUTILITY] to set up the trigger:

**Figure 383: Trigger Cross-References—Sample Dialogue to Create a Trigger Cross-reference on a Field**

```
Select UTILITY OPTION: CROSS-REFERENCE A FIELD

MODIFY WHAT FILE: PATIENT
Select FIELD: NAME

CURRENT CROSS-REFERENCES:
    1    REGULAR 'B' INDEX OF FILE
    2    TRIGGER OF THE 'DATE NAME CHANGED' FIELD OF THE PATIENT
        FILE
Choose E (Edit)/D (Delete)/C (Create): CREATE
WANT TO CREATE A NEW CROSS-REFERENCE FOR THIS FIELD? NO// YES
CROSS-REFERENCE NUMBER: 3// <Enter>
Select TYPE OF INDEXING: REGULAR// TRIGGER

WHEN THE 'NAME' field (#.01) OF THE 'PATIENT' File (#2) IS CHANGED,
WHAT FIELD SHOULD BE 'TRIGGERED': NAME:MONITOR:TIME
DO YOU WANT TO PERMIT ADDING A NEW 'MONITOR' ENTRY? NO// Y <Enter> (YES)
WELL THEN, DO YOU WANT TO **FORCE** ADDING A NEW ENTRY
    EVERY TIME? NO// Y <Enter> (YES)
    ...OK

--- SET LOGIC ---

IN ANSWERING THE FOLLOWING QUESTION, 'TIME'
    CAN BE USED TO REFER TO THE EXISTING TRIGGERED FIELD VALUE.
PLEASE ENTER AN EXPRESSION WHICH WILL BECOME THE
    VALUE OF THE 'TIME' field (#1 ) OF THE 'MONITOR' File (#16001)
WHENEVER 'NAME' IS ENTERED OR CHANGED: NOW

DO YOU WANT TO MAKE THE SETTING OF 'TIME' CONDITIONAL? NO// <Enter> (NO)

--- KILL LOGIC ---

IN ANSWERING THE FOLLOWING QUESTION, 'TIME'
    CAN BE USED TO REFER TO THE EXISTING TRIGGERED FIELD VALUE.
NOTE: 'OLD NAME' CAN BE USED TO REFER TO THE VALUE OF
    THE NAME FIELD BEFORE ITS CHANGE OR DELETION.
PLEASE ENTER AN EXPRESSION WHICH WILL BECOME THE VALUE OF
    THE 'TIME' field (#1) OF THE 'MONITOR' File (#16001)
WHENEVER 'NAME' IS CHANGED OR DELETED: @
ARE YOU SURE YOU WANT TO 'ADD A NEW ENTRY' WHEN THIS
    KILL LOGIC OCCURS? NO// Y <Enter> (YES)

DO YOU WANT TO MAKE THE DELETING OF 'TIME' CONDITIONAL? NO// <Enter> (NO)

WANT TO PROTECT THE 'TIME' FIELD, SO THAT
    IT CAN'T BE CHANGED BY THE 'ENTER & EDIT' ROUTINE? NO// <Enter> (NO)
```

```
NO-DELETION MESSAGE: <Enter>
DESCRIPTION:
1>The TIME field of the Monitor file is triggered whenever
2>the NAME field of the Patient file is entered or changed. The
3>new value=NOW. A new entry in the Monitor file is created
4>at the same time. If the NAME field in the Patient file is
5>deleted, TIME is deleted.
6><Enter>

...CROSS-REFERENCE IS SET
DO YOU WANT TO RUN THE CROSS-REFERENCE FOR EXISTING ENTRIES NOW? NO// <Enter> (NO)
```

This example ([Figure 383](#)) shows the *extended pointer syntax* used to specify a field in another file. The patient's NAME is used as a lookup value in the (fictitious) MONITOR file. A new (fictitious) MONITOR file entry is created by the trigger. In a sense, this trigger really updates two fields in the (fictitious) MONITOR file, NAME, and TIME.

An alternative extended pointer syntax is **NAME IN MONITOR FILE:TIME**. This syntax is exactly equivalent to **NAME:MONITOR:TIME**, and can better express the meaning of the extended syntax if you are a new user.



**NOTE:** The at-sign (@) indicates that a field is to be deleted by the trigger.

## 22 DIALOG File

### 22.1 DIALOG File: User Messages

#### 22.1.1 Introduction

The VA FileMan DIALOG (#.84) file is used to store dialogue that would normally appear on a screen during interaction with a user. This dialogue can include error messages, user help, and other types of prompts. VA FileMan distributes a set of entries in the DIALOG (#.84) file.

The VA FileMan [BLD^DIALOG](#) or [\\$EZBLD^DIALOG](#) APIs are used to move text from the DIALOG (#.84) file into arrays. The text can then be displayed using the display mode of choice.

Developers can add entries to the DIALOG (#.84) file. Entries such as error messages, help messages, and other general prompts can be placed in the file. The DIALOG (#.84) file should *not* be used for storing alternate synonyms either for data or for fields in the data dictionary, such as field labels or descriptions.



**NOTE:** To add entries to the DIALOG (#.84) file, you *must* use a numberspace assigned by the Database Administrator.

Advantages of the DIALOG (#.84) file for user interaction are:

- User interaction can be easily separated from the other program functionality, a necessary step in creating alternate interfaces to roll-and-scroll, such as GUI.
- Text stored in the DIALOG (#.84) file can be re-used.
- Package error lists can be identified and listed by error number in documentation.
- Text can be returned in multiple languages *without* changes to developers' code.



**REF:** For details, see the “[Internationalization and the DIALOG File](#)” section.

#### 22.1.2 Use of the DIALOG File

VA FileMan controls and distributes entries in the DIALOG (#.84) file in the number range **0** through **10000**. These entries should *not* be edited by other package developers, with the exception of adding foreign language equivalents for text.



**REF:** For details, see the “[Internationalization and the DIALOG File](#)” section.

Some of the VA FileMan error messages are available for retrieval by other package developers, using the VA FileMan program calls. These messages are listed in “[Appendix A—VA FileMan Error Codes](#).” Entries within the VA FileMan number range that are *not* in the Error Codes listing should *not* be used, as they are subject to change.

Other packages can make entries in the DIALOG (#.84) file for their own use. The Database Administrator (DBA) assigns number ranges to a subscribing package.

If your package or site already has a file numberspace assigned by the DBA, you can use that number (or numbers) multiplied by **10000** (plus any decimal value between **.001** and **.999**) for adding entries to the DIALOG (#.84) file. For example:

- Kernel owns the NEW PERSON (#200) file, so it can use numbers 2000000 through 2000000.999 in the DIALOG (#.84) file.
- Site 665 owns numberspace 665000 for files, so you can use 6,650,000,000 through 6,650,000,000.999 in the DIALOG (#.84) file.

If developers do *not* follow these guidelines, their DIALOG (#.84) file entries can be overwritten when new packages are installed.



**NOTE:** An entry number does *not* have to be an integer; up to **3** decimal places can be used to identify an entry.

### 22.1.3 Creating DIALOG File Entries

Developers can enter or edit entries to the DIALOG (#.84) file using the VA FileMan Enter or Edit File Entries option [DIEDIT]. The only required fields are:

- DIALOG NUMBER, which uniquely identifies the entry
- TYPE (Error, Help, or General Message)
- TEXT

The dialogue text can contain parameter windows delimited by vertical bars (|). Within a pair of vertical bars, the developer puts a value that corresponds to a subscript in a parameter list. This subscript does *not* need to be numeric, but can be meaningful alpha characters, such as “FIELD”. When the dialogue text with windows is retrieved using a call to either the [BLD^DIALOG](#) or [\\$EZBLD^DIALOG](#) APIs, a subscripted parameter list is input to the call. The parameters are matched by subscript to the windows in the text, and the values from the parameter list are inserted into the corresponding windows in the text. If parameters are included in the text, the INTERNAL PARAMETERS NEEDED field should be set to **YES**. The PARAMETER Multiple field is used in documenting these parameters.

For error messages only, a list of output parameters can also be passed to the [BLD^DIALOG](#) or [\\$EZBLD^DIALOG](#) APIs. This list is returned by the routine in a standard format. Output parameters might be, for example, file or field numbers that the calling routine can then use to make a decision. Output parameters should also be documented in the PARAMETER Multiple.

Another important optional field is the POST-MESSAGE ACTION field. If the developer wishes to perform some special action whenever a message is retrieved, M code is simply inserted into this field. The code is then executed whenever the associated message is retrieved with a call to the [BLD^DIALOG](#) or [\\$EZBLD^DIALOG](#) APIs.

The TRANSLATION (LANGUAGE) Multiple in the DIALOG (#.84) file allows a developer to enter text in a language other than English.



**REF:** For additional information on this feature, see the “[Internationalization and the DIALOG File](#)” section.

Finally, there is a place to enter documentation for the ROUTINE names and LINE TAGs that use the dialogue entries. This is optional internal documentation for use by developers only.

Figure 384 is an example creating a new entry in the DIALOG (#.84) file.

Figure 384: DIALOG File—Sample Dialogue Creating a New Entry in the DIALOG (#.84) File

```
Select DIALOG: 10001
Are you adding '10001' as a new DIALOG (the 239TH)? Y <Enter> (YES)
TYPE: ? <Enter>
Enter code that reflects how this dialogue is used when talking to the users.
Choose from:
1          ERROR
2          GENERAL MESSAGE
3          HELP
TYPE: 3 <Enter> HELP
PACKAGE: VA FILEMAN <Enter> DI
DESCRIPTION:
1>Here we enter a description of the help message itself. This
2>description is for our own documentation.
3><Enter>
EDIT Option: <Enter>
INTERNAL PARAMETERS NEEDED: Y <Enter> YES
TEXT:
1>Here we enter the actual text of the help messages, with
2>parameters designated by vertical bars |1| as shown.
3><Enter>
EDIT Option: <Enter>
Select PARAMETER SUBSCRIPT: 1
Are you adding '1' as a new PARAMETER SUBSCRIPT (the 1ST for this DIALOG)? Y
<Enter> (YES)
PARAMETER DESCRIPTION: Brief description of parameter 1 goes here. For
documentation only.
Select PARAMETER SUBSCRIPT: <Enter>
POST MESSAGE ACTION: ? <Enter> This is Standard MUMPS code. This code will be
executed whenever this message is retrieved through a call to BLD^DIALOG or
$$EZBLD^DIALOG
POST MESSAGE ACTION: S MYVAR="HELP #10001 WAS REQUESTED"
Select LANGUAGE: <Enter>
Select ROUTINE NAME: DIKZ// <Enter>
ROUTINE NAME: DIKZ// <Enter>
LINE TAG: // <Enter>
```

## 22.2 Internationalization and the DIALOG File

### 22.2.1 Role of the VA FileMan DIALOG File in Internationalization

The VA FileMan DIALOG (#.84) file is used to store dialogue that would normally appear on a screen during interaction with a user. The DIALOG (#.84) file becomes especially important in assisting developer support for *non-English* speaking users, because it allows easy entry and retrieval of *non-English* dialogue *without* making any changes to code that is already using the DIALOG (#.84) file.

### 22.2.2 Use of the DIALOG File in Internationalization

A system variable, **DUZ(LANG)**, identifies to VA FileMan the language currently in use. This system variable is set equal to a number that corresponds to the ID NUMBER of an entry in the LANGUAGE (#.85) file.



**REF:** For more information, see the “[VA FileMan LANGUAGE File](#)” section.

This number is also used as a subscript for the TRANSLATION (LANGUAGE) Multiple in which *non-English* text can be stored.



**NOTE:** For users running Kernel 8.0 or later, this variable is set automatically during signon.

For every entry needing translation in the DIALOG (#.84) file, the developer should populate the FOREIGN TEXT field for the desired language. When either of the text retrieval routines, [BLD^DIALOG](#) or [\\$SEZBLD^DIALOG](#), is called, if **DUZ("LANG")** is greater than one (1), VA FileMan looks at the language location specified by **DUZ("LANG")** to find the text. If text *cannot* be found at that location, VA FileMan defaults to use the English equivalent from the TEXT field. As with English text, parameters to be inserted into the text can be passed to the call.



**REF:** See also the [BLD^DIALOG\(\): DIALOG Extractor](#) and [\\$SEZBLD^DIALOG\(\): DIALOG Extractor \(Single Line\)](#) APIs.

### 22.2.3 Creating Non-English Text in the DIALOG File

Once an entry exists in the DIALOG (#.84) file, developers can enter or edit *non-English* equivalents for the TEXT field, using VA FileMan's Enter or Edit File Entries option [DIEDIT].

**Figure 385: DIALOG File—Sample Dialogue to Create Non-English Text in the DIALOG (#.84) File**

```
Select DIALOG: 10001 <Enter> This is English text for a test message.
.
.
.

Select LANGUAGE: ?
Answer with TRANSLATION LANGUAGE
    You may enter a new TRANSLATION, if you wish
    Enter the number or name for a non-English language.
    English language cannot be selected.
Answer with LANGUAGE ID NUMBER, or NAME
Choose from:
2      GERMAN
3      SPANISH
4      FRENCH
5      FINNISH
6      ITALIAN
10     ARABIC
11     RUSSIAN

Select LANGUAGE: 2 <Enter> GERMAN
Are you adding '2' as a new TRANSLATION (the 1ST for this DIALOG)? Y <Enter>
(Yes)
FOREIGN TEXT:
1>Here is where we enter the non-English text.
```

## 22.3 VA FileMan LANGUAGE File

### 22.3.1 Introduction

Certain types of data (e.g., dates and numbers) should be formatted differently for display depending on the language of the end user. The VA FileMan LANGUAGE (#.85) file is designed to help solve this problem for users of interactive VA FileMan. The LANGUAGE (#.85) file stores M code used to perform language-specific conversions on such data. A system variable identifies to VA FileMan the language currently in use. The LANGUAGE (#.85) file can store 2, 3, and 4-character abbreviations for the language.

At this time, VA FileMan distributes in the LANGUAGE (#.85) file only in the English equivalent of language-specific data conversions specified in [Table 115](#).

### 22.3.2 Use of the LANGUAGE File

A system variable, **DUZ**(“**LANG**”), identifies to VA FileMan the language currently in use. This system variable is set equal to a number that corresponds to the ID NUMBER of an entry in the LANGUAGE (#.85) file. It tells VA FileMan where to find the appropriate data conversion code from the LANGUAGE (#.85) file at the time the code needs to be executed (e.g., when printing a date).



**NOTE:** For users running Kernel 8.0 or later, this variable is set automatically during signon.

Developers can enter or create their own entries in the LANGUAGE (#.85) file. The Database Administrator assigns an ID NUMBER for each unique language entry in the LANGUAGE (#.85) file. If developers do *not* follow these guidelines, their language entry may be overwritten when VA FileMan is installed.

[Table 115](#) lists the LANGUAGE (#.85) file entries that have been assigned and are distributed with VA FileMan:

**Table 115: LANGUAGE (#.85) File—Language Entries**

Entry #	Value
1	English
2	German
3	Spanish
4	French
5	Finnish
6	Italian
10	Arabic
11	Russian

When installing VA FileMan via a KIDS build, the LANGUAGE (#.85) file is updated to include entries for all **ISO 639-2:1998** (as revised 11/21/2012) languages.

### 22.3.3 Creating LANGUAGE File Entries

Developers can enter or edit entries in the LANGUAGE (#.85) file using VA FileMan’s Enter or Edit File Entries option [DIEDIT]. The only required fields are:

- ID NUMBER that uniquely identifies a language.
- NAME of the language.

If M code is *not* found within the current language for a specific conversion, VA FileMan defaults to use the English equivalent.

The other fields that can be entered for any LANGUAGE (#.85) file entry are described in [Table 116](#). At the time the code in any of these fields is executed, the data to be converted is in the local variable **Y**. The M code in the field should put the transformed output back into **Y**, without altering any other local variables.



**NOTE:** More detail can be found in the field description for each field. Looking at the English equivalent in entry number **1** can also be helpful.

**Table 116: LANGUAGE (#.85) File—Other Fields**

Field	Description
ORDINAL NUMBER FORMAT	Changes 1 to 1ST, 2 to 2ND, etc.
CARDINAL NUMBER FORMAT	Changes 1234567 to 1,234,567.
UPPERCASE CONVERSION	Converts text to uppercase.
LOWERCASE CONVERSION	Converts text to lowercase.
DATE/TIME FORMAT	Converts date in internal VA FileMan format to: <b>MMM,DD,YYYY@HH:MM:SS</b>
DATE/TIME FORMAT (FMTE)	Does other date conversions from date in internal VA FileMan format. This call has an additional input flag that indicates the conversion to be done (see below).

[Table 117](#) lists the Date/Time flags:

**Table 117: LANGUAGE (#.85) File—Date/Time Flags**

Flag	Format	Description
1	MMM DD, YYYY@HH:MM:SS	Space before year.
2	MM/DD/YY@HH:MM:SS	No leading zeroes on month, day.
3	DD/MM/YY@HH:MM:SS	No leading zeroes on month, day.
4	YY/MM/DD@HH:MM:SS	--
5	MMM DD,YYYY@HH:MM:SS	No space before year.
6	MM-DD-YYYY @ HH:MM:SS	Special spacing for time.
7	MM-DD-YYYY@HH:MM:SS	--
S	--	Always return seconds.



<b>Flag</b>	<b>Format</b>	<b>Description</b>
U	--	Return uppercase month (use only with 1 or 5).
P	--	Return time with am, pm.
D	--	Return only date without time.

## 23 VA FileMan Functions (Creating)

### 23.1 Introduction

As mentioned in the “VA FileMan Functions” section in the *VA FileMan Advanced User Manual*, as a developer in VA FileMan you can create your own computed-expression functions. In some ways, a function can be thought of as an OUTPUT transform that can work on any field. For example, you may have a preference for seeing many dates displayed as 20-7-69, rather than the JUL 20,1969 format that VA FileMan typically produces. Since this date is internally stored in the form 2690720 (see the description of %DT), you could write a line of code that took the internally stored format in the variable X and transformed it using:

**Figure 386: VA FileMan Functions—Sample Code that Takes an Internally Stored Format in a Variable and Transforms It**

```
+$(E(X,6,7)_"-"_+$(E(X,4,5)_"-"_$(E(X,2,3)
```

### 23.2 Function File Entries

This is exactly what you are allowed to do when you edit the FUNCTION (#.5) file using the Enter or Edit File Entries option [DIEDIT].

To continue the above example, you could create a DASHDATE function, which could then be used by any user to display date-valued fields and expressions in the DAY-MONTH-YEAR format as follows:

**Figure 387: VA FileMan Functions—Sample Displaying Date-Valued Fields and Expressions in the DAY-MONTH-YEAR Format**

```
Select OPTION: ENTER AND EDIT FILES
INPUT TO WHAT FILE: FUNCTION
EDIT WHICH ATTRIBUTE: ALL// <Enter>
Select COMPUTED-FIELD FUNCTION: DASHDATE
ARE YOU ADDING 'DASHDATE' AS A NEW COMPUTED-FIELD FUNCTION? Y <Enter> (YES)
MUMPS CODE: S X=+$(E(X,6,7)_"-"_+$(E(X,4,5)_"-"_$(E(X,2,3)
EXPLANATION: PRINTS DATE IN "DD-MM-YY" FORMAT
DATE-VALUED: NO
NUMBER OF ARGUMENTS: 1
WORD-PROCESSING: <Enter>
```

Notice that the MUMPS CODE field contains code to transform the variable X (the argument of the function) into a different X. If two arguments were required for the function, the first would be found in the variable X1 and the second in X. Although the new function being created here takes a date-valued argument, it is *not* itself considered to be date-valued since it does *not* produce values that look like the standard VA FileMan internal representation of a date. If this function was only meaningful in a word-processing context, you would put a W at the “WORD-PROCESSING:” prompt.



**NOTE:** If there is an output transform on a field, the function code is applied to the field after it has been transformed. In most cases, if a field has an OUTPUT transform, you should therefore use the following syntax:

```
FUNCTION_NAME ( INTERNAL ( FIELD_NAME ) )
```

Rather than:

```
FUNCTION_NAME ( FIELD_NAME ) .
```

A function can also be defined as taking no arguments. This is very similar to the special variables in M like **\$I** and **\$H**. For example, you could define a function like BELL as follows:

**Figure 388: VA FileMan Functions—Sample Function without Arguments**

```
Select COMPUTED-FIELD FUNCTION: BELL
  ARE YOU ADDING A NEW COMPUTED-FIELD FUNCTION? Y <Enter> (YES)
MUMPS CODE: SET X=$C(7) <Enter>
EXPLANATION: CAUSES A 'BEEP' TO OCCUR ON OUTPUT <Enter>
DATE-VALUED: NO
NUMBER OF ARGUMENTS: 0
WORD-PROCESSING: <Enter>
```

Users could then embed “beeps” in output templates by entering:

```
FIRST PRINT FIELD: BELL
```



**NOTE:** No parentheses are shown for a function that has no arguments.

You can delete a function in the usual way by deleting the NAME of the function. Such deletions do *not* harm any computed fields that already have been created using the function. However, you *cannot* edit the computed field unless you remove reference to the deleted function.



**CAUTION:** Due to concatenation, do *not* use IF, FOR, or QUIT statements when defining functions. Also, any variables you introduce within a function’s code (but *not* X, X1, etc.) should be NEWed.

The FUNCTION (#.5) file already contains several functions.



**REF:** For a description of the functions exported with VA FileMan, see the “VA FileMan Functions” section in the *VA FileMan Advanced User Manual*.

## 24 DIFROM

### 24.1 Introduction

DIFROM is the mechanism that was used *in the past* to transfer software packages from one VA FileMan environment to another.



**NOTE:** DIFROM has been *superseded* by the Kernel Installation and Distribution System (KIDS) for this function, starting with Kernel 8.0. DIFROM can still be used, for the time being, for the purpose of package export between VA FileMan systems where Kernel has *not* been installed. DIFROM is *not* supported for use within the VA.

Package transfer is a two-stage process:

1. DIFROM is run on the source system. It is a *nondestructive* process that uses the **^UTILITY** global to build data structures and store information about the package.
2. DIFROM creates init routines. Later, on the target system, the init routines are run to recreate each component of the package and put them into place according to the installer's instructions.

Another component of the package export process is the PACKAGE (#9.4) file.



**NOTE:** The PACKAGE (#9.4) file inits, **DIKPI\***, are *not* included in the VA FileMan 22.2 KIDS distribution.

A PACKAGE (#9.4) file entry contains information about the components of a package. It also indicates how the installation will proceed on the target system. The PACKAGE (#9.4) file also has fields that document the package production and installation process. PACKAGE (#9.4) file entries can be created using the standard VA FileMan editing options.

## 24.2 Exporting Data

### 24.2.1 Preparing To Run DIFROM

DIFROM simply creates routines, “init routines.” DIFROM names routines by appending **INI\*** or **I###** to the package namespace (e.g., nmspI005 or nmspINI1). It overwrites any like-named routines. Except for replacing routines with the same name, DIFROM is *nondestructive*, and unlike the init installation process, neither changes nor destroys data. The DIFROM user should ensure that there is sufficient disk space to hold the init routines DIFROM creates.



**CAUTION:** As of Kernel 8.0, DIFROM has been *superseded* by the Kernel Installation and Distribution System (KIDS) for the function of transferring software packages from one VA FileMan environment to another. DIFROM can still be used for the time being for the purpose of package export between VA FileMan systems where Kernel has *not* been installed.

## 24.2.2 PACKAGE File and DIFROM


The PACKAGE (#9.4) file is used both to document a software package and to aid in exporting the package. A PACKAGE (#9.4) file entry is *not* required to build inits; inits can be built on-the-fly. Some of the fields are used for documentation only and some for both the export process and documentation. Whenever you build an init using an entry in the PACKAGE (#9.4) file, that entry is also put into the PACKAGE (#9.4) file of the target system when the init is run. Thus, a copy of the documentation for the package is on both the source and target systems.



The fields that DIFROM uses during the package export process are described in [Table 118](#). All fields not noted below are used for documentation only:



- [NAME](#)
- [PREFIX](#)
- [Template Multiples](#)
- [EXCLUDED NAME SPACE](#)
- [ENVIRONMENT CHECK ROUTINE](#)
- [PRE-INIT AFTER USER COMMIT](#)
- [POST-INITIALIZATION ROUTINE](#)
- [FILE](#)
- [Other PACKAGE File Fields](#)

**Table 118: DIFROM—Fields Used during the Package Export Process**


Field	Description
NAME	This is a brief ( <b>4-30</b> characters) name describing the package. It is used to identify the package and does <i>not</i> affect the init directly. However, it is the key field used when installing the PACKAGE (#9.4) file entry on the target system. If you change the name and install a package on a system where it already exists under a different name, a new entry is created in the PACKAGE (#9.4) file on the target system. The unchanged old entry remains, too.
PREFIX	This is the <b>2-4</b> character namespace of the package. It is the unique identifier for the package. The PREFIX controls which templates, options, bulletins, etc., are included in the init routines for export. Those components with names beginning with the package's PREFIX are <i>automatically</i> exported, except for those beginning with the letters in the EXCLUDED NAME SPACE Multiple.
Template Multiples	There is a Multiple field for each of the following template types: <ul style="list-style-type: none"> <li>• INPUT</li> <li>• SORT</li> <li>• PRINT</li> <li>• SCREEN (FORM)</li> </ul> The developer uses these Multiples to have the init include templates in addition to those within the PREFIX namespace. Each of these Multiples contains the free-text name of a

Field	Description
	<p>template and the number of the file associated with that template (a pointer to the FILE of Files).</p> <p> <b>NOTE:</b> For SCREEN (FORM) templates, all blocks pointed-to by exported forms are <i>automatically</i> included in the init regardless of their namespace. The blocks need <i>not</i> be specified by the developer.</p>
EXCLUDED NAME SPACE	<p>The developer can use the EXCLUDED NAME SPACE Multiple to exclude templates, options, bulletins, etc., that are a subset of the package's namespace. For example, if the namespace of a package were PRC and the EXCLUDED NAME SPACE Multiple contained the entry PRCZ, then any of the components of the package with names beginning with "PRCZ" would <i>not</i> be exported.</p>
ENVIRONMENT CHECK ROUTINE	<p>When the installer starts the init, the routine identified in the ENVIRONMENT CHECK ROUTINE field is run <i>before</i> any of the init routines DIFROM created and before any questions are asked. The installer <i>cannot</i> interrupt the init process until this routine has completed. Thus, this pre-init should be used to simply examine the environment; it should <i>not</i> change any data.</p>
PRE-INIT AFTER USER COMMIT	<p>The routine named in the PRE-INIT AFTER USER COMMIT field runs after the installer has committed to proceeding with the install but before any data is updated. This routine can edit or delete data. The developer uses this routine to make any data conversions, etc., that need to be performed <i>before</i> the init brings in new data.</p>
POST-INITIALIZATION ROUTINE	<p>The routine named in the POST-INITIALIZATION ROUTINE field runs <i>after</i> the inits put everything in place. Here, the developer makes any data conversions, etc., that need to be performed <i>after</i> the new data is installed.</p>
FILE	<p>This is a Multiple field used to describe how the data dictionaries (DDs) and data from the exported files are to be handled in the inits.</p> <p>The following fields are included within the FILE Multiple:</p> <ul style="list-style-type: none"> <li>• <b>FILE</b> <p>This field contains the number of the file to be exported. It is a pointer to the FILE (#1) file of files.</p> </li> <li>• <b>FIELD</b> <p>This optional Multiple within the FILE Multiple allows the developer to send a subset of the fields from a file. If only some of the fields are being exported, a "partial" file is being sent. If no entries are made in the FIELD Multiple, all of the fields from the file are exported. Only the names of fields at the top-level of a file can be entered. Thus, single fields at the top-level and entire Multiples with all the subfields and subfiles descendent from those Multiples can be sent.</p> </li> </ul>

Field	Description
	<p>The <b>.01</b> field is <i>automatically</i> sent, whether or not it appears in this Multiple, unless the file being exported is the NEW PERSON (#200) file. If a partial of File #200 is being sent, the <b>.01</b> is sent only if it is included in this Multiple or if the PREFIX is <b>XU</b> (Kernel's namespace).</p> <p> <b>NOTE:</b> This list only applies to the information about fields found in the data dictionary. It is <i>not</i> possible at this time to send a subset of the actual data.</p> <ul style="list-style-type: none"> <li> <p><b>ASSIGN A VERSION NUMBER</b></p> <p>If this SET OF CODES field is <b>YES</b>, the version number entered by the developer while running DIFROM to build the init is used to create the following node when the init is run on the target system:</p> <pre data-bbox="764 783 1222 806">^DD(File#,0,"VR")=Version Number</pre> <p>The version number is that of the package being installed, <i>not</i> the VA FileMan version number.</p> <p>If this field is <b>NO</b> or left null, a "VR" node is <i>not</i> built by the init. Thus, whatever was present in this node on the target system remains. Once a "VR" node has been set, the developer should continue to update it with each version. Otherwise, the node contains the wrong version.</p> </li> <li> <p><b>UPDATE THE DATA DICTIONARY</b></p> <p>This SET OF CODES field controls whether or not a pre-existing DD on the target system is updated during the init. The DD is included in the init routines regardless of how this question is answered. If a DD for the file does <i>not</i> exist on the target system, it is always installed.</p> <p>If this field is <b>YES</b> or left null, the DD in the init overlays an existing DD on the target system.</p> <p> <b>NOTE:</b> The existing DD on the target system is <i>not</i> deleted first. For example, if a field is changed from one type to another, it is possible that the DD information from the previous definition of the field is left behind. This situation can cause problems for VA FileMan. If this might happen, the developer is urged to clean up the field from the DD in a pre-init, using a call to <a href="#">^DIK</a>.</p> <p>If this field is <b>NO</b>, the DD currently on the target system is <i>not</i> changed. The developer can still send data for the file.</p> </li> <li> <p><b>MAY USER OVERRIDE DD UPDATE</b></p> <p>If this SET OF CODES field is <b>YES</b>, the installer decides if a</p> </li> </ul>

Field	Description
	<p>pre-existing DD is overwritten. When the init routine runs, the question, “Shall I write over the existing Data Definition?” is asked if there is a pre-existing DD on the target system.</p> <p>If the installer answers this question <b>NO</b>, the existing DD is <i>not</i> changed. This feature is useful when a package contains some DDs that are unchanged from the previous version. If the DD is <i>not</i> found on the target system, it is brought in by the init regardless of this field’s contents.</p> <p>If answered <b>NO</b> or left null, the installer <i>cannot</i> choose whether or not to <i>not</i> bring in the DD.</p> <p> <b>NOTE:</b> If there is a screen on the DD, the question is <i>not</i> asked regardless of the contents of this field. The result of the screen’s test determines if the new DD is installed or <i>not</i>.</p> <ul style="list-style-type: none"> <li>• <b>SCREEN TO DETERMINE DD UPDATE</b> <p>The developer can enter M code in this field to examine the target environment to determine whether or <i>not</i> to bring in a DD. The code should set the value of <b>\$T</b>:</p> <ul style="list-style-type: none"> <li>○ If <b>\$T is true</b>, the new DD is installed.</li> <li>○ If <b>\$T=0</b>, the new DD is <i>not</i> installed.</li> </ul> <p>If the developer enters a screen, the installer is <i>not</i> given the option of installing the DD. The screen alone determines whether or <i>not</i> the DD is installed.</p> <p> <b>NOTE:</b> If the DD does <i>not</i> exist on the target system, the screen is ignored and the incoming DD is installed.</p> </li> <li>• <b>DATA COMES WITH FILE</b> <p>If this SET OF CODES field is <b>YES</b>, DIFROM picks up <i>all</i> of the data for the file from the system on which the developer builds the init. This data is included in the init routines. Data from <i>all</i> fields is sent even if the developer is only sending selected fields from the DD. Pointers are <i>not</i> resolved to their external values. Thus, data with pointers should <i>not</i> be sent if the pointed-to entries can be in different locations on the target system.</p> <p>If this field is <b>NO</b> or left null, the init does <i>not</i> pick up data. The contents of the following two fields are ignored:</p> <ul style="list-style-type: none"> <li>○ MERGE OR OVERWRITE SITE’S DATA</li> <li>○ MAY USER OVERRIDE DATA UPDATE</li> </ul> </li> <li>• <b>MERGE OR OVERWRITE SITE’S DATA</b> <p>This SET OF CODES field controls how exported entries are combined with existing ones on the target site. The possible values are:</p> </li> </ul>



Field	Description
	<ul style="list-style-type: none"> <li>○ “m” (MERGE); default.</li> <li>○ “o” (OVERWRITE).</li> </ul> <p>When an init is installed, incoming entries and subentries are checked to see if they match ones on the target system.</p> <p> <b>REF:</b> A detailed description of this process is given in the <a href="#">“DIFROM: Running an INIT (Steps 1-16)”</a> section.</p> <p>If a match is <i>not</i> found, the entry or subentry is added. The contents of this field determine what happens to entries that do match.</p> <p>If incoming entries are to be merged with existing ones, fields with <i>non</i>-null values are left unchanged on the target system. Data from the init is placed into fields with null values.</p> <p>If incoming entries are to overwrite existing ones, fields with <i>non</i>-null values in the init overwrite values currently on the target system. If the field is null in the init and the field on the target system contains data, the current value is <i>not</i> overwritten with a null value.</p> <ul style="list-style-type: none"> <li>• <b>MAY USER OVERRIDE DATA UPDATE</b></li> </ul> <p>If this SET OF CODES field is <b>YES</b>, the installer can decide whether or <i>not</i> to install the data from the init. The installer can choose to bring in the data or <i>not</i> to bring it in. However, the merge/overwrite flag <i>cannot</i> be changed; merge <i>cannot</i> be switched to overwrite, and vice versa.</p> <p>If the field is <b>NO</b> or left null, the installer <i>cannot</i> choose if the target system’s data is updated or <i>not</i>.</p>
Other PACKAGE File Fields	<p>Other PACKAGE (#9.4) file fields are used only for documentation and do <i>not</i> affect the DIFROM procedure. One of the documentation fields, SHORT DESCRIPTION, is required. It is a free text field of up to <b>60</b> characters. Other documentation fields include:</p> <ul style="list-style-type: none"> <li>• ROUTINE</li> <li>• GLOBAL</li> <li>• VERSION</li> <li>• DEVELOPMENT ISC</li> <li>• KEY VARIABLE</li> </ul> <p>There are fields to document the development, verification, site installation, and patch history. This data describing the package is bundled and exported with the rest of the package. It is put into the recipient’s PACKAGE (#9.4) file.</p> <p>Some of the documentation fields are updated on the target system when the init is run. For example, the date/time that the pre- and post-inits are run is <i>automatically</i> recorded in the PACKAGE (#9.4) file entry as is the version number.</p>

## 24.3 Order Entry and DIFROM

DIFROM for VA FileMan was customized to support Order Entry. Order Entry inits *must* export records from the PROTOCOL (#101) file. This file contains pointers back to itself, similar to the OPTION (#19) file. Since DIFROM does *not* currently resolve these pointers, a joint effort was made by Order Entry and VA FileMan developers to support Order Entry inits that correctly install the protocols.



**REF:** For details, see Order Entry documentation.

Basically, the process involves the creation of a second set of routines, similar to init routines, to export the Order Entry protocols and to resolve the pointers in the PROTOCOL (#101) file. An Order Entry routine, **ORVOM**, is run to create these routines. The resulting routines are named *nmspONI\**, the **ONIT** routines. These routines are run at the target site after the init routines to install the protocols.

The following considerations pertain to the creation of Order Entry inits:

- Like regular inits, Order Entry inits can be created either based on an entry in the PACKAGE (#9.4) file or on-the-fly.
- Order Entry's file Order Parameters contains the PACKAGE PARAMETERS Multiple. This Multiple controls the export and installation of entries from the PROTOCOL (#101) file. Thus, it is used like the PACKAGE (#9.4) file. To export entries from the PROTOCOL (#101) file in a sophisticated way, use the PACKAGE PARAMETERS instead of building the export on-the-fly.

If the developer is going to use the PACKAGE PARAMETERS, there *must* be a PACKAGE (#9.4) file entry. Then, create an entry in the PACKAGE PARAMETERS Multiple within the ORDER PARAMETERS (#100.99) file. The **.01** field of this Multiple is a DINUMed pointer to the PACKAGE (#9.4) file entry. This implies that the namespace *must* be the same as that used for the init.

- Whether the Order Entry init is built from the PACKAGE PARAMETERS or on-the-fly, next run the **ORVOM** routine. The **ORVOM** routines look at the PACKAGE PARAMETERS (if they exist) or prompt the developer for the names of protocols to be sent. They build **ONIT** routines that are similar to inits but contain only PROTOCOL (#101) file entries. The code generated in these routines installs and resolves pointers on the PROTOCOL (#101) file entries. (The **ORVOM** routines are part of the Order Entry package and are maintained by the Order Entry developers. They were reviewed by the VA FileMan developers.)
- If the init is being built from an entry in the PACKAGE (#9.4) file, enter the namespaced **ONIT** routine into the POST-INITIALIZATION ROUTINE field in the PACKAGE (#9.4) file entry. It is run *automatically* as a post-init.

If the init is *not* being built from the PACKAGE (#9.4) file, the developer *must* tell the installers to run the **ONIT** routines *manually after* they run the init routines.

- Now, build the actual init using DIFROM in a normal way as described in the "[Exporting Data](#)" section.

DIFROM has been modified for Order Entry to *automatically* pick up the entry from the PACKAGE PARAMETERS Multiple of the ORDER PARAMETERS (#100.99) file. When the init is run any pointers back to the PROTOCOL (#101) file that are contained in this entry are resolved.



**REF:** For more information about resolving pointers during package installation, see the documentation on "[DIFROM: Running an INIT \(Steps 1-16\)](#)."

## 24.4 Running DIFROM (Steps 1-17)

Running DIFROM is an interactive process. Prompts are presented to which the developer responds. The dialogue is described in the topics that follow. In addition, the internal workings of the DIFROM process are detailed. The different parts of running DIFROM are shown in the order in which they occur:

1. [Starting DIFROM](#)
2. [Preliminary Validations](#)
3. [Package Identification](#)
4. [Identifying Init Routines](#)
5. [Specifications for Exported Files](#)
6. [Entering Current Version Information](#)
7. [Including Templates \(No Package File Entry\)](#)
8. [Including Other Package Components](#)
9. [Exporting File Security](#)
10. [Specifying Routine Size](#)
11. [DIFROM Gathers Miscellaneous Package Components](#)
12. [DIFROM Builds Routines Containing Data Dictionaries](#)
13. [DIFROM Builds Routines Containing Data Values](#)
14. [DIFROM Builds Routines Containing Security Access Codes](#)
15. [DIFROM Gathers Templates and Forms](#)
16. [DIFROM Completes Building Routines of Package Components](#)
17. [DIFROM Completes the Code that Runs the Init](#)



**CAUTION:** DIFROM is *not* to be used by VA developers. DIFROM has been replaced by the Kernel Installation and Distribution system (KIDS).

### 24.4.1 Starting DIFROM

In order to run DIFROM, the developer *must* have programmer access [i.e., **DUZ(0)** contains @]. There is no menu option for running DIFROM. It *must* be run by using the following M command from programmer mode:

```
D ^DIFROM
```

### 24.4.2 Preliminary Validations

DIFROM compares the version number from the second line of the DIFROM routine with the VA FileMan version node from the MUMPS OPERATING SYSTEM (#.7) file. This node is **^DD(“VERSION”)**. If the version numbers do *not* match, an error message is displayed and the program exits.

DIFROM then makes sure **DUZ(0)**[“@”]. If *not*, the developer sees an error message and the program exits.

### 24.4.3 Package Identification

DIFROM prompts the developer for the 2-4 character package name (namespace). DIFROM uses these characters to do a lookup for a matching PREFIX on the PACKAGE (#9.4) file. If a match is found, DIFROM uses information from the PACKAGE (#9.4) file entry when building the init.

Even if no matching entry is found, the process continues. In that situation, DIFROM prompts the developer for the necessary information that is otherwise stored in the PACKAGE (#9.4) file. In this way, an init can be built on-the-fly.

### 24.4.4 Identifying Init Routines

DIFROM creates a routine name by appending the suffix **INIT** to the package's namespace. The developer is informed of the name. DIFROM determines whether a routine called *nmsp***INIT** is already on the system. If one exists, DIFROM prints a warning. The developer decides whether or *not* to continue.



**NOTE:** DIFROM has been superseded by the Kernel Installation and Distribution System (KIDS) for this function, starting with Kernel 8.0. DIFROM can still be used, for the time being, for the purpose of package export between VA FileMan systems where Kernel has *not* been installed.



**NOTE:** The **INI\*** routines that DIFROM creates overlay any **INI\*** routines with the same name that exists on the system. This situation does *not* cause problems when running inits. However, to avoid confusion for the user, it is suggested that previous init routines under the same namespace be deleted before rebuilding the init.

### 24.4.5 Specifications for Exported Files

DIFROM asks the developer whether any data dictionaries (DDs) are included with the init. The developer *must* answer **YES** in order to include either DDs or file data.

If the init is being built from a PACKAGE (#9.4) file entry, the developer is given the option to display online the information in the FILE Multiple from the relevant PACKAGE (#9.4) file entry. If the FILE Multiple has no entries or if the developer is building an init without the PACKAGE (#9.4) file, the developer is prompted for a list of files to be included in the init.

If the developer does *not* want to accept the PACKAGE (#9.4) file information as shown or if the init is being built on-the-fly, DIFROM allows the developer to enter or edit the FILE Multiple's data. This data specifies how to include the files in the init and what installation options the installer has at the time the init is run on the target system. The documentation describing the FILE Multiple of the PACKAGE (#9.4) file details the questions the developer sees and the significance of the answers.

A developer can send only some of the fields from a file (i.e., send a partial file). The **FIELDS** Multiple contains a list of exported fields when a partial file is being exported. Normally, the **.01** field of a file is automatically exported even if it is *not* specified in the **FIELDS** Multiple. However, the developer has the option of sending or *not* sending the **.01** field of **NEW PERSON** (#200) file. If a partial of File #200 is being sent and the package does *not* have Kernel's namespace (**XU**), the **.01** field is sent only if it is specified for export.

If the init is being built from a PACKAGE (#9.4) file entry, DIFROM next loops through each of the template Multiples. It builds a list of the templates to be included in the init. There are Multiples for the following templates:

- INPUT
- PRINT
- SORT
- SCREEN (FORM)

The developer uses these Multiples to send templates that are *not* within the package’s namespace.

### 24.4.6 Entering Current Version Information

DIFROM prompts for information that is required by the VA Programming Standards and Conventions (SAC) to appear on the second line of all routines. The developer *must* enter the following:

- Package name (if it *cannot* be picked up from the PACKAGE [#9.4] file)
- Version number
- Date distributed

The existing PACKAGE (#9.4) file entry is updated with this information. The version number entered at this step is used to build target system nodes that look like the following line of code in [Figure 389](#):

**Figure 389: DIFROM—Entering Current Version Information: Sample Code**

```
^DD(File#,0,"VR")=Version Number
```

### 24.4.7 Including Templates (No Package File Entry)

DIFROM asks the developer “Do you want to include all the templates?”, if the init is *not* being built from a PACKAGE (#9.4) file entry:

- Answer **YES**—The init includes *all* templates associated with the files being sent, regardless of their namespace.
- Answer **NO**—Only namespaced templates are included.



**NOTE:** If there is a PACKAGE (#9.4) file entry, namespaced templates and templates in the template Multiples are *automatically* sent.



**REF:** For details, see the “[DIFROM Gathers Templates and Forms](#)” section.

### 24.4.8 Including Other Package Components

DIFROM asks the developer if the following should be included in the init:

- OPTIONS
- BULLETINS
- SECURITY KEYS
- FUNCTIONS
- HELP FRAMES

Whereas templates are always sent with the init, the developer *must* specifically ask that these other components be included. The developer's choices are saved in a list. Only components in the package's namespace are included. There is currently no way to send items that are *not* namespaced. Also, if their namespace appears in the EXCLUDED NAME SPACE Multiple in the PACKAGE (#9.4) file, they are *not* sent.

### 24.4.9 Exporting File Security

DIFROM asks the developer whether security codes (e.g., READ, WRITE, and LAYGO access) should be sent with the DDs.

### 24.4.10 Specifying Routine Size

DIFROM prompts the developer for maximum routine size. This size determines how large the init routines that contain the data is going to be. The routines that contain the code that is executed to install the data are of fixed size. DIFROM obtains the default value for maximum routine size from ^DD("ROU"). The size of the init routines *cannot* be less than 2000 characters. The upper limit should be set in accordance with current portability standards.

### 24.4.11 DIFROM Gathers Miscellaneous Package Components

At this point, the interactive part of building the init is complete. DIFROM now uses the information provided by the developer along with data stored in the PACKAGE (#9.4) file entry (if one exists) to build the init routines.

DIFROM first checks the developer's answers to the questions about sending OPTIONS, BULLETINS, SECURITY KEYS, FUNCTIONS, and HELP FRAMES. For each one that the developer elected to send, DIFROM reads through entries in the associated file and picks up those entries in the package's namespace. For each one, DIFROM makes sure that the name is *not* included in one of the entries from the EXCLUDED NAME SPACE Multiple. For example, if an OPTION's name is PRCZ TEST OPTION and the namespace of the init is PRC, the OPTION is a candidate for export. However, if PRCZ is entered in the EXCLUDED NAME SPACE Multiple of the PACKAGE (#9.4) file entry, the OPTION is *not* sent. The data for each component to be included in the init routines is loaded into the ^UTILITY global.

Namespaced bulletins can be sent. However, data in the MAIL GROUP Multiple, a pointer to the MAIL GROUP (#3.8) file, is *not* sent. On the target system, the installer is reminded that mail groups can be added to bulletins.

### 24.4.12 DIFROM Builds Routines Containing Data Dictionaries

DIFROM builds the routines containing the DDs, data, and file security. To save space in the init routines, cross-references are *not* sent. They are rebuilt when the inits are run on the target system. DDs are turned into routines that hold parts of each data dictionary node on separate lines. The global reference is listed on one line; its value is recorded on the next line. Thus, for each node in the data dictionary there are two corresponding lines in the init routine.

The routine lines that hold data dictionary information begin with two semicolons. This format conforms to the VA programming standard for using \$TEXT to reference routine lines. When the data dictionaries are put into place during the init process, the lines are referenced using indirection as follows:

**Figure 390: DIFROM—Using Indirection to Reference DDs Put into Place during the Init Process: Sample Code**

^DD(442,0)="value"	becomes	;;^DD(442,0)
		;;="value"

If the “value” is too long to fit on a single line, it is divided between two lines. The first “value” line starts with a tilde (~) and the second with an equal sign (=).

If the installer chooses to update the data dictionaries, data dictionary nodes on the target system are overwritten. This brings in newly-defined fields, including specifications for cross-references or triggers. It also replaces existing field definitions (data dictionary nodes) with incoming definitions. Thus, revisions of existing fields can occur. However, the process does *not* alter nodes that exist on the target system but that are *not* in the incoming data dictionary. For example, if a field has been deleted from the source system’s data dictionary, that field is *not* deleted on the recipient’s system. Instead, a pre-init program can be used to delete obsolete fields and obsolete data dictionary nodes.

If auditing is turned on at the sending site, the DD node indicating that auditing should occur is sent. In this situation, auditing is turned on at the installing site if the data dictionaries are updated.

### 24.4.13 DIFROM Builds Routines Containing Data Values

DIFROM stores data values differently than it stores data dictionary information. The recipient’s data dictionaries can be updated directly, node by node, but data *must* first be evaluated for a match of entries. As described in the “[DIFROM: Running an INIT \(Steps 1-16\)](#)” section, updating of the target system’s data is done only after checking for matches. For this reason, the init routines first store data values in a ^UTILITY global structure that is rebuilt on disk on the target system. This allows the existing and incoming values to be compared.

The routines that DIFROM creates to transport data are similar in structure to the ones created to transport data dictionaries. The nodal address and associated values are maintained on separate program lines. The structure as it appears on the target system and as it is contained in the init routines is:

**Figure 391: DIFROM—Routines Data Transport Structure: Sample Code**

```
^UTILITY(U,$J,file#,entry#,node)="value"  
  
    transported as      ;;^UTILITY(U,$J,file#,entry#,node)  
                        ;;="value"
```

### 24.4.14 DIFROM Builds Routines Containing Security Access Codes

DIFROM creates a separate global array for storage of security Access codes if the developer indicates that they should be sent with the package. Security codes are extracted from the data dictionaries and saved in another routine. The nodes containing security information, such as write protection on a field, are *not* in the same routine as the data definition of the field.

When the package is installed, the recipient is asked whether security codes should be updated. A positive response invokes a special program that puts the nodes containing security information back in the DD structures. For example:

**Figure 392: DIFROM—Nodes Containing Security Information in the DD Structures—Sample Code**

```
^DIC(442,0)                is always installed  
^DIC(442,0,"DD")="@"      is only installed upon user request
```



DIFROM sends most file security codes only if the developer has answered **YES** to the question about sending security. However, the following two kinds of field level security codes are always sent:

- **Write Access**—If set to the ^ (a write-protected field) or the @ (programmer access required), or if the field is a MUMPS-type field.
- **Delete Access**—If set to the @ (programmer access required) or if the field is a MUMPS-type field.

### 24.4.15 DIFROM Gathers Templates and Forms

Next, DIFROM puts INPUT, PRINT, and SORT templates into ^UTILITY. It then puts FORMS (SCREEN TEMPLATES) into ^UTILITY along with any BLOCKS that are pointed-to by the FORMS being included. DIFROM uses the list compiled during the interactive dialogue with the developer to select templates. Namespaced templates, with the exception of any in the EXCLUDED NAME SPACE Multiple of the PACKAGE (#9.4) file entry, are always included. In addition, any templates in the template Multiples are also included. If the init being built does *not* have a corresponding PACKAGE (#9.4) file entry and the developer asked to send *all* templates, *all* templates associated with the files being sent in the init are selected regardless of their namespace.

FILEGRAM and EXTRACT templates are sent along with the other entries in the PRINT TEMPLATE (#.4) file. However, the templates used by the Export Tool (Selected Fields for Export and Export) are *never* included by DIFROM when a package's components are assembled. These templates *must* be created at the local site.

### 24.4.16 DIFROM Completes Building Routines of Package Components

DIFROM reads through everything it stored in the ^UTILITY global and builds init routines containing the information. This information includes:

- TEMPLATES
- OPTIONS
- BULLETINS
- SECURITY KEYS
- FUNCTIONS
- HELP FRAMES



**NOTE:** Except for TEMPLATES, only those components in the package's namespace can be sent.

The PACKAGE (#9.4) file entry, if any, is *automatically* included with the init. This entry is added to the target system when the init is run. It completely replaces an entry with the same name at the target site. This entry is a record of what was included with the init.

### 24.4.17 DIFROM Completes the Code that Runs the Init

DIFROM's final step is to build those routines that contain the code that is executed when the init is run. The code retrieves and installs all of the data components that are being sent. The code that goes into the *nmspINI0*, *nmspINI1*, *nmspINI2*, *nmspINI3*, *nmspINI4* and *nmspINIT* routines is nearly identical for all regular inits. (If the package's namespace is less than 4 characters, the routines are named *nmsINIT0* to *nmspINIT4*.)



## 24.5 Importing Data

### 24.6 DIFROM: Running an INIT (Steps 1-16)

A package is installed on the target system by “running the init” for the package. Here, the process for installing a package from inits is described in the order in which it occurs.

1. [Preliminary Steps](#)
2. [Check of Version Number](#)
3. [Running Environment Check Routine \(DIFROM and DIFQ Variables\)](#)
4. [Determining Install Status of DDs and Data](#)
5. [Determining Install Status of Security Codes](#)
6. [Determining Install Status of other Package Components](#)
7. [Starting the Update](#)
8. [Running the Pre-Init after User Commit Routine](#)
9. [Installing Data Dictionaries](#)
10. [Installing Data](#)
11. [Reindexing Files](#)
12. [Installing Other Package Components](#)
13. [General Processing](#)
14. [Special Processing](#)
15. [Running the Post-Initialization Routine](#)
16. [Recording the Install on the Target System](#)

#### 24.6.1 Preliminary Steps

As a safeguard, the target system should always be backed up before running an init. This allows the system to be restored should an error, possibly corrupting the database, occur when the init is run.

To ensure that the installer has complete access to all files being installed during an init, the installer should have programmer access when running the init.

Init routines *must* be run from programmer mode after the routines have been loaded onto the target system. For example, to run an init with the package namespace of ZZTK, do the following:

**Figure 393: DIFROM—Running an Init: Sample Code**

```
>D ^ZZTKINIT
```

## 24.6.2 Check of Version Number

When an init is built, the VA FileMan version number of the source system is put into the init routine. When the init is run, that version number is compared to the version number of the target system that is stored in the MUMPS OPERATING SYSTEM (#.7) file node, **^DD("VERSION")**. If the init was built using a version of VA FileMan later than the one on the target system, an error message is displayed and the installer is *not* allowed to continue running the init.

This precaution is necessary because a newer version of VA FileMan may contain features and DD structures that are *not* recognized by previous versions. Trying to use the new features or to install the new structures on an older system could cause the installation to fail or to produce undesirable results.

## 24.6.3 Running Environment Check Routine (DIFROM and DIFQ Variables)

The ENVIRONMENT CHECK ROUTINE is a field in the PACKAGE (#9.4) file that can indicate a routine to run as part of the init process. If the developer has included a routine name in the ENVIRONMENT CHECK ROUTINE field, this routine is run next. The routine is written by package developers to provide capabilities *not* possible from the init routines alone.

The developer's Environment Check routine can be used to explore the current system and halt the init process under certain conditions. For example, if a prior version of the package *must* be initialized before this one, a warning message might be displayed and the process halted.

The **DIFQ** variable is used to stop the init process. Within the Environment Check routine, the developer may **KILL DIFQ** if conditions warrant the stopping of the init process.

The **DIFROM** variable is defined throughout the init process. It contains the version number of the incoming package. The developer can use it for checking in any pre- or post-init routines.

## 24.6.4 Determining Install Status of DDs and Data

The init determines which file's data dictionaries and data values are installed on the target system. Based on the parameters the developer included in the init in combination with the environment encountered at the target site, the installer is asked a series of questions for each file.



**NOTE:** With the one exception mentioned below, no changes are made on the target system at this time. The answers obtained are saved to be used later in the installation process when the target system is updated.

The exported files are checked one-by-one. What happens to each file is described in the list that follows:

- The name of the file is displayed to the installer whether or not a partial DD is being sent and whether or not data is coming with the file. If there is *not* a file with the same file number on the target system, the DD is installed and the installer is next presented with the questions concerning the installation of the data.
- If there is already a file under that number and the names are the same, the init tells the installer:

You already have the "*file name*" File.

- If there is a file with that number, but the file names do *not* match, the installer is asked if the name should be replaced. The default response is **NO**. In the event of miss matched file names, the following instructions are provided:
  - If the installer is sure that the files are really the same and that just the name has been changed, this question should be answered **YES**. In this case, the init does a [DIE](#) call to change the name of the file on the target system. (This is the only situation in which the target system is altered during this phase of the install.) The init then continues with the dialogue as if the file names had matched in the first place.
  - If the installer determines that the files are *not* the same and answers **NO**, then the init asks if the incoming file should replace the file currently on the system. If the installer answers **NO** to this question, the current file is left unchanged. However, this choice results in the installation of an incomplete package. Therefore, if this happens, the installation should probably be stopped and the package developer consulted.
  - If the installer chooses to replace the file on the target system, the init asks if the current file's data and templates should be kept. Based on the answers to these questions, the current DD (and optionally the data and templates) is deleted, before the new DD is brought in. A call to DIU is set up to do the DD deletion and also to delete the data and templates if the installer so instructs.



**REF:** For additional information, see the description of [EN^DIU2](#).

- If to this point the DD is installed, the init checks if the developer defined a screen to determine whether or not to install the DD. The existence of a developer-defined screen overrides the installer's ability to decide if the DD should be installed. If the screen exists and its conditions are *not* met, the DD is *not* installed but the init continues. The package developer should indicate what to do when the screen stops the DD from installing.
- If the developer decided to let the installer determine if the DD is installed, the init asks if an existing DD should be overwritten. If the installer answers **NO**, the existing DD is unchanged. Package developers should indicate when it is okay to answer this question **NO**.
- If data is being brought with the DD and the package developer decided to ask the question, the installer is asked whether to overwrite the target system data or merge it with the incoming data. The package developer determines whether data merges or overwrites; the installer can decide if the data is installed, *not* how it is installed. The developer should advise the installer on how to answer this question.
- If the developer did *not* give the installer the option of installing the data or not, the init just indicates whether the data merges with or overwrites the current data.

## 24.6.5 Determining Install Status of Security Codes

If the developer sent file security Access codes with the file, the init asks if security codes present on the target system should be overwritten. In most cases, file security is built into files by the developer. However, if there are local security codes that need to be preserved, the installer should answer this question **NO**.



**NOTE:** Even if the installer says *not* to bring in security codes, the init installs the following field security:

- **Write Access**—If set to the ^ (a write-protected field) or the @ (programmer access required), or the field is a MUMPS-type field, Write Access security is installed.
- **Delete Access**—If set to an @ (programmer access required) or the field is a MUMPS-type field, Delete Access security is installed.

## 24.6.6 Determining Install Status of other Package Components

The installer is notified of the kinds of components included in the init. The init asks whether or not to overwrite existing components with the same name. The possible components are:

- INPUT TEMPLATES
- SORT TEMPLATES
- PRINT TEMPLATES, SCREEN TEMPLATES (FORMS)
- OPTIONS
- FUNCTIONS
- BULLETINS
- SECURITY KEYS
- HELP FRAMES

The developer should instruct the installer if it is all right *not* to install any of the components included in the init.

## 24.6.7 Starting the Update

Finally, the init asks “ARE YOU SURE EVERYTHING’S OK?” To this point, there are many chances to stop the init with no changes having been made to the target system. However, if the installer answers:

- **YES**—Init proceeds to install the package.
- **NO**—Init process is safely halted.

## 24.6.8 Running the Pre-Init after User Commit Routine

First, the init runs the PRE-INIT AFTER USER COMMIT routine if the developer included a routine name in the PRE-INIT AFTER USER COMMIT field in the PACKAGE (#9.4) file.

The developer’s PRE-INIT AFTER USER COMMIT routine does things that are *not* possible with the init routines alone. Often, it cleans up DDs or data on the target system *before* the init routines bring in any of the new DDs or data. For example, obsolete fields or parts of field definitions can be removed from data dictionaries.

## 24.6.9 Installing Data Dictionaries

The init installs the data dictionaries for files sent with the init. The data dictionaries are then reindexed.

Data dictionaries are set in place node-by-node, integrating with what already exists. In other words, if a node is brought in by the DD that exists on the target system, the existing node is replaced. However, if a node that is *not* included in the init exists on the target system, the init does *not* delete that node. This feature allows users to create local fields and cross-references.

However, this does mean that the developer *must* carefully consider what the target system's data dictionary looks like after installation. For example, if the developer in the account used to build the init changes the definition of a field or removes a cross-reference, the field or cross-reference *must* be deleted, or otherwise cleaned up on the target account by the PRE-INIT AFTER USER COMMIT routine. This cleanup ensures that the data dictionary does *not* end up with an inconsistent structure after the init.

Further, each line of a WORD-PROCESSING field resides on a separate node. Thus, a change in one of the field attributes that is a WORD-PROCESSING field (e.g., field description or technical description) *cannot* completely overwrite a pre-existing attribute. If the incoming value has fewer lines than the pre-existing one, the install does *not* delete the surplus lines automatically.

## 24.6.10 Installing Data

The init brings in data that was sent with the files.

Depending on the developer's specifications, incoming data either overwrites or merges with data existing on the target system. In either case, if an incoming entry or subentry does *not* exist on the current system, one is added. If an existing entry or subentry is found and if data is to be overwritten, each field's value is replaced with *non-null* incoming values. Null values do *not* overwrite existing values. If data is to be merged, only those fields with null values are updated with incoming values. Hence, when merging, new values are added without altering any pre-existing ones.

Since the installation of data is dependent on whether or not an incoming entry or subentry already exists on the target system, the init *must* determine if they are the same. The process, described as follows, is repeated for each incoming entry or subentry:

- **Checking the B Cross-reference or Zero Node**

The **B** cross-reference holds the entry's name (.01 field) along with the internal entry number. If a **B** cross-reference exists for the file, it is searched for an existing value that matches the incoming one. (The **B** cross-reference holds the name as a subscript.) The maximum length of subscripts is defined for each operating system and is stored in the MUMPS OPERATING SYSTEM (#.7) file. The init uses this length, for example, 63 (default) or 99 as the limit of characters to compare.

Files occasionally lack a **B** cross-reference. In this case, the init examines the actual data (first piece of the entry's zero node) for a match of values.

If a match (either of the **B** cross-reference or of the first piece of the zero node) is *not* found, the incoming entry is considered new and is added to the file. If a match is found, additional checks (discussed below) are made to determine whether the entries can be associated.

- **Using the Internal Entry Number to Verify a Match**

Once a match of the .01 fields of the incoming and existing entries is found, the init determines whether the internal entry numbers of the two entries are related. If the file has a defined .001 field, internal entry number is a meaningful attribute of an entry. In this situation, when the name and internal entry numbers match, identifiers are checked to verify the match.

If the INPUT transform of the **.01** field contains **DINUM**, it operates in the same way as a **.001** field. In this case, the **.01** field and the internal entry number *must* match for the entries to be considered the same.

After a match is established based on the **.001** field (or DINUMed **.01** field), the identifiers are checked. If the identifiers for the two entries are the same, the entries are considered the same. If the identifiers do *not* match, the new entry is *not* installed at all.

- **Using Identifiers to Verify a Match**

If the file is *not* referenced by number (i.e., **.001** field does *not* exist) and there are duplicate **B** cross-references or entries in the file with duplicate **.01** fields, the init *cannot* resolve the ambiguity without identifiers. A well-designed file uses one or more identifiers so that each entry is unique with respect to name and identifiers. If the file lacks identifiers and a **.001** field, the init associates the incoming entry with the first existing entry with a matching name.

If identifiers exist, the init gets the global location of the identifier (piece position) from the data dictionary and uses indirection to retrieve the identifier's value from the **^UTILITY** storage global. This value is then compared with the existing entry's identifier value for a match. Only identifiers that have valid field numbers are used in this process.

The init matches identifiers in the same way it matches **.01** fields. If the values of all the incoming identifiers match the existing ones, the two entries are considered to be the same. If the values do *not* match, the possibility of identity is rejected and the search continues. If none of the values for existing entries matches the incoming entry, the incoming entry is considered new and is added to the file. However, as mentioned above, if a **.001** field exists or the **.01** field is DINUMed, the entry is *not* installed if the identifiers differ.

Once the internal entry number on the target system for matching entries is found, it is used to place the incoming data, either by merging with or overwriting existing values.



**NOTE:** No audit trail is kept of data brought in by an init even if the audit flag is on for a field receiving data.

### 24.6.11 Reindexing Files

Once all the new data has been integrated, the files are reindexed. If any of the files have compiled cross-references, the compiled cross-reference routines are rebuilt. Then, if any data was sent for a file, the init reindexes *all* cross-references for *all* records in the file. Only the **SET** logic is executed.

### 24.6.12 Installing Other Package Components

The init brings in the remaining components built into the init. They are installed in the following order:

1. Help Frames
2. Bulletins
3. PACKAGE (#9.4) file entry for the package being installed
4. PACKAGE PARAMETER Multiple from the ORDER PARAMETERS (#100.99) file (an Order Entry file)
5. Options

6. Security Keys
7. Functions
8. Print Templates
9. Sort Templates
10. Input Templates
11. Blocks associated with Screen Templates (Forms)
12. Screen Templates (Forms) themselves

The init might contain some or all of these components. They consist of entries that are placed into pre-existing files. Many of them are prefixed with the package namespace.

There is special coding in DIFROM to bundle and install data sent from files, such as:

- HELP FRAME (#9.2)
- BULLETIN (#3.6)
- OPTION (#19)
- INPUT TEMPLATE (#.402)

For example, DIFROM resolves pointers for these files. It does *not* resolve pointers for data sent for other files in an init. To resolve pointers, DIFROM replaces, in the init routines, a pointer to another file with the pointer's external value. When the data is installed at the target site, the init routines use this external value for a lookup in the **B** cross-reference of the pointed-to file. When the corresponding entry number is found, the external value is replaced with this entry number as the new pointer value. Thus, the values of pointer fields are correct for the data brought in by the init.

### 24.6.13 General Processing

The general process used for installing each of the package components is described in this section. Component-specific special processing is described in the "[Special Processing](#)" section.

The init reads the name of the incoming entry from the **^UTILITY** global and searches for a matching name in the relevant file's **B** cross-reference. The cross-reference for the HELP FRAME (#9.2) file, for example, looks like this:

**Figure 394: DIFROM—Sample HELP FRAME (#9.2) File Cross-Reference**

```
^DIC(9.2, "B", entryname, DA)
```

If an exact match is *not* found, the incoming entry is considered new and is added as a new file entry. If an exact match is found, [Special Processing](#) is done. Each different type of entry has its own special processing. Unless noted in the "[Special Processing](#)" section, the entire matching old entry is deleted from the target system *before* the new entry is installed.

For either new or replaced entries, other [Special Processing](#), such as resolving pointers, is done for each different type of entry. This processing is also described in detail below.

Finally, all cross-references on the new or replaced entry are reindexed (**SET** logic only).



**NOTE:** *Not* all files are reindexed.

## 24.6.14 Special Processing

[Table 119](#) lists the component-specific special processing with DIFROM.

**Table 119: DIFROM—Special Processing**

Process	Description
HELP FRAMES	<p>If an exact match is found for a HELP FRAME entry, only the existing WORD-PROCESSING field TEXT and the Multiple fields RELATED FRAME and INVOKED BY ROUTINE are deleted from the existing entry. Then, the new entry is brought in on top of the old one.</p> <p>For all entries brought in by the init, the init loops through the RELATED FRAME Multiple and resolves the POINTER field RELATED FRAME, which is a pointer back to the HELP FRAME (#9.2) file.</p>
BULLETINS	<p>If a matching entry is found, the old entry in the BULLETIN (#3.6) file is deleted. However, entries in the bulletin's MAIL GROUP Multiple (which identify recipients of the bulletin) present on the target system before the install remains associated with the bulletin after the incoming bulletin is installed.</p> <p>The init displays each bulletin brought in by the init and reminds the installer to "Remember to add mail groups for new bulletins."</p>
PACKAGE FILE ENTRIES	<p>The current date/time is stuffed into the field DATE INSTALLED AT THIS SITE field, within the VERSION Multiple for the current version of the package.</p> <p>The POINTER field PRIMARY HELP FRAME is resolved.</p>
PACKAGE PARAMETERS entry in the ORDER PARAMETERS (#100.99) file (an Order Entry file)	<p>The following POINTER fields are resolved:</p> <ul style="list-style-type: none"> <li>• DISPLAY GROUP DEFAULT</li> <li>• PROTOCOL TO EXPORT</li> <li>• DEFAULT PROTOCOL</li> <li>• MENU</li> </ul> <p>If pointers to the PROTOCOL (#101) file <i>cannot</i> be resolved because the pointed-to protocol <i>cannot</i> be found, the init routines add a new entry to the PROTOCOL (#101) file (with just a .01 field) in order to resolve the pointer. This is done because PROTOCOLS are exported in a special set of routines (called <b>ONIT</b> routines) that are normally executed as a post-init.</p>
OPTIONS	<p>If a matching entry is found, the entire old entry is <i>not</i> deleted. Only the DESCRIPTION field (a WORD-PROCESSING field) and the ITEMS Multiple (containing menu items) are deleted from the old entry before the new one is brought in.</p> <p>For example, if the site has a local lock on an OPTION, and no lock is brought in by the init, the local lock is preserved.</p> <p>The following pointer fields and the .01 field of the ITEMS Multiple (which points back to the Option file) are <i>all</i> resolved:</p> <ul style="list-style-type: none"> <li>• SERVER BULLETIN</li> <li>• SERVER MAIL GROUP</li> <li>• PACKAGE</li> </ul>



Process	Description
	<ul style="list-style-type: none"> <li>HELP FRAME</li> </ul>
SECURITY KEYS	No special processing, except that if a matching entry is found in the target system, it is merged rather than replaced. Note that pointers in the SUBORDINATE KEY Multiple are <i>not</i> resolved; so, data should <i>not</i> be exported in that Multiple.
FUNCTION	No special processing is done for the FUNCTION (#.5) file.
PRINT, INPUT, and SORT TEMPLATES	The only special processing done for these templates is that after they are all installed, compiled PRINT and INPUT templates are <i>automatically</i> recompiled. The init uses the system's preferred routine size from the MUMPS OPERATING SYSTEM (#.7) file when compiling these templates. It is possible that the recipient of the init could already have routines with the same names that the compiling routine uses. Thus, the developer should warn the installer of the routine names that are used by incoming compiled templates, especially if the developer is sending templates that are <i>not</i> namespaced.
SCREEN TEMPLATES (FORMS)	Any BLOCKS that are pointed-to by FORMS are <i>automatically</i> included in the init routines. The BLOCKS are installed first, with no special processing. Then, the FORMS are installed. Finally, pointers to the BLOCK (#.404) file from the FORM (#.403) file are resolved.

### 24.6.15 Running the Post-Initialization Routine

At the developer's discretion, there can be a routine identified in the POST-INITIALIZATION ROUTINE field in the PACKAGE (#9.4) file. This routine is written by the package developers and provides added capability that is *not* possible within the init routines alone.

If the developer has included a POST-INITIALIZATION ROUTINE in the init, it is run now.

The POST-INITIALIZATION ROUTINE can be used to do cleanup after all of the other components contained in the init have been installed. For example, it might:

- Delete obsolete options and update OPTION (#19) file pointers.
- Check the status of such things as file protection.
- Issue some additional information to the installer.
- Perform some sort of data conversion. For example, the routine might move some old data to a new location in a file to match a changed data dictionary.

### 24.6.16 Recording the Install on the Target System

If pre- or post-init routines were included, the PACKAGE (#9.4) file fields that track the date and time that those routines were run are updated with the current date and time. If any new files were added to the target system, the record count of the FILE (#1) file is updated to reflect the new files.

Then, the init routines update any VERSION number nodes on the files that have been specified by the Package developer.

Finally, the VERSION number node is set in the PACKAGE (#9.4) file entry (if any).

The init is now complete.



## 25 Appendix A—VA FileMan Error Codes

### 25.1 Introduction

This section describes the error codes returned by VA FileMan’s Database Server (DBS) Application Programming Interfaces (APIs). When an error condition is recognized, the following are returned to the client application:

- An error code
- The text of the error
- When appropriate, one or more parameters

The “[How the Database Server \(DBS\) Communicates](#)” section describes in detail the array structure in which this information about the error is returned.

Section [25.2](#), “[Error Codes](#),” lists error codes that are ordered by error code number. Each error code includes the following components:

- Error Number.
- **Description**—The condition that produced the error.
- **Text**—The text of the error message. Within the text, information that is inserted into the message at the time it is created is represented by a parameter name surrounded by vertical bars (“|”). For example, in the text of [Error 201](#), you see “|1|”. Parameter **1** represents the variable name that is missing or invalid. When the message is created, the name of the variable causing the error is substituted into the text for the |1|.
- **Parameters**—The parameters associated with the error message. Each parameter is followed by a short description. The names of the parameters identify both the place within the text of a message into which they are inserted and the subscript in the **PARAM** array that identifies them. Some parameter names are constant in all appropriate error messages:
  - **FILE**—Representing file number.
  - **FIELD**—Representing field number.
  - **IENS**—Representing the Internal Entry Number String (IENS).

If you need to identify in your application code the file, field, or entry that caused an error, check these subscripts of the **PARAM** array. Of course, if no parameters are listed, this indicates that there are none associated with the particular error condition.

### 25.2 Error Codes

#### Error 101

DESCRIPTION:

The option or function can only be done if DUZ(0)="@", designating the user as having programmer access.

TEXT:

Only those with programmer access can perform this function.

PARAMETERS:

None.

## Error 110

### DESCRIPTION:

An attempt to get a lock timed out. The record is locked and the desired action *cannot* be taken until the lock is released.

### TEXT:

The record is currently locked.

### PARAMETERS:

- **“FILE”**—File or subfile number.
- **“IENS”**—Internal Entry Number String (IENS) of entry numbers.

## Error 111

### DESCRIPTION:

An attempt to get a lock timed out. The File Header Node is locked, and the desired action *cannot* be taken until the lock is released.

### TEXT:

The File Header Node is currently locked.

### PARAMETERS:

**“FILE”**—File number.

## Error 120

### DESCRIPTION:

An error occurred during the execution of a VA FileMan hook (e.g., an INPUT transform, DIC screen). The type of hook in which the error occurred is identified in the text. When relevant, the file, field, and IENS for which the hook was being executed are identified in the **PARAM** nodes. The substance of the error is usually identified by a separate error message generated during the execution of the hook itself. That error is usually the one preceding this one in the **DIERR** array.

### TEXT:

The previous error occurred when performing an action specified in a |**1**|.

### PARAMETERS:

- **“1”**—Type of VA FileMan executable code.
- **“FILE”**—File number.
- **“FIELD”**—Field number.
- **“IENS”**—Internal Entry Number String (IENS).

## Error 200

### DESCRIPTION:

There is an error in one of the variables passed to a VA FileMan call or in one of the parameters passed in the actual parameter list.

### TEXT:

An input variable or parameter is missing or invalid.

### PARAMETERS:

None.

## Error 201

### DESCRIPTION:

The specified input variable is either:

- Required but *not* defined
- *Not* valid.

### TEXT:

The input variable |1| is missing or invalid.

### PARAMETERS:

“1”—Variable name.

## Error 202

### DESCRIPTION:

The specified parameter is either required but missing or invalid.

### TEXT:

The input parameter that identifies the |1| is missing or invalid.

### PARAMETERS:

“1”—Parameter as identified in the VA FileMan documentation.

## Error 203

### DESCRIPTION:

An incorrect subscript is present in an array that is passed to VA FileMan. For example, one of the subscripts in the **FDA** that identifies **FILE**, **IENS**, or **FIELD** is incorrectly formatted.

### TEXT:

The subscript that identifies the |1| is missing or invalid.

### PARAMETERS:

“1”—The data element incorrectly specified by a subscript.

## Error 204

### DESCRIPTION:

Control characters are *not* permitted in the database.

### TEXT:

The input value contains control characters.

### PARAMETERS:

“1”—Input value.

## Error 205

### DESCRIPTION:

Error message output when a file or subfile number and its associated IEN string are *not* in sync (i.e., the number of comma pieces represented by the IEN string do *not* match the file/subfile level according to the “UP” nodes).

### TEXT:

File# |1| and IEN string |IENS| represent different subfile levels.

### PARAMETERS:

- “1”—File or subfile number.
- “IENS”—Internal Entry Number String (IENS).

## Error 206

### DESCRIPTION:

VA FileMan is trying to pack fields onto a single node for a record, and the data does *not* fit. The application has asked for too many fields back for this record.

### TEXT:

The data requested for record |1| is too long to pack together.

### PARAMETERS:

“1”—Record number.

## Error 207

### DESCRIPTION:

The library function [\\$\\$HTML^DILF](#) can encode or decode a string to and from HTML, used within VA FileMan to pack a value containing embedded ^s into a ^-delimited string. Encoding increases the length of the string. If encoding would cause the length to exceed the portable string length limit, [\\$\\$HTML^DILF](#) instead returns this error.

### TEXT:

The value |1| is too long to encode into HTML.

### PARAMETERS:

“1”—Value.

## Error 299

### DESCRIPTION:

A lookup that was restricted to finding a single entry found more than one.

### TEXT:

More than one entry matches the value '[1]'.

### PARAMETERS:

- “1”—Lookup value.
- “FILE”—File number.
- “IENS”—Internal Entry Number String (IENS).

## Error 301

### DESCRIPTION:

Flags passed in a variable [e.g., **DIC(0)**] or in a parameter are incorrect.

### TEXT:

The passed flag(s) '[1]' are unknown or inconsistent.

### PARAMETERS:

“1”—Letters from flag.

## Error 302

### DESCRIPTION:

The calling application has asked the system to add a new record, and has supplied a record number, but a record already exists at that number.

### TEXT:

Entry '[IENS]' already exists.

### PARAMETERS:

- “FILE”—File number.
- “IENS”—Internal Entry Number String (IENS).

## Error 304

### DESCRIPTION:

The problem with this IEN string is that it lacks the final “;”. This is a common mistake for beginners.

### TEXT:

The IENS '[IENS]' lacks a final comma.

### PARAMETERS:

“IENS”—Internal Entry Number String (IENS).

## **Error 305**

### DESCRIPTION:

A root is used to identify an input array, but the array is empty.

### TEXT:

The array with a root of '**1**' has no data associated with it.

### PARAMETERS:

**"1"**—Passed root.

## **Error 306**

### DESCRIPTION:

When an IENS is used to explicitly identify a subfile, *not* a subfile entry, then the first comma-piece should be empty. This one was *not*.

### TEXT:

The first comma-piece of IENS '**IENS**' should be empty.

### PARAMETERS:

**"IENS"**—Internal Entry Number String (IENS).

## **Error 307**

### DESCRIPTION:

One of the IENs in the IENS has been left out, leaving an empty comma-piece.

### TEXT:

The IENS '**IENS**' has an empty comma-piece.

### PARAMETERS:

**"IENS"**—Internal Entry Number String (IENS).

## **Error 308**

### DESCRIPTION:

The syntax of this IENS is incorrect. For example, a record number may be illegal, or a subfile may be specified as already existing, but have a parent that is just now being added.

### TEXT:

The IENS '**IENS**' is syntactically incorrect.

### PARAMETERS:

**"IENS"**—Internal Entry Number String (IENS).



## Error 309

### DESCRIPTION:

A Multiple field is involved. Either the root of the Multiple or the necessary entry numbers are missing.

### TEXT:

There is insufficient information to identify an entry in a subfile.

### PARAMETERS:

None.

## Error 310

### DESCRIPTION:

Some of the IENS subscripts in this **FDA** conflict with each other. For example, one IENS may use the sequence number **?1** while another uses **+1**. This would be illegal, because the sequence number **1** is being used to represent two different operations.

Consult your documentation for an explanation of the various conflicts possible.

The IENS returned with this error happens to be one of the IENS values in conflict.

### TEXT:

The IENS '[IENS]' conflicts with the rest of the FDA.

### PARAMETERS:

**"IENS"**—Internal Entry Number String (IENS).

## Error 311

### DESCRIPTION:

Adding an entry to a file without including all required identifiers violates database integrity. The entry identified by this IENS lacks some of its required identifiers in the passed-in **FDA**.

### TEXT:

The new record '[IENS]' lacks some required identifiers.

### PARAMETERS:

**"IENS"**—Internal Entry Number String (IENS).

## Error 312

### DESCRIPTION:

All required identifiers *must* be present for a new entry to be filed. One or more of those fields is missing for the (sub)file.

### TEXT:

The list of fields is missing a required identifier for File #[**FILE**].

### PARAMETERS:

**"FILE"**—File or subfile number.

## Error 330

### DESCRIPTION:

The value passed by the calling application should be a certain data type, but according to the checks it is *not*.

### TEXT:

The value '|1|' is not a valid |2|.

### PARAMETERS:

- “1”—Passed value.
- “2”—Data type.

## Error 348

### DESCRIPTION:

The calling application passed a VARIABLE POINTER value. That value points to a file that does *not* exist or that lacks a Header Node.

### TEXT:

The passed value '|1|' points to a file that does not exist or lacks a Header Node.

### PARAMETERS:

“1”—Passed value.

## Error 351

### DESCRIPTION:

When passing an **FDA** to the [Updater](#), any entries intended as **Finding** or **LAYGO Finding** nodes *must* include a **.01** node that has the lookup value. This value need *not* be a legitimate **.01** field value but it *must* be a valid and unambiguous lookup value for the file.

### TEXT:

FDA nodes for lookup '|IENS|' omit a .01 node with a lookup value.

### PARAMETERS:

- “**FILE**”—File number.
- “**IENS**”—IENS subscript for **Finding** or **LAYGO Finding** node.

## Error 352

### DESCRIPTION:

When passing an **FDA** to the [Updater](#), any entries intended as **LAYGO** or **LAYGO Findings** nodes *must* include **.01** node. Every new entry *must* have a value for the **.01** field.

### TEXT:

The new record ‘|**IENS**|’ for file #|**FILE**| lacks a .01 field.

### PARAMETERS:

- “**FILE**”—File number.
- “**IENS**”—IENS subscript for **Finding** or **LAYGO Finding** node.

## Error 401

### DESCRIPTION:

The specified file or subfile does *not* exist; it is *not* present in the data dictionary.

### TEXT:

File #|**FILE**| does not exist.

### PARAMETERS:

“**FILE**”—File number.

## Error 402

### DESCRIPTION:

The specified file or subfile lacks a valid global root; the global root is missing or is syntactically *not* valid.

### TEXT:

The global root of file #|**FILE**| is missing or not valid.

### PARAMETERS:

- “**FILE**”—File number.
- “**ROOT**”—File root.
- “**IENS**”—Internal Entry Number String (IENS).

## Error 403

### DESCRIPTION:

The File Header Node, the top-level of the data file as described in this manual, *must* be present for VA FileMan to determine certain kinds of information about a file.

### TEXT:

File #|**FILE**| lacks a Header Node.

### PARAMETERS:

“**FILE**”—File number.

## Error 404

### DESCRIPTION:

You have identified a file by the global node of its data file and found its Header Node. You needed to use the Header Node to identify the number of the file, but that piece of information is missing from the Header Node.

### TEXT:

The File Header node of the file stored at |1| lacks a file number.

### PARAMETERS:

“1”—File root.

## Error 405

### DESCRIPTION:

The NO EDIT flag is set for the file. No instruction to override that flag is present.

### TEXT:

Entries in file |1| cannot be edited.

### PARAMETERS:

- “1”—File name.
- “FILE”—File number.

## Error 406

### DESCRIPTION:

The data definition for a .01 field for the specified file is missing. This file is therefore *not* valid for most database operations.

### TEXT:

File #|FILE| has no .01 field definition.

### PARAMETERS:

“FILE”—File number.

## Error 407

### DESCRIPTION:

The subfile number of a WORD-PROCESSING field has been passed in the place of a file parameter. This is *not* acceptable. Although the system implements WORD-PROCESSING fields as independent files, it does *not* allow them to be treated as files for purposes of most database activities.

### TEXT:

A word-processing field is not a file.

### PARAMETERS:

“FILE”—Subfile number of WORD-PROCESSING field.

## Error 408

### DESCRIPTION:

The file lacks a name. For subfiles,  $\$P(^{DD}(file\#,0),U)$  is null. For root files,  $\$O(^{DD}(file\#,0,“NM”,“”))=“”$ .

### TEXT:

File# |**FILE**| lacks a name.

### PARAMETERS:

“**FILE**”—File number.

## Error 409

### DESCRIPTION:

The indicated file does *not* exist in the VA FileMan database.

### TEXT:

File ‘|**1**|’ could not be found.

### PARAMETERS:

“**1**”—File name or number.

## Error 420

### DESCRIPTION:

A cross-reference was specified for a lookup, but that cross-reference does *not* exist on the file. The file has entries, but the index does *not*. This error implies nothing about whether the index is defined in the file’s data dictionary (DD).

### TEXT:

There is no |**1**| index for File #|**FILE**|.

### PARAMETERS:

- “**1**”—Cross-reference name.
- “**FILE**”—File number.

## Error 501

### DESCRIPTION:

A search of the data dictionary reveals that the field name or number passed does *not* exist in the specified file.

### TEXT:

File #|**FILE**| does not contain a field |**1**|.

### PARAMETERS:

- “**1**”—Field name or number.
- “**FILE**”—File number.
- “**FIELD**”—Field number.

## Error 502

### DESCRIPTION:

The field has been identified, but some key part of its definition is missing or corrupted. **^DD(file#,field#,0)** may *not* be defined. Some key piece of that node may be missing.

### TEXT:

Field# **|FIELD|** in file# **|FILE|** has a corrupted definition.

### PARAMETERS:

- “**FILE**”—File number.
- “**FIELD**”—Field number.

## Error 505

### DESCRIPTION:

The field name passed is ambiguous. It *cannot* be determined to which field in the file it refers.

### TEXT:

There is more than one field named ‘|1|’ in File #**|FILE|**.

### PARAMETERS:

- “**1**”—Field name.
- “**FILE**”—File number.

## Error 510

### DESCRIPTION:

For some reason, the data type for the specified field *cannot* be determined. This can mean that the data dictionary is corrupted.

### TEXT:

The data type for Field #**|FIELD|** in File #**|FILE|** cannot be determined.

### PARAMETERS:

- “**FIELD**”—Field number.
- “**FILE**”—File number.

## Error 520

### DESCRIPTION:

An incorrect kind of field is being processed. For example, filing is being attempted for a COMPUTED field or validation for a WORD-PROCESSING field.

### TEXT:

A **|1|** field cannot be processed by this utility.

### PARAMETERS:

- “**1**”—Data type or other field characteristic (e.g., **.001**, **DINUMed**).
- “**FILE**”—File number.
- “**FIELD**”—Field number.

## Error 525

### DESCRIPTION:

It is indicated that a subfile is involved (e.g., by choosing a Multiple field’s field number), but no fields from the subfile are chosen.

### TEXT:

No fields are specified for subfile #**FILE**.

### PARAMETERS:

“**FILE**”—Subfile number.

## Error 537

### DESCRIPTION:

This error means that a certain field in a certain file has a data type of POINTER, but something is wrong with the rest of the data dictionary (DD) information needed to make that pointer work. For example, perhaps the number of the pointed-to file, which should follow the **P** in the second ^-piece of the field descriptor node, is missing.

Another problem would be if the global root of the pointed-to file were missing from the field’s definition; that should be found in the third ^-piece of the field descriptor.

### TEXT:

Field #**FIELD** in File #**FILE** has a corrupted pointer definition.

### PARAMETERS:

- “**FILE**”—File number.
- “**FIELD**”—Field number.

## Error 601

### DESCRIPTION:

The entry identified by **FILE** and **IENS** does *not* exist in the database.

### TEXT:

The entry does not exist.

### PARAMETERS:

- **“FILE”**—File or subfile number (*external only*).
- **“IENS”**—Internal Entry Number String (IENS) (*external only*).

## Error 602

### DESCRIPTION:

There is a **-9** node for the entry; therefore, the entry *cannot* be accessed.

### TEXT:

The entry is not available for editing.

### PARAMETERS:

- **“FILE”**—File or subfile number (*external only*).
- **“IENS”**—Internal Entry Number String (IENS) (*external only*).

## Error 603

### DESCRIPTION:

A specific entry in a specific file lacks a value for a required field. This error message returns the name of the field that is missing.

### TEXT:

Entry #**|1|** in File #**|FILE|** lacks the required Field #**|FIELD|**.

### PARAMETERS:

- **“1”**—Entry number.
- **“FILE”**—File number.
- **“FIELD”**—Field number.



## Error 630

### DESCRIPTION:

The database is corrupted. The value for a specific field in one entry should be a certain data type, but it is *not*.

### TEXT:

In Entry # |1| of File #|FILE|, the value '|2|' for Field #|FIELD| is not a valid '|3|'.

### PARAMETERS:

- “1”—Entry number.
- “2”—Field value.
- “3”—Data type.
- “FILE”—File number.
- “FIELD”—Field number.

## Error 648

### DESCRIPTION:

The database is corrupted. In a specific VARIABLE POINTER field of a certain entry, the field's value points to a file that either does *not* exist or that lacks a Header Node.

### TEXT:

In Entry #|1| of File #|FILE|, the value '|2|' for Field #|FIELD| points to a file that does not exist or lacks a Header Node.

### PARAMETERS:

- “1”—Entry number.
- “2”—Field value.
- “FILE”—File number.
- “FIELD”—Field number.

## Error 701

### DESCRIPTION:

The value is invalid. Possible causes include:

- Value did *not* pass INPUT transform.
- Value for a POINTER or VARIABLE POINTER field *cannot* be found in the pointed-to file.
- A screen was *not* passed.

TEXT:

The value ‘|3|’ for field |1| in file |2| is not valid.

PARAMETERS:

- “1”—Field name.
- “2”—File name.
- “3”—Value that was found to be invalid.
- “FIELD”—Field number (*external only*).
- “FILE”—File number (*external only*).
- “IENS”—Internal Entry Number String (IENS) identifying entry with invalid value (*external only*, sometimes returned).

## Error 703

DESCRIPTION:

The value passed *cannot* be found in the indicated file using [\\$\\$FIND1^DIC](#).

TEXT:

The value ‘|1|’ cannot be found in file #|FILE|.

PARAMETERS:

- “1”—Lookup value.
- “FILE”—File number.
- “IENS”—Internal Entry Number String (IENS).

## Error 710

DESCRIPTION:

The data dictionary specifies that the field is uneditable. Data already exists in the field. It *cannot* be changed.

TEXT:

Data in Field #|FIELD| in File #|FILE| cannot be edited.

PARAMETERS:

- “FIELD”—Field number.
- “FILE”—File number.

## Error 712

### DESCRIPTION:

The value of a field *cannot* be deleted either for any of the following reasons:

- It is a required field.
- It is the **.01** of a file.
- Test in the “**DEL**” node was *not* passed.

### TEXT:

The value of field |1| in file |2| cannot be deleted.

### PARAMETERS:

- “**1**”—Field name.
- “**2**”—File name.
- “**FIELD**”—Field number (*external only*).
- “**FILE**”—File number (*external only*).

## Error 714

### DESCRIPTION:

The field uses **\$Piece** storage and the data contains a caret (^). The data *cannot* be filed.

### TEXT:

Data for Field |1| in File |2| contains an ‘^’.

### PARAMETERS:

- “**1**”—Field name.
- “**2**”—File name.
- “**FILE**”—File number (*external only*).
- “**FIELD**”—Field number (*external only*).

## Error 716

### DESCRIPTION:

Data being filed is too long for the field. Specifically, this occurs when data of the wrong length is being filed in a **\$Extract (Em,n)** field.

### TEXT:

Data for field |1| in file |2| is too long.

### PARAMETERS:

- “**1**”—Field name.
- “**2**”—File name.
- “**FIELD**”—Field number (*external only*).
- “**FILE**”—File number (*external only*).

## Error 720

### DESCRIPTION:

The lookup for a pointer fails. This is an error only when LAYGO is *not* allowed.

### TEXT:

The value cannot be found in the pointed-to file.

### PARAMETERS:

- **“FILE”**—File number; the number of the file in which the POINTER field exists.
- **“FIELD”**—Field number of the POINTER field.

## Error 726

### DESCRIPTION:

There is an attempt to take an action with word-processing data, but the specified field is *not* a WORD-PROCESSING field.

### TEXT:

Field #|**FIELD**| in File #|**FILE**| is not a word-processing field.

### PARAMETERS:

- **“FIELD”**—Field number.
- **“FILE”**—File number.

## Error 730

### DESCRIPTION:

Based on how the data type is defined by a specific field in a specific file, the passed value is *not* valid.

### TEXT:

The value ‘|**1**’ is not a valid |**2**| according to the definition in Field #|**FIELD**| of File #|**FILE**|.

### PARAMETERS:

- **“1”**—Passed value.
- **“2”**—Data type.
- **“FIELD”**—Field number.
- **“FILE”**—File number.

## Error 740

### DESCRIPTION:

When one or more fields are declared as a key for a file, there *cannot* be duplicate values in those fields for entries in the file. The values being passed for validation, when combined with values for unchanging fields in the entry if necessary, create a duplicate key. The changes destroy the integrity of the key; therefore, they are *invalid*.

### TEXT:

New values are invalid because they create a duplicate Key '[1]' for the [2] file.

### PARAMETERS:

- "1"—Name of key.
- "2"—Name of affected file.

## Error 742

### DESCRIPTION:

Every field in a key *must* have a value. The incoming data *cannot* delete the value for any field in a key.

### TEXT:

The value of field [1] in the [2] file cannot be deleted because that field is part of the '[3]' key.

### PARAMETERS:

- "1"—Field name.
- "2"—File name.
- "3"—Key name.
- "FILE"—File number.
- "FIELD"—Field number.

## Error 744

### DESCRIPTION:

Every field that is in a key *must* have a value. No value for this field exists.

### TEXT:

Field [1] is part of Key '[2]', but the field has not been assigned a value.

### PARAMETERS:

- "1"—Field name.
- "2"—Key name.
- "FIELD"—Field number.
- "FILE"—File number.

## Error 746

### DESCRIPTION:

A lookup node is present in the **FDA**, but no Primary Key fields are provided.

The **K** flag was used, but no Primary Key fields were provided in the **FDA** for **Finding** and **LAYGO Finding** nodes.

### TEXT:

No fields in Primary Key ‘|1|’ have been provided in the FDA to look up ‘|IENS|’ in the |2| file.

### PARAMETERS:

- “1”—Key name.
- “2”—File name.
- “IENS”—Internal Entry Number String (IENS) of lookup node (*external only*).
- “KEY”—Key number (*external only*).
- “FILE”—File number (*external only*).

## Error 810

### DESCRIPTION:

A **%ZOSF** node required to perform a function does *not* exist. The *Kernel 8.0 & Kernel Toolkit 7.3 Developer’s Guide* contains a complete list of **%ZOSF** nodes.

### TEXT:

A necessary **%ZOSF** node does not exist on your system.

### PARAMETERS:

None.

## Error 820

### DESCRIPTION:

The ZSAVE CODE (#2619) field in the MUMPS OPERATING SYSTEM (#.7) file is empty for the operating system being used. It is impossible to perform functions, such as compiling templates or cross-references.

### TEXT:

There is no way to save routines on the system.

### PARAMETERS:

None.

## Error 840

### DESCRIPTION:

The TERMINAL TYPE (#3.2) file does *not* have an entry that matches **IOST(0)**.

### TEXT:

Terminal type '|1|' cannot be found in the Terminal Type file.

### PARAMETERS:

**"1"**—Terminal type as identified by **IOST(0)**.

## Error 842

### DESCRIPTION:

The field in the TERMINAL TYPE (#3.2) file that contains the specified characteristic of the terminal is null.

### TEXT:

|1| cannot be found for Terminal Type |2|.

### PARAMETERS:

- **"1"**—Terminal type characteristic.
- **"2"**—Terminal type.

## Error 845

### DESCRIPTION:

A Kernel %ZIS call with **IOP** set to **"HOME"** returns **POP**.

### TEXT:

The characteristics for the HOME device cannot be obtained.

### PARAMETERS:

None.

## Error 1300

### DESCRIPTION:

The entry encountered an error during subfile filing.

### TEXT:

The entry encountered an error during subfile filing.

### PARAMETERS:

**"IEN"**—Internal entry number.

## **Error 1500**

### DESCRIPTION:

Error given for unsuccessful lookup of SEARCH template in **BY(0)** input variable.

### TEXT:

SEARCH template |1| in BY(0) variable cannot be found, is for the wrong file, or has no list of search results.

### PARAMETERS:

“1”—Name of SEARCH template in input variable **BY(0)**.

## **Error 1501**

### DESCRIPTION:

Error message shown to user when no code was generated during compilation of SORT TEMPLATES.

### TEXT:

There is no code to save for this compiled Sort Template routine.

### PARAMETERS:

None.

## **Error 1502**

### DESCRIPTION:

Error message notifying the user that there are no more available routine numbers for compiled Sort Template routines. This should never happen, since routine numbers are re-used.

### TEXT:

All available routine numbers for compilation are in use.

IRM needs to run ENRLS^DIOZ to release the routine numbers.

### PARAMETERS:

None.

## **Error 1503**

### DESCRIPTION:

Warn user to shorten compiled cross-reference routine name.

### TEXT:

Routine name is too long. Compilation has been aborted.

### PARAMETERS:

None.



## Error 1504

### DESCRIPTION:

If doing transfer/merge of a single record from one file to another and the **.01** field names do *not* match, you *cannot* do the transfer/merge.

### TEXT:

No matching .01 field names found. Transfer/Merge cannot be done.

### PARAMETERS:

None.

## Error 1610

### DESCRIPTION:

A question mark or, in the case of a variable pointer field, a *<something>.*? was passed to the Validator. The Validator does *not* process help requests.

### TEXT:

Help is being requested from the Validator utility.

### PARAMETERS:

- **“FILE”**—File number.
- **“FIELD”**—Field number.

## Error 1700

### DESCRIPTION:

Generic message for Silent DIFROM.

### TEXT:

Error: |1|.

### PARAMETERS:

**“1”**—Generic message.

## Error 1701

### DESCRIPTION:

Transport structure does *not* contain SPECIFIC ELEMENT.

### TEXT:

Transport structure does not contain |1|.

### PARAMETERS:

**“1”**—Describes missing element in transport structure.

## **Error 1805**

### DESCRIPTION:

For some reason a record or a field in a record could *not* be filed. The cause of the error should be present in another message.

### TEXT:

An error occurred during the actual filing of data into the FileMan database.

### PARAMETERS:

None.

## **Error 1810**

### DESCRIPTION:

The attempt to move data from a host file into the M environment failed. A possible cause is that the host file does *not* exist in the path specified.

### TEXT:

The data from host file ‘|1|’ could not be moved into a FileMan file.

### PARAMETERS:

“1”—Host file name.

## **Error 1812**

### DESCRIPTION:

A host file was located; however, no data was present in it. This error also occurs if the only “data” is the designation of file and fields with no actual data present to file.

### TEXT:

The host file, |1|, contains no data to import.

### PARAMETERS:

“1”—Host file name.

## **Error 1820**

### DESCRIPTION:

The foreign format name that was passed could *not* be found in the FOREIGN FORMAT (#.44) file.

### TEXT:

There is no Foreign Format named ‘|1|’.

### PARAMETERS:

“1”—Foreign format.

## **Error 1821**

### DESCRIPTION:

The format of the imported data *must* either be delimited by a specified character or be fixed length. The format being specified is neither.

### TEXT:

If no record delimiter is specified, the foreign format *must* be fixed length.

### PARAMETERS:

None.

## **Error 1822**

### DESCRIPTION:

For a fixed length import, the length data for a field is impossible. For example, the length is zero or the start position is larger than the end position.

### TEXT:

The length of a field is incorrectly specified.

### PARAMETERS:

None.

## **Error 1833**

### DESCRIPTION:

The **F** flag for the import call means that the file and field information is in the host file. However, the file and/or fields parameter contained data. This conflicts with the **F** flag.

### TEXT:

The F flag conflicts with the File or Fields parameter.

### PARAMETERS:

None.

## **Error 1850**

### DESCRIPTION:

The device for printing the import report was *not* properly specified. This could be caused either by a user's response or by the device specifications passed to the [FILE^DDMP](#) call. The problem could involve either device or queuing instructions.

### TEXT:

There is an error in device selection or queuing setup.

### PARAMETERS:

None.

## **Error 1870**

### DESCRIPTION:

A requested IMPORT template does *not* exist in the IMPORT TEMPLATE (#.46) file for the file being imported into.

### TEXT:

IMPORT template |1| does not exist for File #|FILE|.

### PARAMETERS:

- “1”—Template name.
- “FILE”—File number.

## **Error 3021**

### DESCRIPTION:

A lookup in to the FORM (#.403) file for the given form failed.

### TEXT:

Form |1| does not exist in the Form file, or DDSFILE is not the Primary File of the form.

### PARAMETERS:

“1”—Form name.

## **Error 3022**

### DESCRIPTION:

There are no pages defined in the PAGE Multiple of the given form.

### TEXT:

Form |1| contains no pages.

### PARAMETERS:

“1”—Form name.

## **Error 3023**

### DESCRIPTION:

The given page was *not* found on the form.

### TEXT:

The form does not contain a page |1|.

### PARAMETERS:

“1”—Page name or number.

## Error 8090

### DESCRIPTION:

Used in displaying an error message when the lookup value *X* does *not* pass the pre-lookup transform code (^DD(File#,.01,7.5)node) during [^DIC](#) or [Finder](#) lookups.

### TEXT:

Pre-lookup transform (7.5 node).

### PARAMETERS:

None.

## Error 8095

### DESCRIPTION:

In calls to the [Finder](#), [IX^DIC](#), or [MIX^DIC1](#), if either the first index passed or the default index is a compound index, then only one index can be passed, so neither **DIC(0)** nor flags can contain “**M**”.




### TEXT:


First lookup index is compound, so “M”ultiple index lookups not allowed.

### PARAMETERS:

None.




## Glossary


Term	Description
.001 Field	A field containing the internal entry number of the record.
.01 Field	The one field that <i>must</i> be present for every file and file entry. It is also called the NAME field. At a file's creation the .01 field is given the label NAME. This label can be changed.
Access Codes	In VA FileMan, a string of codes that determines your security access to files, fields, and templates. In Kernel, you enter an Access Code to identify yourself during signon.
Alternate Editor	One of the text editors available for use from VA FileMan. Editors available vary from site to site. They are entries in the ALTERNATE EDITOR (#1.2) file.
At-sign (@)	A VA FileMan security Access Code that gives the user programmer-level access to files and to VA FileMan's developer features. Also, the at-sign character (@) is used at VA FileMan field prompts to delete data.   REF: See " <a href="#">Programmer Access</a> ."
Attribute Dictionary	 REF: See " <a href="#">Data Dictionary</a> ."
Audit	A VA FileMan feature that provides an ongoing chronological listing of who made what changes to data values.
Audit Trail	The record or log of an ongoing audit.
Auditing	The monitoring and recording of computer use.
Backward Pointer	A pointer to your current file from another file; used in the extended pointer syntax.
Boolean Expression	A logical comparison between values yielding a true or false result. In M: <ul style="list-style-type: none"> <li>• Zero means <b>false</b>.</li> <li>• <i>Non-zero</i> (often one) means <b>true</b>.</li> </ul>
Canonic Number	A number with no leading zeroes and no trailing zeroes after a decimal point.
Caption	In ScreenMan, a label displayed on the screen. Captions often identify fields that are to be edited.
CARET (^)	The caret character (^), also sometimes referred to in VistA legacy documentation as the "up-arrow" key, is used in VA FileMan for exiting an option or canceling a response. Also, it is used in combination with a field name or prompt to jump to the specified field or prompt.
Command Area	In ScreenMan, the bottom portion of the screen used to display help information and to accept user commands.
Compound Index	An index that has more than one data-valued subscript.   REF: See " <a href="#">Index</a> ."



Term	Description
Compound Key	A key that is composed of more than one field. Keys are stored in the KEY (#.31) file.  <b>REF:</b> See “ <a href="#">Key</a> ” and “ <a href="#">Simple Key</a> .”
Cross-Reference	An attribute of a field or a file that identifies an action that should take place when the value of a field is changed. Often, the action is the placement of the field’s value into an <a href="#">index</a> : <ul style="list-style-type: none"> <li>• Traditional cross-reference is defined with a specific field.</li> <li>• <a href="#">New-Style cross-reference</a> is a file attribute and can be composed of one or more fields. <a href="#">New-Style cross-references</a> are stored in the INDEX (#.11) file.</li> </ul>
Cursor	On your display terminal, the line or rectangle identifying where your next input is placed on the screen.
Data Dictionary	This is a file that defines a file's structure, its elements (fields and their attributes), and relationships to other files. This is sometimes called schema. Often abbreviated as DD.
Data Dictionary Listing	The printable report that shows the data dictionary.
DATA TYPE	The kind of data stored in a field. For example: <ul style="list-style-type: none"> <li>• NUMERIC</li> <li>• COMPUTED</li> <li>• SET OF CODES</li> <li>• WORD-PROCESSING</li> </ul>
Database	An organized collection of data spanning many files. Often, all the files on a system constitute that system's database.
Default	A computer-provided response to a question or prompt. The default might be a value pre-existing in a file. Often, you can change a default.
Delimiter	A special character used to separate a field, record, or string. VA FileMan usually uses the ^ character as the delimiter within strings.
Device Prompt	A Kernel prompt at which you identify where to send your output.
<a href="#">DIC</a>	VA FileMan routine that searches a file and finds an entry, adds an entry, or returns a condition indicating that the lookup was unsuccessful.
<a href="#">DIE</a>	VA FileMan routine that edits data elements for a given file entry.
DIFROM	(Obsolete) VA FileMan routines that transfer software packages from one VA FileMan environment to another. DIFROM is used to install new packages as well as update versions of current packages. DIFROM can also be used as a simple archiving tool.
<a href="#">DIK</a>	VA FileMan routine that re-indexes or deletes file entries.
<a href="#">DIP</a>	VA FileMan routine that prints data.
<a href="#">DIQ</a>	VA FileMan routine that displays a range of data elements.





Term	Description
<a href="#">DIR</a>	VA FileMan's general purpose reader routine that can be used to issue a prompt, interactively read input, do syntax checking on input, issue error messages or help text, and return input in a processed form.
<a href="#">DIWF</a>	VA FileMan routine that uses the contents of a WORD-PROCESSING field as a target into which data is inserted at print time. The data can come from another file or can be provided by the user interactively at the time of print.
<a href="#">DIWP</a>	VA FileMan routine that formats and (optionally) outputs any group of text lines.
Edit Window	In ScreenMan, the area in which you enter or edit data. It is highlighted with either reverse video or an underline. In Screen Editor, the area in which you enter and edit text; the area between the status bar and the ruler.
Entry	A record in a file. "Entry" and "record" are used interchangeably.
Extended Pointers	A means to reference fields in files other than your current file.
FDA	FileMan Data Array
Field	In an entry, a specified area used to hold values. The specifications of each VA FileMan field are documented in the file's data dictionary.
Field Number	The unique number used to identify a field in a file. A field can be referenced by # followed by the field number.
File	A set of related records (or entries) treated as a unit.
Form	In ScreenMan, a group of one or more pages that comprise a complete transaction. Comparable to an INPUT template.
FREE TEXT	A DATA TYPE field value that can contain any printable characters.
Full-screen Editing	The ability to enter data in various locations on the two-dimensional computer display. Compare to scrolling mode.
Global Variable	A variable that is stored on disk.
Histogram	A type of bar graph that indicates frequency of occurrence of particular values.
Hook	A documented data dictionary attribute, input variable, or parameter in which an application developer can place M code that is executed during a VA FileMan call. Also called a " <a href="#">Programmer Hook</a> ."
Identifier	In VA FileMan, a field that is defined to aid in identifying an entry in conjunction with the NAME (#.01) field.



Term	Description
Index	<p>An ordered list used to speed retrieval of entries from a file based on a value in some field or fields:</p> <ul style="list-style-type: none"> <li>• The term “simple index” refers to an index that stores the data for a single field.</li> <li>• The term “compound index” refers to an index that stores the data for more than one field.</li> </ul> <p>Indexes are created and maintained via <a href="#">cross-references</a>.</p> <p> <b>REF:</b> See also “<a href="#">Uniqueness Index</a>.”</p>
Initialization	The process of setting variables in a program to their starting value.
INPUT Template	A pre-defined list of fields that together comprise an editing session.
INPUT Transform	An executable string of M code which is used to check the validity of input and to convert it into an internal form for storage.
Internal Entry Number (IEN)	The number used to identify an entry within a file. Every record has a unique internal entry number. Often abbreviated as IEN.
Kernel	A VistA software package that functions as an intermediary between the host operating system and VistA application packages. Kernel includes installation, menu, security, and device services.
Key	<p>A group of fields that, taken collectively, uniquely identifies a record in a file or subfile (Multiple). All fields in a key <i>must</i> have values:</p> <ul style="list-style-type: none"> <li>• The term “simple key” refers to keys that are composed of only one field.</li> <li>• The term “compound key” refers to keys that are composed of more than one field.</li> </ul> <p>Keys are stored in the KEY (#.31) file.</p> <p> <b>REF:</b> See also “<a href="#">Primary Key</a>” and “<a href="#">Secondary Key</a>.”</p>
Key Integrity	When a KEY is defined for a file, FileMan enforces key integrity. All fields in a key <i>must</i> have values ( <i>must not</i> be null) and those values, taken together, <i>must</i> be unique across all records in the file; that is, no two records in the file can have the same key. VA FileMan enforces key integrity whenever records are added or edited.
LAYGO	A user’s authorization to create a new entry when editing a computer file. An acronym for <b>Learn As You Go</b> .
Line Editor	<p>The VA FileMan editor that lets you input and change text on a line-by-line basis. The Line Editor works in scrolling mode.</p> <p> <b>REF:</b> See <a href="#">Screen Editor</a>.</p>
Local Variable	A variable that is stored in a local partition.
Lookup	To find an entry in a file using a value for one of its fields.
MailMan	An electronic mail system (e-mail) that allows you to send messages to and receive them from other users via the computer. It is part of VistA.

Term	Description
Menu	A list that includes the names of options from which you can select an activity.
Multiple	A VA FileMan DATA TYPE field value that allows more than one value for a single entry. See Subfile.
MUMPS	Abbreviated as M. The American National Standards Institute (ANSI) computer language used by VA FileMan and throughout Vista. The acronym MUMPS stands for <b>M</b> assachusetts General Hospital <b>U</b> tility <b>M</b> ulti <b>P</b> rogramming <b>S</b> ystem.
NAME Field	The one field that <i>must</i> be present for every file and file entry. It is also called the <b>.01</b> field. At a file's creation the <b>.01</b> field is given the label <b>NAME</b> . This label can be changed.
Navigation	<ol style="list-style-type: none"> <li>1. Navigation can mean switching your reference point from one file to another.</li> <li>2. Navigation can also mean moving your cursor around a terminal display or a document using cursor keys and other commands.</li> </ol>
New-Style Cross-Reference	<p>A cross-reference that is stored in the INDEX (#.11) file. New Style cross-references can be more complex than traditional cross-references. They can create an index with:</p> <ul style="list-style-type: none"> <li>• More than one field value</li> <li>• Transformed field values</li> <li>• Computed subscript values</li> </ul> <p>They can be defined so that subscripts are displayed in inverse collation sequence during question-mark help or when using a Lister call (<a href="#">LIST^DIC</a>). Firing of <b>SET</b> and <b>KILL</b> logic for the index can happen at the record level, rather than each time individual fields that make up the index are edited.</p> <p> <b>REF:</b> See "<a href="#">Cross-Reference</a>."</p>
Non-Canonic Number	A number with either leading zeroes, or trailing zeroes after a decimal point. M treats non-canonic numbers as text instead of as numbers.
Non-Null	A value other than null. A space and zero are <i>non</i> -null values.
Null	Empty. A field or variable that has no value associated with it is null.
Null Response	When replying to a prompt, pressing only the <b>Enter</b> key, abbreviated as <b>&lt;Enter&gt;</b> , to enter nothing.
Numeric Expression	An expression whose value is a number. Compare to string expression.
Operator	One of the processes done to the elements in an expression to create a value.
Option	A computing activity that you can select, usually a choice from a menu.
OUTPUT Transform	An executable string of M code that converts internally stored data into a readable display.
Paste	Insert text or other data as input into one computer program that has been copied into a clipboard by the same or by another computer program.

Term	Description
Pattern Match	In M, an operator that compares the contents of a variable or literal to a specified pattern of characters or kinds of characters.
PF Keys	Keys on a terminal keyboard labeled <b>PF1</b> , <b>PF2</b> , etc. that are used to perform special functions instead of displaying visible characters.
POINTER TO A FILE	A DATA TYPE field value that contains an explicit reference to an entry in a file. POINTER TO A FILE-type fields are used to relate files to each other.
Popup Page	In ScreenMan, a page that overlays the regular ScreenMan screen in order to present the contents of a selected Multiple.
Preferred Editor	The editor always entered when you access a WORD-PROCESSING-type field; your default editor. Kernel <i>must</i> be present to establish a Preferred Editor.
Primary Key	<p>The key chosen by the database designer to be VA FileMan's principal means of identifying records in the file. VA FileMan automatically displays the Primary Key during classic interactive lookup (<a href="#">^DIC</a>) and uses the Primary Key to identify records brought in during a KIDS installation. Exactly one Key in a file or subfile <i>must</i> be designated the Primary Key.</p> <p> <b>REF:</b> See "<a href="#">Key</a>."</p>
PRINT Template	The stored specifications of a printed report, including fields to be printed and formatting instructions.
Programmer Access	The ability to use VA FileMan features that are reserved for application developers. Referred to as "having the at-sign (@)" because the at-sign is the <b>DUZ(0)</b> value that grants programmer access.
Programmer Hook	A documented data dictionary attribute, input variable, or parameter in which an application developer can place M code that is executed during a VA FileMan call. Also called " <a href="#">Hook</a> ."
Prompt	A question or message from the computer requiring your response.
Record	A set of data pertaining to a single entity in a file; an entry in a file.
Record Number	<p> <b>REF:</b> See <a href="#">Internal Entry Number (IEN)</a>.</p>
Relational Navigation	Changing your current (or primary) file reference to another file. Relational navigation is accomplished by using the extended pointer syntax <i>without</i> specifying a field in the referenced file.
Required Field	A field that cannot be left null for an entry.
Routine	A set of M code that performs a process.
Scattergram	A graph in which occurrences of two fields are displayed on an <b>X-Y</b> coordinate grid to aid in data analysis.

Term	Description
Screen Editor	<p>VA FileMan's screen-oriented text editor. It can be used to enter data into any WORD-PROCESSING field using full-screen editing instead of line-by-line editing.</p> <p> REF: See "<a href="#">Line Editor</a>."</p>
Screen-Oriented	<p>A computer interface in which you see many lines of data at a time and in which you can move your cursor around the display screen using screen navigation commands. Compare to <a href="#">Scrolling Mode</a>.</p>
ScreenMan	<p>The set of routines that supports screen-oriented data editing and data display.</p>
Scrolling Mode	<p>The presentation of the interactive dialogue one line at a time. Compare to <a href="#">Screen-Oriented</a>.</p>
SDP	<p>An area on disk set aside for temporary, sequential storage of data; an abbreviation for <b>S</b>equential <b>D</b>isk <b>P</b>rocessor. It is available on some M implementations (e.g., DSM-11).</p>
SEARCH Template	<p>The saved results of a search operation. Usually, the actual entries found are stored in addition to the criteria used to select those entries.</p>
Secondary Key	<p>Like a Primary Key, fields that make up a Secondary Key <i>must</i> uniquely identify a single record on the file. Key integrity is enforced by VA FileMan for a Secondary Key, exactly the same as for a Primary Key. Secondary Key values, however, are <i>not</i> automatically displayed by VA FileMan during interactive lookup <a href="#">^DIC</a>. A file or subfile can have more than one Secondary Key.</p> <p> REF: See "<a href="#">Key</a>" and "<a href="#">Primary Key</a>."</p>
Security	<p>The strategies and procedures used to ensure that user access to data and data structures is controlled and appropriate.</p>
SET OF CODES	<p>A DATA TYPE field value where a short character string is defined to represent a longer value.</p>
Simple Extended Pointers	<p>An extended pointer that uses a pre-existing pointer relationship to access entries in another file.</p>
Simple Index	<p>An index that stores the data for a single field.</p> <p> REF: See "<a href="#">Index</a>."</p>
Simple Key	<p>A key that is composed of only one field.</p> <p> REF: See "<a href="#">Compound Key</a>."</p>
Sort	<p>To place items in order, often in alphabetical or numeric sequence.</p>
SORT Template	<p>The stored record of sort specifications. It contains sorting order as well as restrictions on the selection of entries. Used to prepare entries for printing.</p>
Spooling	<p>Procedure by which programs and output can be temporarily stored until their turn to execute or print.</p>

Term	Description
Stuff	To place values directly into a field, usually with no user interaction.
Subentry	An entry in a Multiple; also called a Subrecord.
Subfield	A field in a Multiple.
Subfile	The data structure of a Multiple. In many respects, a Subfile has the same characteristics as a file.
Sub-routine	A sequence of M code that performs a specific task, usually used more than once.
Terminal Emulation	Using one kind of terminal or computer display to mimic another kind. Often used with PC remote communication applications.
Terminal Type	The designation of the kind of computer peripheral being used (e.g., the kind of video display or printer). Full terminal type functionality is supplied by Kernel.
Truth Test	An evaluation of an expression yielding a true or false result. In M, usually one of the following is returned from a truth test: <ul style="list-style-type: none"> <li>• <b>1 (true)</b></li> <li>• <b>0 (false)</b></li> </ul>
Uniqueness Index	An index associated with every key and used to enforce uniqueness of the key. Every field in the key <i>must</i> be a subscript on the Uniqueness Index and <i>must</i> have no transforms.
Up-Arrow	The caret character (^), also sometimes referred to in VistA legacy documentation as the “up-arrow” key, is used in VA FileMan for exiting an option or canceling a response. Also, it is used in combination with a field name or prompt to jump to the specified field or prompt.
Upload	Send a file from one computer system to another (usually using communications software).
Utility Routine	A routine that performs a task that many developers use.
Variable	A symbol representing a value that changes during the execution of a routine.
VistA	The Veterans Health Information Systems and Technology Architecture (VistA), within the Department of Veterans Affairs (VA), is the component of the Veterans Health Administration (VHA) that develops software and installs, maintains, and updates compatible computer systems in VA medical facilities. (Previously known as the Decentralized Hospital Computer Program [DHCP].)



**REF:** For a list of commonly used terms and definitions, see the OIT Master Glossary VA Intranet website.

For a list of commonly used acronyms, see the VA Acronym Lookup Intranet website.

## Index

### \$

\$\$CANDO^DIAC1, 369, 397

\$\$CREF^DILF

Root Converter (Open to Closed Format),  
257

\$\$EXTERNAL^DILFD

Converts Internal Value to External Format,  
267

\$\$EZBLD^DIALOG

DIALOG Extractor (Single Line), 163

\$\$FIND1^DIC

Finder (Single Record), 190

\$\$FLDNUM^DILFD

Field Number Retriever, 272

\$\$GET^DDSVVAL, 340

\$\$GET^DDSVVALF, 344

\$\$GET1^DID

Attribute Retriever, 227

\$\$GET1^DIQ

Data Retriever (Single Field), 278

\$\$HTML^DILF

HTML Encoder/Decoder, 263

\$\$IENS^DILF

Return IENS from a DA() Array Structure,  
264

\$\$KEYVAL^DIE

Key Validator, 236

\$\$OREF^DILF

Root Converter (Closed to Open Format),  
265

\$\$ROOT^DILFD

File Root Resolver, 275

\$\$ROUSIZE^DILF, 67

\$\$TEST^DDBRT, 362

\$\$UTC^DIUTC, 365

\$\$VALUE1^DILF

FDA

Value Retriever (Single), 265

\$\$VFIELD^DILFD

Field Verifier, 276

\$\$VFILE^DILFD

File Verifier, 277

^

^%DTC, 120

^DDGF, 313

^DDS, 337

^DI

Programmer Access, 401

^DIAC, 13

^DIC, 14

^DIE, 39

^DIEZ, 49

^DIFG

Filegram Installer, 393

^DIK, 50

^DIKZ, 67

^DIM, 68

^DIOZ, 68

^DIPT, 84

^DIPZ, 84

^DIR, 91

^DIWF, 111

^DIWP, 113

^DIWW, 115

A

Actions

Post-Selection Action

- Advanced File Definition, 437
- Adding (ScreenMan Form Editor)
  - Blocks, 326
  - Fields, 326
  - Pages:, 325
- Adding, Selecting, and Editing
  - ScreenMan Form Editor, 321
- ADDITIONAL FIELDS (#5.1) Field, 370
- Advanced File Definition, 426
  - Assigning a Location for Fields Stored within a Global, 427
  - Assigning Sub-Dictionary Numbers, 428
  - Audit Condition, 438
  - Computed Dates, 429
  - Computed Expressions, 429
  - Computed Multiples, 430
  - Computed Pointers, 429
  - Editing a Cross-reference, 438
  - Executable Help, 439
  - Field Global Storage, 427
  - File Global Storage, 426
  - INPUT Transform, 433
  - INPUT Transforms and the Verify Fields Option, 436
  - Introduction, 426
  - MUMPS Data Type, 431
  - OUTPUT Transform, 436
  - Post-Selection Action, 437
  - Screened Pointers and Set of Codes, 431
  - Special Lookup Programs, 437
  - Storing Data by Position within a Node, 428
  - Storing Data in a Global other than ^DIZ, 426
- APIs
  - \$\$CANDO^DIAC1, 369, 397
  - \$\$CREF^DILF, 257

- \$\$EXTERNAL^DILFD, 267
- \$\$EZBLD^DIALOG, 163
- \$\$FIND1^DIC, 190
- \$\$FLDNUM^DILFD, 272
- \$\$GET^DDSVVAL, 340
- \$\$GET^DDSVVALF, 344
- \$\$GET1^DID, 227
- \$\$GET1^DIQ, 278
- \$\$HTML^DILF, 263
- \$\$IENS^DILF, 264
- \$\$KEYVAL^DIE, 236
- \$\$OREF^DILF, 265
- \$\$ROOT^DILFD, 275
- \$\$ROUSIZE^DILF, 67
- \$\$TEST^DDBRT, 362
- \$\$UTC^DIUTC, 365
- \$\$VALUE1^DILF, 265
- \$\$VFIELD^DILFD, 276
- \$\$VFILE^DILFD, 277
- %XY^%RCR, 125
- ^%DTC, 120
- ^DDS, 337
- ^DIAC, 13
- ^DIC, 14
- ^DIE, 39
- ^DIEZ, 49
- ^DIFG, 393
- ^DIK, 50
- ^DIKZ, 67
- ^DIM, 68
- ^DIOZ, 68
- ^DIPT, 84
- ^DIPZ, 84
- ^DIR, 91
- ^DIWF, 111

^DIWP, 113  
 ^DIWW, 115  
 Auditing, 349  
 BLD^DIALOG, 157  
 BROWSE^DDBR, 354  
 Browser, 353  
 C^%DTC, 120  
 CHANGED^DIAUTL, 351  
 CHK^DIE, 229  
 Classic VA FileMan, 4  
 CLEAN^DILF, 257  
 CLOSE^DDBRZIS, 363  
 COMMA^%DTC, 121  
 CREIXN^DDMOD, 138  
 D^DIQ, 86  
 DA^DILF, 258  
 Database Server (DBS) Calls, 126  
 DELIX^DDMOD, 149  
 DELIXN^DDMOD, 152  
 DIBT^DIPT, 84  
 DO^DIC1, 31  
 DOCLIST^DDBR, 360  
 DQ^DICQ, 38  
 DT^DICRW, 38  
 DT^DILF, 259  
 DT^DIO2, 68  
 DT^DIQ, 86  
 DW^%DTC, 122  
 EN^DDBR, 353  
 EN^DDIOL, 9  
 EN^DIAXU, 384  
 EN^DIB, 14  
 EN^DID, 39  
 EN^DIEZ, 50  
 EN^DIFGG, 395  
 EN^DIK, 52  
 EN^DIKZ, 67  
 EN^DIPZ, 85  
 EN^DIQ, 87  
 EN^DIQ1, 88  
 EN^DIS, 106  
 EN^DIU2, 107  
 EN^DIWE, 108  
 EN1^DIK, 54, 55  
 EN1^DIWF, 112  
 EN2^DIWF, 113  
 ENALL^DIK, 57, 58  
 EXPORT^DDMP, 378  
 EXTRACT^DIAXU, 386  
 FDA^DILF, 261  
 FIELD^DID, 221  
 FIELDLST^DID, 223  
 FILE^DDMP, 372  
 FILE^DICN, 35  
 FILE^DID, 224  
 FILE^DIE, 230  
 Filegrams, 393  
 FILELST^DID, 226  
 FILESEC^DDMOD, 155  
 FIND^DIC, 168  
 GETS^DIQ, 281  
 H^%DTC, 122  
 HELP^%DTC, 123  
 HELP^DIE, 234  
 HLP^DDSUTL, 346  
 Import Tool, 372  
 IX^DIC, 29  
 IX^DIK, 60  
 IX1^DIK, 61  
 IXALL^DIK, 64, 65



LAST^DIAUTL, 350  
 LIST^DIC, 202  
 LOCK^DILF, 264  
 MSG^DDSUTL, 346  
 MSG^DIALOG, 164  
 NOW^%DTC, 123  
 OPEN^DDBRZIS, 363  
 Other, 349  
 POST^DDBRZIS, 364  
 PRD^DILFD, 273  
 PUT^DDSVL, 341  
 PUT^DDSVL, 345  
 RECALL^DILFD, 274  
 REFRESH^DDSUTL, 347  
 REQ^DDSUTL, 347  
 S^%DTC, 123  
 ScreenMan, 337  
 ScreenMan Introduction, 337  
 TURNON^DIAUTL, 349  
 UNED^DDSUTL, 348  
 UPDATE^DIE, 239  
 VAL^DIE, 247  
 VALS^DIE, 251  
 VALUES^DILF, 266  
 WAIT^DICD, 35  
 WP^DDBR, 357  
 WP^DIE, 255  
 X ^DD(DD), 8  
 Y^DIQ, 87  
 YMD^%DTC, 124  
 YX^%DTC, 124  
 Appendix A—VA FileMan Error Codes, 477  
     Introduction, 477  
 Array and Variable Clean-up  
     CLEAN^DILF, 257  
**ASSIGN A VERSION NUMBER**, 456  
 Assigning  
     A Location for Fields Stored within a Global  
         Advanced File Definition, 427  
     Sub-Dictionary Numbers  
         Advanced File Definition, 428  
 Assumptions, xxxv  
 Attribute  
     Dictionary  
         Global File Structure, 415  
     Retriever  
         \$\$GET1^DID, 227  
 ATTRIBUTE FUNCTION (#.04) Field, 369  
 AUDIT (#1.1) File, 352, 378, 380, 438  
 Audit Condition  
     Advanced File Definition, 438  
 Auditing  
     APIs, 349  
     Calls  
         CHANGED^DIAUTL, 351  
         LAST^DIAUTL, 350  
         TURNON^DIAUTL, 349  
 AVAILABLE FIELDS (#5) Field, 370  
**B**  
 B Cross-reference  
     Checking, 471  
 Backward Pointers  
     Relational Navigation  
         ScreenMan Forms, 295  
 BLD^DIALOG  
     DIALOG Extractor, 157  
 Block  
     Properties  
         ScreenMan Forms, 303, 305  
         Apply Only to Repeating Blocks, 290

- Coordinate, 303
- DD Number, 304
- Disable Navigation, 304
- Disallow LAYGO, 304
- Field for Selection, 304
- Index, 304
- Initial Position, 304
- Name, 303, 304
- Order, 303
- Pointer Link, 303
- Post Action, 304
- Pre Action, 304
- Replication, 304
- Stored in the
  - BLOCK File, 304
  - FORM (#.403) File, 303
- Type of Block, 303
- ScreenMan Forms)
  - Post Action, 304
  - Pre Action, 304
- BLOCK (#.404) File, 286, 287, 303, 304, 305, 311, 312, 326, 331, 335, 347, 348, 475
- Block Viewer Screen
  - ScreenMan Form Editor, 323
- Blocks
  - Adding Blocks with ScreenMan Form Editor, 326
  - Header Blocks with ScreenMan Form Editor, 326
- Branching Logic
  - ScreenMan Forms
    - Field Properties, 309
- BROWSE^DDBR, 354
- Browser
  - APIs, 353
  - Calls
    - \$STEST^DDBRT, 362
    - BROWSE^DDBR, 354
    - CLOSE^DDBRZIS, 363
    - DOCLIST^DDBR, 360
    - EN^DDBR, 353
    - OPEN^DDBRZIS, 363
    - POST^DDBRZIS, 364
    - WP^DDBR, 357
- BUILD(S) (#9.6) Field, 397
- Builds Routines Containing
  - Data Dictionaries
    - DIFROM, 464
  - Data Values
    - DIFROM, 465
  - Security Access Codes
    - DIFROM, 465
- BULLETIN (#3.6) File, 473, 474
- BULLETINS, 463, 464, 466, 470, 474
- C**
  - C^%DTC, 120
  - Callable Routines
    - ScreenMan Forms, 313
  - Callout Boxes, xxx
  - Caption
    - ScreenMan Forms
      - Field Properties, 305, 307
  - Category
    - Cross-Reference
      - Classic Calls, 5
  - CHANGED^DIAUTL, 351
  - Check of Version Number
    - DIFROM, Running an INIT, 468
  - Checking the B Cross-reference or Zero Node, 471
  - CHK^DIE

Data Checker, 229

Choosing another Form

    ScreenMan Form Editor, 334

Classic Calls

    \$\$ROUSIZE^DILF, 67

    %XY^%RCR, 125

    ^%DTC, 120

    ^DIAC, 13

    ^DIC, 14

    ^DIE, 39

    ^DIEZ, 49

    ^DIK, 50

    ^DIKZ, 67

    ^DIM, 68

    ^DIOZ, 68

    ^DIPT, 84

    ^DIPZ, 84

    ^DIR, 91

    ^DIWP, 113

    ^DIWW, 115

    C^%DTC, 120

    COMMA^%DTC, 121

    Cross-Referenced by Category, 5

    D^DIQ, 86

    DIBT^DIPT, 84

    DO^DIC1, 31

    DQ^DICQ, 38

    DT^DICRW, 38

    DT^DIO2, 68

    DT^DIQ, 86

    DW^%DTC, 122

    EN^DDIOL, 9

    EN^DIB, 14

    EN^DID, 39

    EN^DIEZ, 50

    EN^DIK, 52

    EN^DIKZ, 67

    EN^DIPZ, 85

    EN^DIQ, 87

    EN^DIQ1, 88

    EN^DIS, 106

    EN^DIU2, 107

    EN^DIWE, 108

    EN1^DIK, 54, 55

    EN1^DIWF, 112

    EN2^DIWF, 113

    ENALL^DIK, 57, 58

    FILE^DICN, 35

    H^%DTC, 122

    HELP^%DTC, 123

    IX^DIC, 29

    IX^DIK, 60

    IX1^DIK, 61

    IXALL^DIK, 64, 65

    Listed

        Alphabetically, 8

    NOW^%DTC, 123

    S^%DTC, 123

    WAIT^DICD, 35

    X ^DD(DD), 8

    Y^DIQ, 87

    YMD^%DTC, 124

    YX^%DTC, 124

    Classic Calls (Alphabetic Order), 8

    Classic VA FileMan API, 4

    CLEAN^DILF

        Array and Variable Clean-up, 257

    Cleaning Up the Output Arrays

        DBS Calls, 134

    CLONE^DDS, 314

CLOSE^DDBRZIS, 363

COMMA^%DTC, 121

Command Summary

- ScreenMan Form Editor, 320

COMPILED ROUTINE (#.83) File, 69

Completes Building Routines of Package Components

- DIFROM, 466

Completes the Code that Runs the Init

- DIFROM, 466

Computed

- Dates
  - Advanced File Definition, 429
- Expressions
  - Advanced File Definition, 429
- Fields
  - ScreenMan Forms, 295
- Multiples
  - Advanced File Definition, 430
- Pointers
  - Advanced File Definition, 429

Contents of Arrays

- DBS Calls, 130
  - DIERR Array, 132
  - DIHELP Array, 130
  - DIMSG Array, 131

Conventions

- Documentation, xxix

Convert IENS to DA() Array Structure

- DA^DILF, 258

Converts Internal Value to External Format

- \$\$EXTERNAL^DILFD, 267

Create Export Template Option, 378

Creating

- DIALOG File Entries, 446

LANGUAGE File Entries, 450

Non-English Text in the DIALOG (#.84) File, 448

VA FileMan Functions, 452

- Function File Entries, 452
- Introduction, 452

CREIXN^DDMOD

- New-Style Cross-Reference Creator, 138

Cross-Reference A Field Option, 413, 438, 440, 443

Cross-references

- ^DIKZ, 67
- EN^DIK, 50, 52, 54, 55, 57, 58, 60, 61, 64, 65
- EN^DIKZ, 67
- EN1^DIK, 54, 55
- ENALL^DIK, 57, 58
- Global File Structure, 413, 417
- IX^DIK, 60
- IX1^DIK, 61
- IXALL^DIK, 64, 65
- Trigger, 440

**D**

D^DIQ, 86

DA^DILF

- Convert IENS to DA() Array Structure, 258

DAC

- Calls
  - \$\$CANDO^DIAC1, 369, 397

Data

- Editing DBS Calls
  - \$\$KEYVAL^DIE, 236
  - CHK^DIE, 229
  - FILE^DIE, 230
  - HELP^DIE, 234
  - RECALL^DILFD, 274

- UPDATE^DIE, 239
- VAL^DIE, 247
- VALS^DIE, 251
- WP^DIE, 255
- Export
  - EXPORT^DDMP, 378
- Filing
  - ScreenMan Forms, 299
- Import
  - FILE^DDMP, 372
- Length
  - ScreenMan Forms
    - Field Properties, 306
- Retrieval
  - DBS Calls
    - \$\$GET1^DIQ, 278
    - GETS^DIQ, 281
    - EN^DIQ1, 88
    - GETS^DIQ, 281
- Storage Conventions
  - Global File Structure, 409
- Validation
  - ScreenMan Forms
    - Field Properties, 308
    - ScreenMan Forms Form Properties, 300
- DATA (#.05) Field, 397
- Data Checker
  - CHK^DIE, 229
- DATA COMES WITH FILE, 456
- Data Coordinates
  - ScreenMan Forms
    - Field Properties, 307
- Data Dictionary
  - Audit
    - Global File Structure, 415
  - Data Dictionary Utilities Menu, xxxv
  - DBS Calls
    - \$\$FLDNUM^DILFD, 272
    - \$\$GET1^DID, 227
    - \$\$ROOT^DILFD, 275
    - \$\$VFIELD^DILFD, 276
    - \$\$VFILE^DILFD, 277
    - FIELD^DID, 221
    - FIELDLST^DID, 223
    - FILE^DID, 224
    - FILELST^DID, 226
    - PRD^DILFD, 273
  - Listings, xxxv
  - Modification DBS Calls
    - DELIX^DDMOD, 149
    - DELIXN^DDMOD, 152
    - FILESEC^DDMOD, 155
  - DATA DICTIONARY NUMBER (#.03) Field, 397
  - Data Retriever (Single Field)
    - \$\$GET1^DIQ, 278
  - Data Types
    - MUMPS Data Type
      - Advanced File Definition, 431
    - Set of Codes Data Type
      - Advanced File Definition, 431
  - Database Server (DBS)
    - API, 126
    - Calls
      - Alphabetic Order, 138
      - Cross-referenced by Category, 136
  - Date Converter
    - DT^DILF, 259
  - DATE DELETED (#2) Field, 147
  - Date/Time

- %DT, 115, 119
- Formats, Introduction
  - %DT, 115, 119
- Utilities
  - %DT, 115, 119
  - ^%DTC, 120
  - C^%DTC, 120
  - DT^DIO2, 68
  - DW^%DTC, 122
  - H^%DTC, 122
  - NOW^%DTC, 123
  - S^%DTC, 123
  - X ^DD(DD), 8
  - YMD^%DTC, 124
  - YX^%DTC, 124
- DBS Calls, 126
  - \$\$CREF^DILF, 257
  - \$\$EXTERNAL^DILFD, 267
  - \$\$EZBLD^DIALOG, 163
  - \$\$FIND1^DIC, 190
  - \$\$FLDNUM^DILFD, 272
  - \$\$GET1^DID, 227
  - \$\$GET1^DIQ, 278
  - \$\$HTML^DILF, 263
  - \$\$IENS^DILF, 264
  - \$\$KEYVAL^DIE, 236
  - \$\$OREF^DILF, 265
  - \$\$ROOT^DILFD, 275
  - \$\$VALUE1^DILF, 265
  - \$\$VFIELD^DILFD, 276
  - \$\$VFILE^DILFD, 277
  - BLD^DIALOG, 157
  - By Category, 136
  - CHK^DIE, 229
  - CLEAN^DILF, 257
  - Cleaning Up the Output Arrays, 134
  - Contents of Arrays, 130
    - DIERR Array, 132
    - DIHELP Array, 130
    - DIMSG Array, 131
  - CREIXN^DDMOD, 138
  - DA^DILF, 258
  - DELIX^DDMOD, 149
  - DELIXN^DDMOD, 152
  - Documentation Conventions, 129
  - DT^DILF, 259
  - Example of Call to VA FileMan DBS, 135
  - FDA
    - Format of Data Passed to and from VA FileMan, 128
  - FDA^DILF, 261
  - FIELD^DID, 221
  - FIELDLST^DID, 223
  - FILE^DID, 224
  - FILE^DIE, 230
  - FILELST^DID, 226
  - FILESEC^DDMOD, 155
  - FIND^DIC, 168
  - Format and Conventions, 126
  - GETS^DIQ, 281
  - HELP^DIE, 234
  - How Information Is Returned, 130
  - How the Database Server (DBS) communicates, 129
  - How to Use, 126
  - IENS
    - Identify Entries and Subentries, 127
  - Introduction, 126
  - LIST^DIC, 202
  - Listed

- Alphabetically, 138
- By Category, 138
- LOCK^DILF, 264
- MSG^DIALOG, 164
- Obtaining Formatted Text From The Arrays, 134
- Overview, 129
- PRD^DILFD, 273
- RECALL^DILFD, 274
- UPDATE^DIE, 239
- VAL^DIE, 247
- VALS^DIE, 251
- VALUES^DILF, 266
- WP^DIE, 255
- DD AUDIT (#.6) File, 149, 150
- DD Deletion
  - EN^DIU2, 107
- DD Field List Retriever
  - FIELDLST^DID, 223
- DD Field Retriever
  - FIELD^DID, 221
- DD File List Retriever
  - FILELST^DID, 226
- DD File Retriever
  - FILE^DID, 224
- DD Number
  - ScreenMan Forms
    - Block Properties, 304
- DDBR, 353
- DDS DELETE A FORM Option, 311
- DDS EDIT/CREATE A FORM Option, 310, 313, 318
- DDS PURGE UNUSED BLOCKS Option, 311, 312, 335
- DDS RUN A FORM Option, 310
- DDS SCREEN MENU, 310, 311, 312, 313, 318
- DDS Variable, 338
- DDSBK Variable
  - ScreenMan Forms, 298
- DDSSTACK Variable
  - ScreenMan Forms, 299
- DDXP CREATE EXPORT TEMPLATE Option, 378
- Default
  - ScreenMan Forms
    - Field Properties, 306
- DEFAULT PROTOCOL Field, 474
- Delete a Form Option, 311
- Delete a Form ScreenMan Forms Option, 311
- Deleting Screen Elements
  - ScreenMan Form Editor, 335
- DELIX^DDMOD
  - Traditional Cross-reference Delete, 149
- DELIXN^DDMOD
  - New-Style Index Delete, 152
- DESCRIPTION (#1) Field, 397
- Determining Install Status of
  - DDs and Data
    - DIFROM, Running an INIT, 468
  - Other Package Components
    - DIFROM, Running an INIT, 470
  - Security Codes
    - DIFROM, Running an INIT, 470
- Developer Tools, 401
- DEVICE (#3.5) file, 379
- DEVICE (#3.5) File, 73, 279, 364, 373
- DI DDU Menu, xxxv
- DIALOG (#.84) File, 130, 133, 157, 159, 163, 166, 445, 446, 447, 448
  - Creating DIALOG File Entries, 446
  - Creating Non-English Text in the DIALOG (#.84) File, 448

- Internationalization, 447
- Introduction, 445
- LANGUAGE (#.85) File, 449
  - Creating LANGUAGE File Entries, 450
  - Use of the LANGUAGE File, 449
- LANGUAGE File
  - Introduction, 449
  - Role of the VA FileMan DIALOG File in Internationalization, 447
  - Use of the DIALOG (#.84) File, 445
    - Internationalization, 447
  - User Messages, 445
- DIALOG Extractor
  - BLD^DIALOG, 157
- DIALOG Extractor (Single Line)
  - \$\$EZBLD^DIALOG, 163
- DIALOG(#.84) File, 158, 159, 163
- DIAUDIT PURGE DATA Option, 352
- DIBT^DIPT, 84
- Dictionary of Files, 410
- DIEDFILE Option, 23, 25, 437, 438
- DIEDIT Option, 14, 49, 442, 446, 448, 450, 452
- DIERR Array, 132
- DIFG Option, 216
- DIFQ Variables
  - DIFROM, 468
- DIFROM, 454
  - Exporting Data, 454
  - Importing Data, 467
  - Introduction, 454
  - Order Entry and DIFROM, 460
  - PACKAGE (#9.4) File, 455
  - PACKAGE File and DIFROM
    - ENVIRONMENT CHECK ROUTINE, 456
    - EXCLUDED NAME SPACE, 456
    - FILE, 456
    - NAME, 455
    - Other PACKAGE File Fields, 459
    - POST-INITIALIZATION ROUTINE, 456
    - PREFIX, 455
    - PRE-INIT AFTER USER COMMIT, 456
    - Template Multiples, 455
- Preparing To Run DIFROM, 454
- Running
  - DIFROM
    - Builds Routines Containing
      - Data Dictionaries, 464
      - Data Values, 465
      - Security Access Codes, 465
    - Completes Building Routines of Package Components, 466
    - Completes the Code that Runs the Init, 466
    - Entering Current Version Information, 463
    - Exporting File Security, 464
    - Gathers Miscellaneous Package Components, 464
    - Gathers Templates and Forms, 466
    - Identifying the Init Routines, 462
    - Including Other Package Components, 463
    - Including Templates (No Package File Entry), 463
    - Package Identification, 462
    - Preliminary Validations, 461
    - Specifications for Exported Files, 462
    - Specifying Routine Size, 464
    - Starting DIFROM, 461



- Steps, 461
- INIT
  - Check of Version Number, 468
  - Determining Install Status of
    - DDs and Data, 468
    - Other Package Components, 470
    - Security Codes, 470
  - DIFQ Variables, 468
  - General Processing, 473
  - Installing
    - Data, 471
    - Data Dictionaries, 471
    - Other Package Components, 472
  - Pre-init After User Commit Routine, 470
  - Preliminary Steps, 467
  - Recording the Install on the Target System, 475
  - Reindexing the Files, 472
  - Running Environment Check Routine, 468
  - Running the Post-Initialization Routine, 475
  - Starting the Update, 470
  - Steps, 467
- DIHELP Array, 130
- DIIDENT Option, 416
- DIINQUIRE Option, 87
- DIITRAN Option, 420, 433, 434
- DILIST Option, xxxv, 39, 404
- DIMODIFY Option, 49, 420, 426, 427, 428, 434, 439, 443
- DIMSG Array, 131
- DIOTHER Menu, 310, 313, 318
- DIPRINT Option, 85, 399
- DIRDEX Option, 57, 59, 65, 66, 140
- Disable
  - Disallow LAYGO
    - ScreenMan Forms
      - Field Properties, 308
    - Editing
      - ScreenMan Forms
        - Field Properties, 308
    - Navigation
      - ScreenMan Forms
        - Block Properties, 304
  - Disallow LAYGO
    - ScreenMan Forms Block Properties, 304
  - Disclaimers, xxix
    - Software, xxix
  - DISEARCH Option, 85, 106
  - Display
    - D^DIQ, 86
  - Display Group
    - ScreenMan Forms
      - Field Properties, 307
  - DISPLAY GROUP DEFAULT Field, 474
  - Displaying Multiples in Repeating Blocks
    - ScreenMan Forms, 289
  - Distribution Package
    - Global File Structure, 418
  - DITEMP Option, 399
  - DIUSER Menu, 313, 318, 336
  - DIUTILITY Menu, 23, 49, 57, 59, 65, 66, 140, 413, 420, 433, 437, 438, 440, 443
  - DIUTILITY Menus, 25
  - DIVERIFY Option, 436
  - DIXREF Option, 413, 438, 440, 443
  - DO^DIC1, 31
  - DOCLIST^DDBR, 360
  - Documentation

- Conventions, xxix
  - DBS Calls, 129
- Navigation, xxxi
- Symbols, xxix
- DQ^DICQ, 38
- DT^DICRW, 38
- DT^DILF
  - Date Converter, 259
- DT^DIO2, 68
- DT^DIQ, 86
- DW^%DTC, 122
- E**
- Edit File Option, 23, 25, 437, 438
- Edit/Create a Form Option, 310, 313, 318
- Edit/Create a Form ScreenMan Option, 310
- Editing
  - Cross-reference
    - Advanced File Definition, 438
  - ScreenMan Form Editor
    - Field Properties, 328
    - Block Properties, 330
    - Field Captions and Data Length, 330
    - Form Properties, 334
    - Page Properties, 332
    - Popup Page Coordinates, 333
- Editing, Adding, and Selecting
  - ScreenMan Form Editor, 321
- Editors
  - ScreenMan
    - Form Editor, 318
- Elements
  - Moving Screen Elements with ScreenMan Form Editor, 327
  - Selecting Screen Elements with ScreenMan Form Editor, 327

- EN^DDBR, 353
- EN^DDIOL
  - Message Loader, 9
- EN^DIAXU
  - Extract Data (Single Entry), 384
- EN^DIB, 14
- EN^DID, 39
- EN^DIEZ, 50
- EN^DIFGG
  - Filegram Generator, 395
- EN^DIK, 52
- EN^DIKZ, 67
- EN^DIPZ, 85
- EN^DIQ, 87
- EN^DIQ1, 88
- EN^DIS, 106
- EN^DIU2, 107
- EN^DIWE, 108
- EN1^DIK, 54, 55
- EN1^DIWF, 112
- EN2^DIWF, 113
- Enable/Disable Auditing
  - TURNON^DIAUTL, 349
- ENALL^DIK, 57, 58
- Enter or Edit File Entries Option, 14, 49, 442, 446, 448, 450, 452
- Entering Current Version Information
  - DIFROM, 463
- Entry Editing
  - ^DIE, 39
  - ^DIK, 50
  - EN^DIB, 14
  - EN^DIQ1, 88
  - EN^DIWE, 108
- ENVIRONMENT CHECK ROUTINE

PACKAGE File and DIFROM, 456	3021, 502
Error Codes, 477	3022, 502
101, 477	3023, 502
110, 478	304, 481
111, 478	305, 482
120, 478	306, 482
1300, 497	307, 482
1500, 498	308, 482
1501, 498	309, 483
1502, 498	310, 483
1503, 498	311, 483
1504, 499	312, 483
1610, 499	330, 484
1700, 499	348, 484
1701, 499	351, 484
1805, 500	352, 485
1810, 500	401, 485
1812, 500	402, 485
1820, 500	403, 485
1821, 501	404, 486
1822, 501	405, 486
1833, 501	406, 486
1850, 501	407, 486
1870, 502	408, 487
200, 479	409, 487
201, 479	420, 487
202, 479	501, 487
203, 479	502, 488
204, 480	505, 488
205, 480	510, 488
206, 480	520, 489
207, 480	525, 489
299, 481	537, 489
301, 481	601, 490
302, 481	602, 490

- 603, 490
- 630, 491
- 648, 491
- 701, 491
- 703, 492
- 710, 492
- 712, 493
- 714, 493
- 716, 493
- 720, 494
- 726, 494
- 730, 494
- 740, 495
- 742, 495
- 744, 495
- 746, 496
- 8090, 503
- 8095, 503
- 810, 496
- 820, 496
- 840, 497
- 842, 497
- 845, 497
- Introduction, 477
- Examples
  - Call to VA FileMan DBS, 135
- EXCLUDED NAME SPACE
  - PACKAGE File and DIFROM, 456
- Executable Caption
  - ScreenMan Forms
    - Field Properties, 305
- Executable Default
  - ScreenMan Forms
    - Field Properties, 306
- Executable Help, 130, 131
  - Advanced File Definition, 439
- EXecutable Help, 131
- Exiting, Quitting, Saving, and Obtaining Help
  - ScreenMan Form Editor, 323
- Export Tool API
  - Calls
    - EXPORT^DDMP, 378
- EXPORT^DDMP: Data Export, 378
- Exporting
  - Data
    - DIFROM, 454
  - File Security
    - DIFROM, 464
- Extract Data (Multiple Entries)
  - EXTRACT^DIAXU, 386
- Extract Data (Single Entry)
  - EN^DIAXU, 384
- Extract Tool, 384
  - Calls
    - EN^DIAXU, 384
    - EXTRACT^DIAXU, 386
  - Introduction, 384
- EXTRACT^DIAXU
  - Extract Data (Multiple Entries), 386
- F**
- FDA
  - Format of Data Passed to and from VA FileMan, 128
  - Loader
    - FDA^DILF, 261
  - Value Retriever (Single)
    - \$\$VALUE1^DILF, 265
  - Values Retriever
    - VALUES^DILF, 266
- FDA^DILF

- FDA
  - Loader, 261
- Features
  - ScreenMan Forms, 289
- Field
  - Definition 0-Node
    - Global File Structure, 418
  - Global Storage
    - Advanced File Definition, 427
  - Identifiers
    - Global File Structure, 416
  - Number Retriever
    - \$\$FLDNUM^DILFD, 272
  - Order
    - ScreenMan Forms
      - Field Properties, 305
  - Properties
    - ScreenMan Forms
      - Branching Logic,, 309
      - Caption, 305, 307
      - Data Coordinates, 307
      - Data Length, 306
      - Data Validation, 308
      - Default, 306
      - Disable Editing, 308
      - Disallow LAYGO, 308
      - Display Group, 307
      - Executable Caption, 305
      - Executable Default, 306
      - Field, 305
      - Field Order, 305
      - Field Type, 305
      - Post Action, 309
      - Post Action on Change, 309
      - Pre Action, 309
      - Required, 307
      - Right Justify, 307
      - Subpage Link, 308
      - Suppress Colon After Caption, 305
      - Unique Name, 305
    - ScreenMan Forms
      - Field Properties, 305
    - Type
      - ScreenMan Forms
        - Field Properties, 305
    - Verifier
      - \$\$VFIELD^DILFD, 276
- FIELD, 456
  - Field for Selection
    - ScreenMan Forms Block Properties, 304
  - FIELD NUMBER (#.04) Field, 397
  - FIELD^DID
    - DD Field Retriever, 221
  - FIELDLIST^DID
    - DD Field List Retriever, 223
  - Fields
    - Adding Fields with ScreenMan Form Editor, 326
    - ADDITIONAL FIELDS (#5.1), 370
    - ATTRIBUTE FUNCTION (#.04), 369
    - AVAILABLE FIELDS (#5), 370
    - BUILD(S) (#9.6), 397
    - DATA (#.05), 397
    - DATA DICTIONARY NUMBER (#.03), 397
    - DATE DELETED (#2), 147
    - DESCRIPTION (#1), 397
    - FIELD NUMBER (#.04), 397
    - ID NUMBER (#.001), 404
    - LAST UPDATED (#.07), 397

- LOOKUP TERM (#.02), 397
- NAME (#.01)
  - META DATA DICTIONARY (#.9)
    - File, 397
  - OBJECT NAME (#.06), 397
  - STOP CODE NUMBER (#8), 350
  - TYPE (#.03), 369
  - TYPE (#25), 397
  - Validator
    - VALS^DIE, 251
    - ZSAVE CODE (#2619), 496
- FILE, 456
  - PACKAGE File and DIFROM, 456
- FILE (#1) File, 456, 475
- File Characteristics Nodes
  - Global File Structure, 415
- File Entries (Data Storage)
  - Global File Structure, 411
- File Global Storage
  - Advanced File Definition, 426
- File Header
  - Global File Structure, 410
- File Root Resolver
  - \$\$ROOT^DILFD, 275
- File Verifier
  - \$\$VFILE^DILFD, 277
- FILE^DDMP: Data Import, 372
- FILE^DICN, 35
- FILE^DID
  - DD File Retriever, 224
- FILE^DIE
  - Filer, 230
- Filegram Generator
  - EN^DIFGG, 395
- Filegram Installer

- ^DIFG, 393
- Filegrams
  - API, 393
    - Calls
      - ^DIFG, 393
      - EN^DIFGG, 395
      - Introduction, 393
    - Option, 216
- FILELST^DID
  - DD File List Retriever, 226
- FileMan
  - Error Codes, 477
    - Introduction, 477
  - Functions
    - Creating, 452
- FileMan UTILITY Functions menu, 25
- Filer
  - FILE^DIE, 230
- Files
  - Advanced File Definition, 426
  - AUDIT (#1.1), 352, 378, 380, 438
  - BLOCK (#.404), 286, 287, 303, 304, 305, 311, 312, 326, 331, 335, 347, 348, 475
  - BULLETIN (#3.6), 473, 474
  - COMPILED ROUTINE (#.83), 69
  - DD AUDIT (#.6), 149, 150
  - DEVICE (#3.5), 73, 279, 364, 373, 379
  - DIALOG (#.84), 130, 133, 157, 159, 163, 166, 445, 446, 447, 448
  - DIALOG(#.84), 158, 159, 163
  - Entry in the Dictionary of Files
    - Global File Structure, 410
  - FILE (#1), 456, 475
  - FOREIGN FORMAT (#.44), 374
  - FOREIGN FORMAT (#.44), 375

FOREIGN FORMAT (#.44), 376  
FOREIGN FORMAT (#.44), 376  
FOREIGN FORMAT (#.44), 500  
FORM (#.403), 286, 300, 303, 304, 311, 331, 337, 475, 502  
FUNCTION (#.5), 452, 453, 475  
Global File Structure, 409  
HELP FRAME (#9.2), 473, 474  
HOSPITAL LOCATION (#44), 350  
IMPORT TEMPLATE (#.46), 502  
INDEX (#.11), 16, 77, 81, 138, 142, 145, 146, 148, 152, 172, 186, 188, 192, 199, 200, 413, 414, 417  
INPUT TEMPLATE (#.402), 473  
KEY (#.31), 36, 49, 172, 191, 237, 414  
LANGUAGE (#.85), 404, 447, 449, 450  
MAIL GROUP (#3.8), 464  
META DATA DICTIONARY (#.9), 397  
    BUILD(S) (#9.6) Field, 397  
    DATA (#.05) Field, 397  
    DATA DICTIONARY NUMBER (#.03) Field, 397  
    DESCRIPTION (#1) Field, 397  
    FIELD NUMBER (#.04) Field, 397  
    LAST UPDATED (#.07) Field, 397  
    LOOKUP TERM (#.02) Field, 397  
    NAME (#.01) Field, 397  
    OBJECT NAME (#.06) Field, 397  
    TYPE (#25) Field, 397  
MUMPS OPERATING SYSTEM (#.7), xxxii, 67, 461, 468, 471, 475, 496  
NEW PERSON (#200), 2, 18, 27, 43, 176, 184, 185, 195, 242, 314, 369, 462  
OPTION (#19), 473, 475  
OPTION (#19), 181, 182, 197, 208, 215, 216, 245, 460

ORDER PARAMETERS (#100.99), 460, 472, 474  
PACKAGE (#9.4), 454, 455, 459, 460, 462, 463, 464, 466, 468, 470, 472, 475  
PATIENT (#2), 378, 441, 443  
POLICY (1.6), 369, 370  
PRINT TEMPLATE (#.4), 84, 85, 393, 395, 396, 466  
PROTOCOL (#101), 460, 474  
SORT TEMPLATE (#.401), 84, 399  
STATE (#5), 175, 188, 194, 201, 208, 271, 272  
TERMINAL TYPE (#3.2), 279, 356, 363, 497

#### FILESEC^DDMOD

Set File Protection Security Codes, 155

#### FIND^DIC

Finder, 168

#### Finder

FIND^DIC, 168

Finder (Single Record)

\$\$FIND1^DIC, 190

FOREIGN FORMAT (#.44) File, 374, 375, 376, 500

FORM (#.403) File, 286, 300, 303, 304, 311, 331, 337, 475, 502

Form (ScreenMan Forms)

Layout: Forms and Pages, 286

Properties, 300

    Data Validation, 300

    Form Name, 300

    Post Action, 300

    Post Save, 300

    Pre Action, 300

    Record Selection Page, 300

    Title, 300

Structure, 286

## Form Doc Print

- ^DIWF, 111
- EN1^DIWF, 112
- EN2^DIWF, 113

## Form Editor

- ScreenMan, 318
  - Adding Blocks, 326
  - Adding Fields, 326
  - Adding Pages, 325
  - Adding, Selecting, and Editing, 321
  - Block Viewer Screen, 323
  - Choosing another Form, 334
  - Command Summary, 320
  - Deleting Screen Elements, 335
  - Editing Block Properties, 330
  - Editing Field Captions and Data Length, 330
  - Editing Field Properties, 328
  - Editing Form Properties, 334
  - Editing Page Properties, 332
  - Editing Pop-p Page Coordinates, 333
  - Exiting, Quitting, Saving, and Obtaining Help, 323
  - Going to Another Page, 324
  - Header Blocks, 326
  - Introduction, 318
  - Invoking, 318
  - Main Screen, 322
  - Moving Screen Elements, 321, 327
  - Navigating on the Form Editor Screens, 324
  - Navigating on the Main Screen and Block Viewer Screen, 320
  - Quick Page Navigation, 320
  - Reordering All Fields on a Block, 330
  - Selecting Screen Elements, 327

## Format and Conventions

- DBS Calls, 126

## Formatter

- ^DIWP, 113

## Form-Only Fields

- ScreenMan Forms, 290

## Forms and Pages

- ScreenMan Forms: Form Layout, 286

## Forms in ScreenMan, 286

## Forward Pointers

- Relational Navigation

- ScreenMan Forms, 292

## FUNCTION, 475

## FUNCTION (#.5) File, 452, 453, 475

## Function File Entries

- VA FileMan Functions (Creating), 452

## Functional Description, 1

## Functions

- Creating VA FileMan Functions, 452

## FUNCTIONS, 463, 464, 466, 470

## G

## Gathers

- Miscellaneous Package Components

- DIFROM, 464

- Templates and Forms

- DIFROM, 466

## General Processing

- DIFROM, Running an INIT, 473

## GETS^DIQ

- Data Retriever (Multiple Fields), 281

## Global File Structure, 409

- Attribute Dictionary, 415

- Cross-references, 413, 417

- Data Dictionary Audit, 415

- Data Storage Conventions, 409



- Distribution Package, 418
- Field Definition 0-Node, 418
- Field Identifiers, 416
- File Characteristics Nodes, 415
- File Entries (Data Storage), 411
- File Header, 410
- File's Entry in the Dictionary of Files, 410
- INDEX File, 413
- Introduction, 409
- KEY File, 414
- Other Field Definition Nodes, 421
- Package Revision Data, 418
- Post-Action, 415
- Reading the Attribute Dictionary: An Example, 424
- Screens, 417
- Special Lookup, 416
- Version Number, 418
- Write Identifiers, 416

Glossary, 504

Going to Another Page

- ScreenMan Form Editor, 324

**H**

- H^%DTC, 122

Header Blocks

- ScreenMan Form Editor, 326
- ScreenMan Forms Page Property, 301

Help

- At Prompts, xxxiv
- Online, xxxiv
- Question Marks, xxxiv

- HELP FRAME (#9.2) File, 473, 474
- HELP FRAMES, 463, 464, 466, 470, 474
- Help Messages (ScreenMan)
  - HLP^DDSUTL, 346
  - MSG^DDSUTL, 346
- HELP^%DTC, 123
- HELP^DIE
  - Helper, 234
- Helper
  - HELP^DIE, 234
- HLP^DDSUTL, 346
- Home Pages
  - Adobe Website, xxxv
  - VA Software Document Library (VDL) Website, xxxv
- HOSPITAL LOCATION (#44) File, 350
- How Information Is Returned
  - DBS Calls, 130
- How the Database Server (DBS) communicates, 129
- How to
  - Obtain Technical Information Online, xxxiv
  - Read the Attribute Dictionary: An Example Global File Structure, 424
  - Use the DBS calls, 126
  - Use this Manual, 27
- HTML Encoder/Decoder
  - \$\$HTML^DILF, 263
- HTML Manuals, xxviii

**I**

- ID NUMBER (#.001) Field, 404
- Identifier Option, 416
- Identifying the Init Routines
  - DIFROM, 462
- IENS
  - Identify Entries and Subentries, 127
  - Return from a DA() Array Structure
    - \$\$IENS^DILF, 264
- IMPORT TEMPLATE (#.46) File, 502

- Import Tool API, 372
  - Calls
    - FILE^DDMP, 372
  - Introduction, 372
- Importing Data
  - DIFROM, 467
- Including
  - Other Package Components
    - DIFROM, 463
  - Templates (No Package File Entry)
    - DIFROM, 463
- Index
  - ScreenMan Forms Block Properties, 304
- INDEX (#.11) File, 16, 77, 81, 138, 142, 145, 146, 148, 152, 172, 186, 188, 192, 199, 200, 413, 414, 417
  - Global File Structure, 413
- Initial Position
  - ScreenMan Forms Block Properties, 304
- INPUT Template, 475
- INPUT TEMPLATE (#.402) File, 473
- INPUT TEMPLATES, 470
- INPUT Transform
  - Advanced File Definition, 433
- Input Transform (Syntax) Option, 420, 433
- INPUT Transforms and the Verify Fields Option
  - Advanced File Definition, 436
- Inquiry to File Entries Option, 87
- Installing
  - Data
    - DIFROM, Running an INIT, 471
  - Data Dictionaries
    - DIFROM, Running an INIT, 471
  - Other Package Components
    - DIFROM, Running an INIT, 472

- Intended Audience, xxviii
- Internationalization
  - Creating Non-English Text in the DIALOG (#.84) File, 448
  - DIALOG (#.84) File, 447
  - LANGUAGE (#.85) File, 449
  - Role of the DIALOG (#.84) File, 447
  - Use of the DIALOG (#.84) File, 447
- Introduction, 1
  - Advanced File Definition, 426
  - DBS Calls, 126
  - DIALOG (#.84) File, 445
  - DIFROM, 454
  - Extract Tool, 384
  - Filegrams
    - API, 393
  - Global File Structure, 409
  - Import Tool API, 372
  - LANGUAGE (#.85) File, 449
  - ScreenMan Form Editor, 318
  - ScreenMan Forms, 286
  - Trigger Cross-references, 440
  - VA FileMan Functions
    - Creating, 452
- Invoke ScreenMan
  - ^DDS, 337
- Invoking the ScreenMan Form Editor, 318
- Is This a Pop-Up Page?
  - ScreenMan Forms Page Property, 301
- IX^DIC, 29
- IX^DIK, 60
- IX1^DIK, 61
- IXALL^DIK, 64, 65
- K**
- KEY (#.31) File, 36, 49, 172, 191, 237, 414

- Global File Structure, 414
- Key Validator
  - \$\$KEYVAL^DIE, 236
- L**
- LANGUAGE (#.85) File, 404, 447, 449, 450
  - Creating LANGUAGE File Entries, 450
  - Introduction, 449
  - Use of the LANGUAGE (#.85) File, 449
- LAST UPDATED (#.07) Field, 397
- LAST^DIAUTL, 350
- LAYGO
  - ScreenMan Forms Field Properties, 308
- Linking Pages of a Form
  - ScreenMan Forms, 287
- List File Attributes Option, xxxv, 39, 404
- LIST^DIC
  - Lister, 202
- Lister
  - LIST^DIC, 202
- Lock Global Reference
  - LOCK^DILF, 264
- LOCK^DILF
  - Lock Global Reference, 264
- Lookup
  - Adding Entries
    - ^DIAC, 13
    - ^DIC, 14
    - DQ^DICQ, 38
    - FILE^DICN, 35
    - IX^DIC, 29
  - DBS Calls
    - \$\$FIND1^DIC, 190
    - FIND^DIC, 168
    - LIST^DIC, 202
  - Special Lookup Programs

- Advanced File Definition, 437
- LOOKUP TERM (#.02) Field, 397
- Lower Right Coordinate
  - ScreenMan Forms Page Property, 301
- M**
- MAIL GROUP (#3.8) File, 464
- Main Screen
  - ScreenMan Form Editor, 322
- Major APIs, 4
- Manuals
  - In HTML, xxviii
  - Reference, xxxv
- MAY USER OVERRIDE DATA UPDATE, 456
- MAY USER OVERRIDE DD UPDATE, 456
- MENU Field, 474
- Menus
  - Data Dictionary Utilities, xxxv
  - DDS SCREEN MENU, 310, 311, 312, 313, 318
  - DI DDU, xxxv
  - DIOOTHER, 310, 313, 318
  - DIUSER, 313, 318, 336
  - DIUTILITY, 23, 25, 49, 57, 59, 65, 66, 140, 413, 420, 433, 437, 438, 440, 443
  - FileMan UTILITY Functions, 25
  - Other Options, 310, 313, 318
  - ScreenMan, 310, 311, 312, 313, 318
  - Utility Functions, 23, 49, 57, 59, 65, 66, 140, 413, 420, 433, 437, 438, 440, 443
  - VA FileMan, 313, 318, 336
- MERGE OR OVERWRITE SITE'S DATA, 456
- META DATA DICTIONARY (#.9) File, 397
  - BUILD(S) (#9.6) Field, 397
  - DATA (#.05) Field, 397

DATA DICTIONARY NUMBER (#.03) Field, 397

DESCRIPTION (#1) Field, 397

FIELD NUMBER (#.04) Field, 397

LAST UPDATED (#.07) Field, 397

LOOKUP TERM (#.02) Field, 397

NAME (#.01) Field, 397

OBJECT NAME (#.06) Field, 397

TYPE (#25) Field, 397

Modify File Attributes Option, 49, 420, 426, 427, 428, 434, 439, 443

Moving Screen Elements

- ScreenMan Form Editor, 321, 327

MSG^DDSUTL, 346

MSG^DIALOG

- Output Generator, 164

MUMPS Data Type

- Advanced File Definition, 431

MUMPS OPERATING SYSTEM (#.7) File, xxxii, 67, 461, 468, 471, 475, 496

**N**

Name

- ScreenMan Forms
  - Block Properties, 304
  - ScreenMan Forms Page Property, 301

NAME

- PACKAGE File and DIFROM, 455

NAME (#.01) Field

- META DATA DICTIONARY (#.9) File, 397

Navigating

- Form Editor Screens
  - ScreenMan Form Editor, 324
- On the Form Editor Screens
  - ScreenMan Form Editor, 324

Quick Page Navigation ScreenMan Form Editor, 320

ScreenMan Form Editor on the Main Screen and Block Viewer Screen, 320

Via DD Fields—Syntax for Pointer Link

- ScreenMan Forms, 293

Via Form Only Fields—Syntax for Pointer Link

- ScreenMan Forms, 294

NEW PERSON (#200) File, 2, 18, 27, 43, 176, 184, 185, 195, 242, 314, 369, 462

New-Style Cross-Reference Creator

- CREIXN^DDMOD, 138

New-Style Index Delete

- DELIXN^DDMOD, 152

Next Page

- ScreenMan Forms Page Property, 301

NOW^%DTC, 123

Number

- ScreenMan Forms Page Property, 301

**O**

OBJECT NAME (#.06) Field, 397

Obtaining Formatted Text From The Arrays

- DBS Calls, 134

Obtaining, Exiting, Saving, and Quitting Help

- ScreenMan Form Editor, 323

Online

- Documentation, xxxiv
- Technical Information, How to Obtain, xxxiv

OPEN^DDBRZIS, 363

OPTION (#19) File, 181, 182, 197, 208, 215, 216, 245, 460, 473, 475

Options

- Create Export Template, 378
- Cross-Reference A Field, 413, 438, 440, 443
- Data Dictionary Utilities, xxxv

DDS DELETE A FORM, 311  
 DDS EDIT/CREATE A FORM, 310, 313, 318  
 DDS PURGE UNUSED BLOCKS, 311, 312, 335  
 DDS RUN A FORM, 310  
 DDS SCREEN MENU, 310, 311, 312, 313, 318  
 DDXP CREATE EXPORT TEMPLATE, 378  
 Delete a Form, 311  
 DI DDU, xxxv  
 DIAUDIT PURGE DATA, 352  
 DIEDFILE, 23, 25, 437, 438  
 DIEDIT, 14, 49, 442, 446, 448, 450, 452  
 DIFG, 216  
 DIIDENT, 416  
 DIINQUIRE, 87  
 DIITRAN, 420, 433, 434  
 DILIST, xxxv, 39, 404  
 DIMODIFY, 49, 420, 426, 427, 428, 434, 439, 443  
 DIOTHER, 310, 313, 318  
 DIPRINT, 85, 399  
 DIRDEX, 57, 59, 65, 66, 140  
 DISEARCH, 85, 106  
 DITEMP, 399  
 DIUSER, 313, 318, 336  
 DIUTILITY, 23, 25, 49, 57, 59, 65, 66, 140, 413, 420, 433, 437, 438, 440, 443  
 DIVERIFY, 436  
 DIXREF, 413, 438, 440, 443  
 Edit File, 23, 25, 437, 438  
 Edit/Create a Form, 310, 313, 318  
 Enter or Edit File Entries, 14, 49, 442, 446, 448, 450, 452  
 Filegrams, 216  
 FileMan UTILITY Functions, 25  
 Identifier, 416  
 Input Transform (Syntax), 420, 433  
 Inquiry to File Entries, 87  
 List File Attributes, xxxv, 39, 404  
 Modify File Attributes, 49, 420, 426, 427, 428, 434, 439, 443  
 Other Options, 310, 313, 318  
 Print File Entries, 85, 399  
 Purge Data Audits option, 352  
 Purge Unused Blocks, 311, 312, 335  
 Re-Index File, 57, 59, 65, 66, 140  
 Run A Form, 310  
 ScreenMan, 310, 311, 312, 313, 318  
 ScreenMan Forms  
     Delete a Form, 311  
     Edit/Create a Form, 310  
     Purge Unused Blocks, 312  
     Run a Form, 310  
 Search File Entries, 85, 106  
 Template Edit, 399  
 Utility Functions, 23, 49, 57, 59, 65, 66, 140, 413, 420, 433, 437, 438, 440, 443  
 VA FileMan, 313, 318, 336  
 Verify Fields, 436  
     Advanced File Definition, 436  
 OPTIONS, 463, 464, 466, 470, 474  
 Order Entry and DIFROM, 460  
 ORDER PARAMETERS (#100.99) File, 460, 472, 474  
 Orientation, 27  
 Other  
     APIs, 349  
     Field Definition Nodes  
         Global File Structure, 421  
 PACKAGE File Fields

- PACKAGE File and DIFROM, 459
- Other Options Menu, 310, 313, 318
- Output Generator
  - MSG^DIALOG, 164
- OUTPUT Transform
  - Advanced File Definition, 436
- Overview
  - DBS Calls, 129
- P**
- PACKAGE (#9.4)File, 464
- PACKAGE (#9.4) File, 454, 455, 459, 460, 462, 463, 464, 466, 468, 470, 472, 475
  - DIFROM, 455
    - ENVIRONMENT CHECK ROUTINE, 456
    - EXCLUDED NAME SPACE, 456
    - FILE, 456
    - NAME, 455
    - Other PACKAGE File Fields, 459
    - POST-INITIALIZATION ROUTINE, 456
    - PREFIX, 455
    - PRE-INIT AFTER USER COMMIT, 456
    - Template Multiples, 455
- PACKAGE FILE ENTRIES, 474
- Package Identification
  - DIFROM, 462
- PACKAGE PARAMETERS, 474
- Package Revision Data
  - Global File Structure, 418
  - Initializer
    - PRD^DILFD, 273
- Page Coordinate
  - ScreenMan Forms Page Property, 301
- Pages

- Adding Blocks with ScreenMan Form Editor, 325
- ScreenMan Forms
  - Properties, 301
  - Header Block, 301
  - Is This a Pop-Up Page?, 301
  - Lower Right Coordinate, 301
  - Name, 301
  - Next Page, 301
  - Number, 301
  - Page Coordinate, 301
  - Parent Field, 302
  - Post Action, 302
  - Pre Action, 302
  - Previous Page, 301
- Parent Field
  - ScreenMan Forms Page Property, 302
- PATIENT (#2) File, 378, 441, 443
- Pointer Link
  - ScreenMan Forms Block Properties, 303
- POLICY (1.6) File, 369, 370
- Post Action
  - ScreenMan Forms
    - Block Properties, 304
    - Field Properties, 309
  - ScreenMan Forms Block Properties, 304
  - ScreenMan Forms Form Properties, 300
  - ScreenMan Forms Page Property, 302
- Post Save
  - ScreenMan Forms Form Properties, 300
- POST^DDBRZIS, 364
- Post-Action
  - Global File Structure, 415
- POST-INITIALIZATION ROUTINE
  - PACKAGE File and DIFROM, 456

- Post-Selection Action
  - Advanced File Definition, 437
- PRD^DILFD
  - Package Revision Data Initializer, 273
- Pre Action
  - ScreenMan Forms
    - Block Properties, 304
    - Field Properties, 309
    - ScreenMan Forms Block Properties, 304
    - ScreenMan Forms Form Properties, 300
    - ScreenMan Forms Page Property, 302
- PREFIX
  - PACKAGE File and DIFROM, 455
- PRE-INIT AFTER USER COMMIT
  - PACKAGE File and DIFROM, 456
- Pre-init After User Commit Routine
  - DIFROM, Running an INIT, 470
- Preliminary
  - Steps
    - DIFROM, Running an INIT, 467
  - Validations
    - DIFROM, 461
- Preparing To Run DIFROM, 454
- Previous Page
  - ScreenMan Forms Page Property, 301
- Print File Entries Option, 85, 399
- PRINT Template, 475
- PRINT TEMPLATE (#.4)File, 466
- PRINT TEMPLATE (#.4) File, 84, 85, 393, 395, 396
- PRINT TEMPLATES, 470
- PRINT^DDS, 316
- Printing
  - ^DIWF, 111
  - ^DIWP, 113
  - ^DIWW, 115
  - DT^DIQ, 86
  - EN^DIQ, 87
  - EN^DIS, 106
  - EN1^DIWF, 112
  - EN2^DIWF, 113
  - Y^DIQ, 87
- Programmer Access
  - ^DI, 401
- Programmer Mode Utilities
  - ^DDGF, 313
  - CLONE^DDS, 314
  - PRINT^DDS, 316
  - RESET^DDS, 317
  - ScreenMan Forms, 313
- Programmer Tools, 401
- Prompting/Messages
  - ^DIR, 91
  - EN^DDIOL, 9
  - HELP^%DTC, 123
  - WAIT^DICD, 35
- Properties
  - Block Coordinate
    - ScreenMan Forms, 303
  - Block Name
    - ScreenMan Forms, 303
  - Block Order
    - ScreenMan Forms, 303
  - Block Properties Stored in the BLOCK File
    - ScreenMan Forms, 304
  - Block Properties Stored in the FORM File
    - ScreenMan Forms, 303
  - Branching Logic
    - ScreenMan Forms, 309
  - Caption

ScreenMan Forms, 305, 307

Data Coordinates  
ScreenMan Forms, 307

Data Length  
ScreenMan Forms, 306

Data Validation  
ScreenMan Forms, 300, 308

DD Number  
ScreenMan Forms, 304

Default  
ScreenMan Forms, 306

Disable Editing  
ScreenMan Forms, 308

Disable Navigation  
ScreenMan Forms, 304

Disallow LAYGO  
ScreenMan Forms, 304, 308

Display Group  
ScreenMan Forms, 307

Editing Block Properties with ScreenMan Form Editor, 330

Editing Field Properties with ScreenMan Form Editor, 328

Editing Form Properties with ScreenMan Form Editor, 334

Editing Page Properties with ScreenMan Form Editor, 332

Executable Caption  
ScreenMan Forms, 305

Executable Default  
ScreenMan Forms, 306

Field  
ScreenMan Forms, 305

Field for Selection  
ScreenMan Forms, 304

Field Order  
ScreenMan Forms, 305

Field Type  
ScreenMan Forms, 305

Form Name  
ScreenMan Forms, 300

Header Blocks  
ScreenMan Forms, 301

Index  
ScreenMan Forms, 304

Initial Position  
ScreenMan Forms, 304

Is This a Pop-Up Page?  
ScreenMan Forms, 301

Lower Right Coordinate  
ScreenMan Forms, 301

Name  
ScreenMan Forms, 304

Next Page  
ScreenMan Forms, 301

Page Coordinate  
ScreenMan Forms, 301

Page Name  
ScreenMan Forms, 301

Page Number  
ScreenMan Forms, 301

Parent Field  
ScreenMan Forms, 302

Pointer Link  
ScreenMan Forms, 303

Post Action  
ScreenMan Forms, 300, 302, 304, 309

Post Action on Change  
ScreenMan Forms, 309

Post Save  
ScreenMan Forms, 300



- Pre Action
  - ScreenMan Forms, 300, 302, 304, 309
- Previous Page
  - ScreenMan Forms, 301
- Record Selection Page
  - ScreenMan Forms, 300
- Replication
  - ScreenMan Forms, 304
- Required
  - ScreenMan Forms, 307
- Right Justify
  - ScreenMan Forms, 307
- Subpage Link
  - ScreenMan Forms, 308
- Suppress Colon After Caption
  - ScreenMan Forms, 305
- Title
  - ScreenMan Forms, 300
- Type of Block
  - ScreenMan Forms, 303
- Unique Name
  - ScreenMan Forms, 305
- Properties of Form-Only Fields
  - ScreenMan Forms, 291
- PROTOCOL (#101) File, 460, 474
- PROTOCOL TO EXPORT Field, 474
- PS Anonymous Directories, xxxvi
- Purge Data Audits Option, 352
- Purge Unused Blocks Option, 311, 312, 335
- Purge Unused Blocks ScreenMan Forms Option, 312
- PUT^DDSVL, 341
- PUT^DDSVL, 345
- Q**
- Question Mark Help, xxxiv
- Quick Page Navigation
  - ScreenMan Form Editor, 320
- Quitting, Exiting, Saving, and Obtaining Help
  - ScreenMan Form Editor, 323
- R**
- Reader
  - ^DIR, 91
- Recall Record Number
  - RECALL^DILFD, 274
- RECALL^DILFD
  - Recall Record Number, 274
- Record Selection Page
  - ScreenMan Forms Form Properties, 300
- Recording the Install on the Target System
  - DIFROM, Running an INIT, 475
- Reference Materials, xxxv
- Referencing
  - Data Dictionary Fields
    - ScreenMan Forms, 295
  - Form-Only and Computed Fields
    - ScreenMan Forms, 296
- Refresh Screen (ScreenMan)
  - REFRESH^DDSUTL, 347
- REFRESH^DDSUTL, 347
- Re-Index File Option, 57, 59, 65, 66, 140
- Reindexing the Files
  - DIFROM, Running an INIT, 472
- Relational Navigation (ScreenMan Forms)
  - Backward Pointers, 295
  - Forward Pointers, 292
- Reordering All Fields on a Block
  - ScreenMan Form Editor, 330
- Replication
  - ScreenMan Forms Block Properties, 304
- REQ^DDSUTL, 347

- Required
  - ScreenMan Forms
    - Field Properties, 307
- RESET^DDS, 317
- Retrieve Audit History
  - CHANGED^DIAUTL, 351
- Retrieve Last Person Who Changed Data
  - LAST^DIAUTL, 350
- Retrieve/Stuff Fields (ScreenMan)
  - \$\$GET^DDSVVAL, 340
  - \$\$GET^DDSVVALF, 344
  - PUT^DDSVVAL, 341
  - PUT^DDSVVALF, 345
- Right Justify
  - ScreenMan Forms
    - Field Properties, 307
- Role of the VA FileMan DIALOG (#.84) File in Internationalization, 447
- Root Converter
  - Closed to Open Format
    - \$\$OREF^DILF, 265
  - Open to Closed Format
    - \$\$CREF^DILF, 257
- Run A Form Option, 310
- Run a Form ScreenMan Forms Option, 310
- Running
  - An INIT (Steps), 467
  - DIFROM (Steps), 461
  - Environment Check Routine
    - DIFROM, Running an INIT, 468
  - Post-Initialization Routine
    - DIFROM, Running an INIT, 475
- Run-Time Field Status (ScreenMan)
  - REQ^DDSUTL, 347
  - UNED^DDSUTL, 348

**S**

- S^%DTC, 123
- Screen Elements
  - Moving with ScreenMan Form Editor, 321
- SCREEN TEMPLATES, 466
- SCREEN TEMPLATES (FORMS), 470, 475
- SCREEN TO DETERMINE DD UPDATE, 456
- Screened Pointers and Set of Codes
  - Advanced File Definition, 431
- ScreenMan, 286
  - API, 337
    - Introduction, 337
  - Calls
    - \$\$GET^DDSVVAL, 340
    - \$\$GET^DDSVVALF, 344
    - ^DDS, 337
    - HLP^DDSUTL, 346
    - MSG^DDSUTL, 346
    - PUT^DDSVVAL, 341
    - PUT^DDSVVALF, 345
    - REFRESH^DDSUTL, 347
    - REQ^DDSUTL, 347
    - UNED^DDSUTL, 348
- Form Editor, 318
  - Adding Blocks, 326
  - Adding Fields, 326
  - Adding Pages, 325
  - Adding, Selecting, and Editing, 321
  - Block Viewer Screen, 323
  - Choosing another Form, 334
  - Command Summary, 320
  - Deleting Screen Elements, 335
  - Editing Block Properties, 330
  - Editing Field Captions and Data Length, 330

- Editing Field Properties, 328
- Editing Form Properties, 334
- Editing Page Properties, 332
- Editing Popup Page Coordinates, 333
- Exiting, Quitting, Saving, and Obtaining Help, 323
- Going to Another Page, 324
- Header Blocks, 326
- Introduction, 318
- Invoking, 318
- Main Screen, 322
- Moving Screen Elements, 321, 327
- Navigating on the Form Editor Screens, 324
- Navigating on the Main Screen and Block Viewer Screen, 320
- Quick Page Navigation, 320
- Reordering All Fields on a Block, 330
- Selecting Screen Elements, 327
- Forms, 286
  - Backward Pointers
  - Relational Navigation, 295
  - Block Properties, 303, 305
  - Callable Routines, 313
  - Computed Fields, 295
  - Data Filing, 299
  - DDSDR Variable, 298
  - DDSSTACK Variable, 299
  - Displaying Multiples in Repeating Blocks, 289
  - Features, 289
  - Form Layout: Forms and Pages, 286
  - Form Properties, 300
  - Form Name, 300
  - Form Structure, 286
  - Form-Only Fields, 290
  - Forward Pointers
  - Relational Navigation, 292
  - Introduction, 286
  - Linking Pages of a Form, 287
  - Navigating Via DD Fields—Syntax for Pointer Link, 293
  - Navigating Via Form Only Fields—Syntax for Pointer Link, 294
  - Options, 310
  - Delete a Form, 311
  - Edit/Create a Form, 310
  - Purge Unused Blocks, 312
  - Run a Form, 310
  - Page Properties, 301
  - Programmer Mode Utilities, 313
  - Properties
    - Block Coordinate, 303
    - Block Name, 303
    - Block Order, 303
    - Block Properties Stored in the BLOCK File, 304
    - Block Properties Stored in the FORM File, 303
    - Branching Logic, 309
    - Caption, 305, 307
    - Data Coordinates, 307
    - Data Length, 306
    - Data Validation, 300, 308
    - DD Number, 304
    - Default, 306
    - Disable Editing, 308
    - Disable Navigation, 304
    - Disallow LAYGO, 304, 308
    - Display Group, 307
    - Executable Caption, 305
    - Executable Default, 306

Field, 305

Field for Selection, 304

Field Order, 305

Field Type, 305

Header Block, 301

Index, 304

Initial Position, 304

Is This a Pop-Up Page?, 301

Lower Right Coordinate, 301

Name, 304

Next Page, 301

Page Coordinate, 301

Page Name, 301

Page Number, 301

Parent Field, 302

Pointer Link, 303

Post Action, 300, 302, 304, 309

Post Action on Change, 309

Post Save, 300

Pre Action, 300, 302, 304, 309

Previous Page, 301

Record Selection Page, 300

Replication, 304

Required, 307

Right Justify, 307

Subpage Link, 308

Suppress Colon After Caption, 305

Title, 300

Type of Block, 303

Unique Name, 305

Properties of Form-Only Fields, 291

Referencing

- Data Dictionary Fields, 295
- Form-Only and Computed Fields, 296
- Relational Navigation
  - Backward Pointers, 295
  - Forward Pointers, 292
  - Syntax for Pointer Link—Navigating Via
  - DD Fields, 293
  - Form Only Fields, 294
  - Variables Available in Repeating Blocks, 290

Help Messages Calls

- HLP^DDSUTL, 346
- MSG^DDSUTL, 346

Programmer Mode Utilities

- ^DDGF, 313
- CLONE^DDS, 314
- PRINT^DDS, 316
- RESET^DDS, 317

Refresh Screen Calls

- REFRESH^DDSUTL, 347

Retrieve/Stuff Fields Calls

- \$\$GET^DDSVAL, 340
- \$\$GET^DDSVALF, 344
- PUT^DDSVAL, 341
- PUT^DDSVALF, 345

Run-Time Field Status Calls

- REQ^DDSUTL, 347
- UNED^DDSUTL, 348

ScreenMan Calls

- \$\$GET^DDSVAL, 340
- \$\$GET^DDSVALF, 344
- ^DDS, 337
- HLP^DDSUTL, 346
- MSG^DDSUTL, 346
- PUT^DDSVAL, 341
- PUT^DDSVALF, 345
- REFRESH^DDSUTL, 347

- REQ^DDSUTL, 347
- UNED^DDSUTL, 348
- ScreenMan Forms
  - Block Properties that Apply Only to Repeating Blocks, 290
- ScreenMan Menu, 310, 311, 312, 313, 318
- Screens
  - Global File Structure, 417
- Search File Entries
  - EN^DIS, 106
- Search File Entries Option, 85, 106
- Security Keys
  - XUSCREENMAN, 318
- Security Keys
  - XUSCREENMAN, 310
- SECURITY KEYS, 463, 464, 466, 470, 475
- Selecting Screen Elements
  - ScreenMan Form Editor, 327
- Selecting, Adding, and Editing
  - ScreenMan Form Editor, 321
- Set File Protection Security Codes
  - FILESEC^DDMOD, 155
- Software Disclaimer, xxix
- SORT Template, 475
- SORT TEMPLATE (#.401) File, 84, 399
- SORT TEMPLATES, 470, 498
- Special Lookup
  - Global File Structure, 416
  - Programs
    - Advanced File Definition, 437
- Specifications for Exported Files
  - DIFROM, 462
- Specifying Routine Size
  - DIFROM, 464
- Standalone VA FileMan, 2

- Starting
  - DIFROM, 461
  - The Update
    - DIFROM, Running an INIT, 470
- STATE (#5) File, 175, 188, 194, 201, 208, 271, 272
- STOP CODE NUMBER (#8) Field, 350
- Storing Data
  - By Position within a Node
    - Advanced File Definition, 428
  - In a Global other than ^DIZ
    - Advanced File Definition, 426
- SUBORDINATE KEY Multiple Field, 475
- Subpage Link
  - ScreenMan Forms
    - Field Properties, 308
- Suppress Colon After Caption
  - ScreenMan Forms
    - Field Properties, 305
- Symbols
  - Found in the Documentation, xxix
- Syntax for Pointer Link—Navigating Via
  - DD Fields
    - ScreenMan Forms, 293
  - Form Only Fields
    - ScreenMan Forms, 294
- T**
- Template Compilation
  - ^DIEZ, 49
- Template Edit Option, 399
- Template Multiples
  - PACKAGE File and DIFROM, 455
- Templates
  - ^DIEZ, 49
  - ^DIOZ, 68

- ^DIPT, 84
- ^DIPZ, 84
- DIBT^DIPT, 84
- EN^DIEZ, 50
- EN^DIPZ, 85
- TEMPLATES, 466
- TERMINAL TYPE (#3.2) File, 279, 356, 363, 497
- Text Editing
  - EN^DIWE, 108
- Title
  - ScreenMan Forms Form Properties, 300
- Tools
  - Extract, 384
  - For Developers, 401
  - Import Tool API, 372
- Traditional Cross-reference Delete
  - DELIX^DDMOD, 149
- Transforms
  - INPUT Transform
    - Advanced File Definition, 433
  - OUTPUT Transform
    - Advanced File Definition, 436
- Triggers
  - Cross-references, 440
    - Different Files, 443
    - Introduction, 440
    - Same File, 441
  - Different Files
    - Cross-references, 443
  - Same File
    - Cross-references, 441
- TURNON^DIAUTL, 349
- TYPE (#.03) Field, 369
- TYPE (#25) Field, 397

- Type of Block
  - ScreenMan Forms Block Properties, 303
- U
- UNED^DDSUTL, 348
- Unique Name
  - ScreenMan Forms
    - Field Properties, 305
- UPDATE THE DATA DICTIONARY, 456
- UPDATE^DIE
  - Updater, 239
- Updater
  - UPDATE^DIE, 239
- URLs
  - Adobe Website, xxxv
  - VA Software Document Library (VDL) Website, xxxv
- Use of the
  - DIALOG (#.84) File, 445
    - Internationalization, 447
  - LANGUAGE (#.85) File, 449
- User Dialogue DBS Calls
  - \$\$EZBLD^DIALOG, 163
  - BLD^DIALOG, 157
  - MSG^DIALOG, 164
- User Messages
  - DIALOG (#.84) File, 445
- Using
  - Identifiers to Verify a Match, 472
  - Internal Entry Number to Verify a Match, 471
- UTC
  - Calls
    - \$\$UTC^DIUTC, 365
- Utilities
  - \$\$ROUSIZE^DILF, 67

- %XY^%RCR, 125
- ^DIM, 68
- COMMA^%DTC, 121
- DO^DIC1, 31
- DT^DICRW, 38
- EN^DID, 39
- EN^DIU2, 107
- Utility DBS Calls
  - \$\$CREF^DILF, 257
  - \$\$EXTERNAL^DILFD, 267
  - \$\$HTML^DILF, 263
  - \$\$IENS^DILF, 264
  - \$\$OREF^DILF, 265
  - \$\$VALUE1^DILF, 265
  - CLEAN^DILF, 257
  - DA^DILF, 258
  - DT^DILF, 259
  - FDA^DILF, 261
  - LOCK^DILF, 264
  - VALUES^DILF, 266
- Utility Functions Menu, 23, 49, 57, 59, 65, 66, 140, 413, 420, 433, 437, 438, 440, 443
- V**
- VA FileMan
  - Error Codes, 477
    - Introduction, 477
  - Functional Description, 1
  - Functions (Creating), 452
    - Function File Entries, 452
    - Introduction, 452
  - Standalone, 2
- VA FileMan Menu, 313, 318, 336
- VA Software Document Library (VDL)
  - Website, xxxv
- VAL^DIE
  - Validator, 247
- Validator
  - VAL^DIE, 247
- VALS^DIE
  - Fields Validator, 251
- VALUES^DILF
  - FDA
    - Values Retriever, 266
- Variables Available in Repeating Blocks
  - ScreenMan Forms, 290
- Verify Fields Option, 436
- Version Number
  - Global File Structure, 418
- W**
- WAIT^DICD, 35
- Websites
  - Adobe Website, xxxv
  - VA Software Document Library (VDL), xxxv
- Word-processing Filer
  - WP^DIE, 255
- Word-processing Print
  - ^DIWP, 113
- WP Print
  - ^DIWP, 113
  - ^DIWW, 115
- WP^DDBR, 357
- WP^DIE
  - Word-processing Filer, 255
- Write Identifiers
  - Global File Structure, 416
- X**
- X ^DD(DD), 8
- XUSCREENMAN Security Key, 310, 318

## **Y**

Y^DIQ, 87

YMD^%DTC, 124

YX^%DTC, 124

## **Z**

Zero Node

Checking, 471

ZSAVE CODE (#2619) Field, 496